
RsAreg800

Release 5.30.47.7

Rohde & Schwarz

Mar 25, 2024

CONTENTS:

| | | |
|----------|-------------------------------------|-----------|
| 1 | Revision History | 3 |
| 1.1 | RsAreg800 | 3 |
| 1.1.1 | Version history | 3 |
| 2 | Getting Started | 5 |
| 2.1 | Introduction | 5 |
| 2.2 | Installation | 6 |
| 2.3 | Finding Available Instruments | 7 |
| 2.4 | Initiating Instrument Session | 8 |
| 2.5 | Plain SCPI Communication | 11 |
| 2.6 | Error Checking | 13 |
| 2.7 | Exception Handling | 14 |
| 2.8 | Transferring Files | 15 |
| 2.9 | Writing Binary Data | 16 |
| 2.10 | Transferring Big Data with Progress | 16 |
| 2.11 | Multithreading | 18 |
| 2.12 | Logging | 21 |
| 3 | Enums | 25 |
| 3.1 | AregAttRcsKeepConst | 25 |
| 3.2 | AregCableCorrSour | 25 |
| 3.3 | AregCconfigBw | 25 |
| 3.4 | AregCconfigOptMode | 25 |
| 3.5 | AregCconfigSystAlign | 26 |
| 3.6 | AregChanMappingGui | 26 |
| 3.7 | AregChanMappingSensor | 26 |
| 3.8 | AregDopplerUnit | 26 |
| 3.9 | AregDynLoggLevel | 27 |
| 3.10 | AregFconfUseCustAntAreg800 | 27 |
| 3.11 | AregFeQatConnMode | 27 |
| 3.12 | AregFeQatMode | 27 |
| 3.13 | AregFeQatOrientation | 27 |
| 3.14 | AregFeType | 28 |
| 3.15 | AregHilUpdateMode | 28 |
| 3.16 | AregMeasPort | 28 |
| 3.17 | AregMultiInstCnctStatus | 28 |
| 3.18 | AregMultiInstMode | 28 |
| 3.19 | AregObjMarkSource | 29 |
| 3.20 | AregPIEd | 29 |
| 3.21 | AregPowSens | 29 |

| | | |
|------|---------------------------|----|
| 3.22 | AregRadarPowIndicator | 29 |
| 3.23 | AregSetupTimeBase | 29 |
| 3.24 | ByteOrder | 30 |
| 3.25 | CalDataMode | 30 |
| 3.26 | CalDataUpdate | 30 |
| 3.27 | Colour | 30 |
| 3.28 | ConnDirection | 30 |
| 3.29 | CustAntFormat | 31 |
| 3.30 | DevExpFormat | 31 |
| 3.31 | DispKeybLockMode | 31 |
| 3.32 | ErFpowSensMapping | 31 |
| 3.33 | ErFpowSensSourceAreg | 31 |
| 3.34 | FormData | 32 |
| 3.35 | FormStatReg | 32 |
| 3.36 | FrontPanelLayout | 32 |
| 3.37 | HardCopyImageFormat | 32 |
| 3.38 | HardCopyRegion | 32 |
| 3.39 | HilDataReceive | 33 |
| 3.40 | IecDevId | 33 |
| 3.41 | IecTermMode | 33 |
| 3.42 | ImpG50G1KcoerceG10K | 33 |
| 3.43 | InclExcl | 33 |
| 3.44 | KbLayout | 34 |
| 3.45 | NetMode | 34 |
| 3.46 | OsetupBw | 34 |
| 3.47 | OsetupConfiguration | 34 |
| 3.48 | OsetupDataSource | 34 |
| 3.49 | OsetupHilProtocol | 35 |
| 3.50 | OsetupMode | 35 |
| 3.51 | OsetupObjRef | 35 |
| 3.52 | OutpConnGlbSignalAreg800A | 35 |
| 3.53 | Parity | 35 |
| 3.54 | PixelTestPredefined | 36 |
| 3.55 | PowSensDisplayPriority | 36 |
| 3.56 | PowSensFiltType | 36 |
| 3.57 | RecScpiCmdMode | 36 |
| 3.58 | RoscBandWidtExt | 36 |
| 3.59 | RoscFreqExtAreg800A | 37 |
| 3.60 | RoscOutpFreqModeSmbb | 37 |
| 3.61 | RoscSourSetup | 37 |
| 3.62 | Rs232BdRate | 37 |
| 3.63 | Rs232StopBits | 37 |
| 3.64 | ScenarioReplyMode | 38 |
| 3.65 | ScenarioStatus | 38 |
| 3.66 | SelftLev | 38 |
| 3.67 | SelftLevWrite | 38 |
| 3.68 | SlopeType | 38 |
| 3.69 | StateExtended | 39 |
| 3.70 | Test | 39 |
| 3.71 | TestCalSelected | 39 |
| 3.72 | TimeProtocolWithGptp | 39 |
| 3.73 | UnitAngle | 39 |
| 3.74 | UnitAngleAreg | 40 |
| 3.75 | UnitLengthAreg | 40 |

| | | |
|-------------|--------------------------------|-----------|
| 3.76 | UnitPower | 40 |
| 3.77 | UnitPowSens | 40 |
| 3.78 | UnitRcsAreg | 40 |
| 3.79 | UnitShiftAreg | 41 |
| 3.80 | UnitSpeed | 41 |
| 3.81 | UnitSpeedAreg | 41 |
| 3.82 | UpdPolicyMode | 41 |
| 4 | RepCaps | 43 |
| 4.1 | HwInstance (Global) | 43 |
| 4.2 | BitNumberNull | 43 |
| 4.3 | Channel | 43 |
| 4.4 | ChannelNull | 44 |
| 4.5 | Connector | 44 |
| 4.6 | Index | 44 |
| 4.7 | Level | 45 |
| 4.8 | MappingChannel | 45 |
| 4.9 | ObjectIx | 45 |
| 4.10 | QatFrontent | 45 |
| 4.11 | RxIndex | 46 |
| 4.12 | Sensor | 46 |
| 4.13 | Subchannel | 46 |
| 4.14 | TrxFrontent | 47 |
| 4.15 | TxIndexNull | 47 |
| 4.16 | UserIx | 47 |
| 5 | Examples | 49 |
| 6 | RsAreg800 API Structure | 51 |
| 6.1 | Calibration | 54 |
| 6.1.1 | All | 55 |
| 6.1.1.1 | Measure | 56 |
| 6.1.2 | Data | 56 |
| 6.1.2.1 | Factory | 57 |
| 6.1.2.2 | Update | 57 |
| 6.1.2.2.1 | Level | 58 |
| 6.1.2.2.1.1 | Force | 58 |
| 6.1.3 | Delay | 59 |
| 6.1.3.1 | Shutdown | 60 |
| 6.1.4 | Frequency | 60 |
| 6.1.5 | Level | 61 |
| 6.1.5.1 | Attenuator | 61 |
| 6.1.6 | Roscillator | 62 |
| 6.1.6.1 | Data | 62 |
| 6.1.6.2 | Store | 63 |
| 6.1.7 | Selected | 64 |
| 6.1.7.1 | Measure | 64 |
| 6.1.8 | Tselected | 64 |
| 6.2 | Device | 65 |
| 6.2.1 | Settings | 66 |
| 6.2.1.1 | Backup | 66 |
| 6.2.1.2 | Restore | 67 |
| 6.3 | Diagnostic | 67 |
| 6.3.1 | BgInfo | 68 |

| | | |
|-------------|-----------------------------|-----|
| 6.3.2 | Debug | 68 |
| 6.3.2.1 | Page | 69 |
| 6.3.3 | Eeprom<Channel> | 70 |
| 6.3.3.1 | Bidentifier | 70 |
| 6.3.3.1.1 | Catalog | 71 |
| 6.3.3.2 | Customize | 71 |
| 6.3.3.3 | Data | 72 |
| 6.3.3.3.1 | Points | 72 |
| 6.3.4 | Info | 73 |
| 6.3.4.1 | Otime | 73 |
| 6.3.4.2 | PoCount | 74 |
| 6.3.5 | Measure | 74 |
| 6.3.5.1 | Point | 75 |
| 6.3.6 | Point | 75 |
| 6.3.6.1 | Configuration | 76 |
| 6.3.7 | Service | 77 |
| 6.4 | Display | 78 |
| 6.4.1 | Annotation | 79 |
| 6.4.2 | Button | 79 |
| 6.4.3 | Dialog | 80 |
| 6.4.4 | Psave | 81 |
| 6.4.5 | Touch | 82 |
| 6.4.5.1 | Time | 83 |
| 6.4.6 | Ukey | 83 |
| 6.4.6.1 | Add | 84 |
| 6.4.7 | Update | 84 |
| 6.5 | FormatPy | 85 |
| 6.6 | Fpanel | 87 |
| 6.6.1 | Keyboard | 87 |
| 6.7 | HardCopy | 88 |
| 6.7.1 | Device | 89 |
| 6.7.2 | Execute | 89 |
| 6.7.3 | File | 90 |
| 6.7.3.1 | Name | 90 |
| 6.7.3.1.1 | Auto | 91 |
| 6.7.3.1.1.1 | Directory | 92 |
| 6.7.3.1.1.2 | File | 93 |
| 6.7.3.1.1.3 | Day | 94 |
| 6.7.3.1.1.4 | Month | 94 |
| 6.7.3.1.1.5 | Prefix | 95 |
| 6.7.3.1.1.6 | Year | 96 |
| 6.7.4 | Image | 96 |
| 6.8 | Initiate<Channel> | 97 |
| 6.8.1 | Power | 97 |
| 6.8.1.1 | Continuous | 98 |
| 6.9 | Kboard | 99 |
| 6.10 | MassMemory | 99 |
| 6.10.1 | Catalog | 102 |
| 6.10.1.1 | Length | 103 |
| 6.10.2 | Dcatalog | 103 |
| 6.10.2.1 | Length | 104 |
| 6.10.3 | Load | 104 |
| 6.10.3.1 | State | 105 |
| 6.10.4 | Store | 105 |

| | | |
|--------------|------------------|-----|
| 6.10.4.1 | State | 105 |
| 6.11 | Memory | 106 |
| 6.12 | Output | 106 |
| 6.12.1 | User<UserIx> | 107 |
| 6.12.1.1 | Direction | 107 |
| 6.12.1.2 | Signal | 108 |
| 6.13 | Read<Channel> | 109 |
| 6.13.1 | Power | 109 |
| 6.14 | Sense<Channel> | 110 |
| 6.14.1 | Power | 110 |
| 6.14.1.1 | Aperture | 110 |
| 6.14.1.1.1 | Default | 111 |
| 6.14.1.1.1.1 | State | 111 |
| 6.14.1.1.2 | Time | 112 |
| 6.14.1.2 | Correction | 112 |
| 6.14.1.2.1 | SpDevice | 113 |
| 6.14.1.2.1.1 | ListPy | 113 |
| 6.14.1.2.1.2 | Select | 113 |
| 6.14.1.2.1.3 | State | 114 |
| 6.14.1.3 | Direct | 115 |
| 6.14.1.4 | Display | 115 |
| 6.14.1.4.1 | Permanent | 116 |
| 6.14.1.4.1.1 | Priority | 116 |
| 6.14.1.4.1.2 | State | 117 |
| 6.14.1.5 | FilterPy | 117 |
| 6.14.1.5.1 | Length | 118 |
| 6.14.1.5.1.1 | Auto | 118 |
| 6.14.1.5.1.2 | User | 119 |
| 6.14.1.5.2 | NsRatio | 120 |
| 6.14.1.5.2.1 | Mtime | 121 |
| 6.14.1.5.3 | Sonce | 121 |
| 6.14.1.5.4 | TypePy | 122 |
| 6.14.1.6 | Frequency | 123 |
| 6.14.1.7 | Logging | 124 |
| 6.14.1.7.1 | State | 124 |
| 6.14.1.8 | Offset | 125 |
| 6.14.1.8.1 | State | 126 |
| 6.14.1.9 | Snumber | 126 |
| 6.14.1.10 | Source | 127 |
| 6.14.1.11 | Status | 128 |
| 6.14.1.11.1 | Device | 128 |
| 6.14.1.12 | Sversion | 128 |
| 6.14.1.13 | TypePy | 129 |
| 6.14.1.14 | Zero | 129 |
| 6.14.2 | Unit | 130 |
| 6.14.2.1 | Power | 130 |
| 6.15 | Slist | 131 |
| 6.15.1 | Clear | 132 |
| 6.15.1.1 | Lan | 132 |
| 6.15.1.2 | Usb | 133 |
| 6.15.2 | Element<Channel> | 133 |
| 6.15.2.1 | Mapping | 134 |
| 6.15.3 | Scan | 134 |
| 6.15.3.1 | Usensor | 135 |

| | | |
|---------------|----------------------|-----|
| 6.15.4 | Sensor | 136 |
| 6.15.4.1 | Map | 136 |
| 6.16 | Source | 136 |
| 6.16.1 | AreGenerator | 137 |
| 6.16.1.1 | Channel | 137 |
| 6.16.1.1.1 | Condition | 139 |
| 6.16.1.1.2 | InputPy | 140 |
| 6.16.1.1.3 | Level | 141 |
| 6.16.1.1.4 | Optimization | 141 |
| 6.16.1.1.5 | Output | 142 |
| 6.16.1.1.6 | System | 143 |
| 6.16.1.2 | Dlogging | 144 |
| 6.16.1.3 | Frontend | 146 |
| 6.16.1.3.1 | Antenna | 146 |
| 6.16.1.3.1.1 | Custom | 147 |
| 6.16.1.3.1.2 | ImportPy | 147 |
| 6.16.1.3.1.3 | Predefined | 147 |
| 6.16.1.3.2 | Cfe<Channel> | 148 |
| 6.16.1.3.2.1 | Add | 148 |
| 6.16.1.3.2.2 | Alias | 149 |
| 6.16.1.3.2.3 | Antenna | 149 |
| 6.16.1.3.2.4 | Custom | 150 |
| 6.16.1.3.2.5 | Flist | 150 |
| 6.16.1.3.2.6 | Row<Index> | 151 |
| 6.16.1.3.2.7 | Fpoints | 152 |
| 6.16.1.3.2.8 | ImportPy | 153 |
| 6.16.1.3.2.9 | Predefined | 154 |
| 6.16.1.3.2.10 | Rx<RxIndex> | 154 |
| 6.16.1.3.2.11 | Glist | 155 |
| 6.16.1.3.2.12 | Row<Index> | 156 |
| 6.16.1.3.2.13 | Tx<TxIndexNull> | 157 |
| 6.16.1.3.2.14 | Glist | 158 |
| 6.16.1.3.2.15 | Row<Index> | 159 |
| 6.16.1.3.2.16 | Ats | 160 |
| 6.16.1.3.2.17 | CableCorr | 161 |
| 6.16.1.3.2.18 | Connector<Connector> | 161 |
| 6.16.1.3.2.19 | Rx<RxIndex> | 162 |
| 6.16.1.3.2.20 | Mode | 162 |
| 6.16.1.3.2.21 | User | 164 |
| 6.16.1.3.2.22 | Attenuation | 164 |
| 6.16.1.3.2.23 | Delay | 165 |
| 6.16.1.3.2.24 | File | 166 |
| 6.16.1.3.2.25 | Tx<TxIndexNull> | 167 |
| 6.16.1.3.2.26 | Mode | 168 |
| 6.16.1.3.2.27 | User | 169 |
| 6.16.1.3.2.28 | Attenuation | 169 |
| 6.16.1.3.2.29 | Delay | 170 |
| 6.16.1.3.2.30 | File | 171 |
| 6.16.1.3.2.31 | Center | 173 |
| 6.16.1.3.2.32 | Id | 174 |
| 6.16.1.3.2.33 | Rmv | 174 |
| 6.16.1.3.2.34 | Rts | 175 |
| 6.16.1.3.2.35 | Rx<RxIndex> | 175 |
| 6.16.1.3.2.36 | Efrontend | 176 |

| | | |
|---------------|--------------------------------|-----|
| 6.16.1.3.2.37 | Ota | 177 |
| 6.16.1.3.2.38 | Offset | 177 |
| 6.16.1.3.2.39 | Tx<TxIndexNull> | 178 |
| 6.16.1.3.2.40 | Efrontend | 178 |
| 6.16.1.3.2.41 | Ota | 179 |
| 6.16.1.3.2.42 | Offset | 179 |
| 6.16.1.3.2.43 | TypePy | 180 |
| 6.16.1.3.3 | Fe<Channel> | 181 |
| 6.16.1.3.3.1 | Add | 181 |
| 6.16.1.3.3.2 | Alias | 181 |
| 6.16.1.3.3.3 | Antenna | 182 |
| 6.16.1.3.3.4 | Custom | 182 |
| 6.16.1.3.3.5 | Flist | 183 |
| 6.16.1.3.3.6 | Row<Index> | 184 |
| 6.16.1.3.3.7 | Fpoints | 185 |
| 6.16.1.3.3.8 | ImportPy | 186 |
| 6.16.1.3.3.9 | Predefined | 186 |
| 6.16.1.3.3.10 | Rx<RxIndex> | 187 |
| 6.16.1.3.3.11 | Glist | 187 |
| 6.16.1.3.3.12 | Row<Index> | 188 |
| 6.16.1.3.3.13 | Tx<TxIndexNull> | 190 |
| 6.16.1.3.3.14 | Glist | 190 |
| 6.16.1.3.3.15 | Row<Index> | 191 |
| 6.16.1.3.3.16 | Ats | 192 |
| 6.16.1.3.3.17 | Bw | 193 |
| 6.16.1.3.3.18 | CableCorr | 194 |
| 6.16.1.3.3.19 | Connector<Connector> | 194 |
| 6.16.1.3.3.20 | Rx<RxIndex> | 195 |
| 6.16.1.3.3.21 | Mode | 195 |
| 6.16.1.3.3.22 | User | 197 |
| 6.16.1.3.3.23 | Attenuation | 197 |
| 6.16.1.3.3.24 | Delay | 198 |
| 6.16.1.3.3.25 | File | 199 |
| 6.16.1.3.3.26 | Tx<TxIndexNull> | 200 |
| 6.16.1.3.3.27 | Mode | 201 |
| 6.16.1.3.3.28 | User | 202 |
| 6.16.1.3.3.29 | Attenuation | 202 |
| 6.16.1.3.3.30 | Delay | 203 |
| 6.16.1.3.3.31 | File | 204 |
| 6.16.1.3.3.32 | Center | 205 |
| 6.16.1.3.3.33 | Connect | 206 |
| 6.16.1.3.3.34 | Disconnect | 206 |
| 6.16.1.3.3.35 | Id | 207 |
| 6.16.1.3.3.36 | Rmv | 207 |
| 6.16.1.3.3.37 | Rts | 208 |
| 6.16.1.3.3.38 | Rx<RxIndex> | 209 |
| 6.16.1.3.3.39 | Efrontend | 209 |
| 6.16.1.3.3.40 | Ota | 210 |
| 6.16.1.3.3.41 | Offset | 210 |
| 6.16.1.3.3.42 | Status | 211 |
| 6.16.1.3.3.43 | Tx<TxIndexNull> | 211 |
| 6.16.1.3.3.44 | Efrontend | 212 |
| 6.16.1.3.3.45 | Ota | 213 |
| 6.16.1.3.3.46 | Offset | 213 |

| | | |
|---------------|----------------------|-----|
| 6.16.1.3.3.47 | TypePy | 214 |
| 6.16.1.3.4 | Last | 214 |
| 6.16.1.3.4.1 | Fe<ChannelNull> | 215 |
| 6.16.1.3.4.2 | Qat<QatFrontent> | 216 |
| 6.16.1.3.5 | Qat<QatFrontent> | 216 |
| 6.16.1.3.5.1 | Add | 217 |
| 6.16.1.3.5.2 | Alias | 217 |
| 6.16.1.3.5.3 | Ats | 217 |
| 6.16.1.3.5.4 | Bw | 217 |
| 6.16.1.3.5.5 | CableCorr | 217 |
| 6.16.1.3.5.6 | Connector<Connector> | 218 |
| 6.16.1.3.5.7 | Rx<RxIndex> | 218 |
| 6.16.1.3.5.8 | Mode | 218 |
| 6.16.1.3.5.9 | User | 219 |
| 6.16.1.3.5.10 | Attenuation | 219 |
| 6.16.1.3.5.11 | Delay | 219 |
| 6.16.1.3.5.12 | File | 219 |
| 6.16.1.3.5.13 | Tx<TxIndexNull> | 219 |
| 6.16.1.3.5.14 | Mode | 220 |
| 6.16.1.3.5.15 | User | 220 |
| 6.16.1.3.5.16 | Attenuation | 220 |
| 6.16.1.3.5.17 | Delay | 220 |
| 6.16.1.3.5.18 | File | 220 |
| 6.16.1.3.5.19 | Center | 221 |
| 6.16.1.3.5.20 | Channels | 221 |
| 6.16.1.3.5.21 | Connect | 221 |
| 6.16.1.3.5.22 | Disconnect | 221 |
| 6.16.1.3.5.23 | Hostname | 221 |
| 6.16.1.3.5.24 | Id | 221 |
| 6.16.1.3.5.25 | IpAddress | 222 |
| 6.16.1.3.5.26 | Mode | 222 |
| 6.16.1.3.5.27 | Name | 222 |
| 6.16.1.3.5.28 | Or | 222 |
| 6.16.1.3.5.29 | Ota | 222 |
| 6.16.1.3.5.30 | Offset | 222 |
| 6.16.1.3.5.31 | Rmv | 223 |
| 6.16.1.3.5.32 | Rts | 223 |
| 6.16.1.3.5.33 | Snumber | 223 |
| 6.16.1.3.5.34 | Status | 223 |
| 6.16.1.3.5.35 | TypePy | 223 |
| 6.16.1.3.6 | Trx<TrxFrontent> | 223 |
| 6.16.1.3.6.1 | Alias | 224 |
| 6.16.1.3.6.2 | Antenna | 225 |
| 6.16.1.3.6.3 | Custom | 225 |
| 6.16.1.3.6.4 | Flist | 226 |
| 6.16.1.3.6.5 | Row<Index> | 227 |
| 6.16.1.3.6.6 | FormatPy | 228 |
| 6.16.1.3.6.7 | Fpoints | 228 |
| 6.16.1.3.6.8 | ImportPy | 229 |
| 6.16.1.3.6.9 | Predefined | 230 |
| 6.16.1.3.6.10 | Mode | 230 |
| 6.16.1.3.6.11 | Rx<RxIndex> | 231 |
| 6.16.1.3.6.12 | File | 232 |
| 6.16.1.3.6.13 | Glist | 233 |

| | | |
|---------------|-------------------------|-----|
| 6.16.1.3.6.14 | Row<Index> | 234 |
| 6.16.1.3.6.15 | Tx<TxIndexNull> | 235 |
| 6.16.1.3.6.16 | File | 236 |
| 6.16.1.3.6.17 | Glist | 237 |
| 6.16.1.3.6.18 | Row<Index> | 238 |
| 6.16.1.3.6.19 | Gain | 239 |
| 6.16.1.3.6.20 | Rx | 239 |
| 6.16.1.3.6.21 | Tx | 240 |
| 6.16.1.3.6.22 | Ats | 241 |
| 6.16.1.3.6.23 | Bw | 242 |
| 6.16.1.3.6.24 | CableCorr | 243 |
| 6.16.1.3.6.25 | Connector<Connector> | 243 |
| 6.16.1.3.6.26 | Rx<RxIndex> | 243 |
| 6.16.1.3.6.27 | Mode | 244 |
| 6.16.1.3.6.28 | User | 245 |
| 6.16.1.3.6.29 | Attenuation | 245 |
| 6.16.1.3.6.30 | Delay | 246 |
| 6.16.1.3.6.31 | File | 247 |
| 6.16.1.3.6.32 | Tx<TxIndexNull> | 249 |
| 6.16.1.3.6.33 | Mode | 249 |
| 6.16.1.3.6.34 | User | 250 |
| 6.16.1.3.6.35 | Attenuation | 251 |
| 6.16.1.3.6.36 | Delay | 252 |
| 6.16.1.3.6.37 | File | 253 |
| 6.16.1.3.6.38 | Center | 254 |
| 6.16.1.3.6.39 | Eirp | 255 |
| 6.16.1.3.6.40 | Port | 256 |
| 6.16.1.3.6.41 | Sensor | 256 |
| 6.16.1.3.6.42 | Gain | 257 |
| 6.16.1.3.6.43 | Id | 258 |
| 6.16.1.3.6.44 | Name | 258 |
| 6.16.1.3.6.45 | Ota | 259 |
| 6.16.1.3.6.46 | Offset | 259 |
| 6.16.1.3.6.47 | Rts | 260 |
| 6.16.1.3.6.48 | Snumber | 261 |
| 6.16.1.3.6.49 | TypePy | 261 |
| 6.16.1.4 | Hil | 262 |
| 6.16.1.5 | Last | 263 |
| 6.16.1.6 | Mapping<MappingChannel> | 263 |
| 6.16.1.6.1 | Adjust | 264 |
| 6.16.1.6.1.1 | All | 264 |
| 6.16.1.6.1.2 | Level | 264 |
| 6.16.1.6.1.3 | DigHeadroom | 265 |
| 6.16.1.6.1.4 | Otime | 266 |
| 6.16.1.6.2 | Psensor | 266 |
| 6.16.1.6.3 | Sensor | 267 |
| 6.16.1.6.4 | SubChannel<Subchannel> | 268 |
| 6.16.1.6.4.1 | Adjust | 268 |
| 6.16.1.6.4.2 | Level | 269 |
| 6.16.1.6.4.3 | Fe | 269 |
| 6.16.1.7 | Marker | 271 |
| 6.16.1.7.1 | Object | 271 |
| 6.16.1.8 | Measurement | 273 |
| 6.16.1.9 | Object<ObjectIx> | 273 |

| | | |
|---------------|------------------------|-----|
| 6.16.1.9.1 | All | 274 |
| 6.16.1.9.2 | SubChannel<Subchannel> | 274 |
| 6.16.1.9.2.1 | Angle | 275 |
| 6.16.1.9.2.2 | Horizontal | 275 |
| 6.16.1.9.2.3 | Attenuation | 276 |
| 6.16.1.9.2.4 | Doppler | 277 |
| 6.16.1.9.2.5 | Frequency | 277 |
| 6.16.1.9.2.6 | Speed | 278 |
| 6.16.1.9.2.7 | Range | 279 |
| 6.16.1.9.2.8 | Rcs | 280 |
| 6.16.1.9.2.9 | State | 281 |
| 6.16.1.10 | Objects | 282 |
| 6.16.1.10.1 | Invalid | 282 |
| 6.16.1.10.2 | Valid | 283 |
| 6.16.1.11 | Omonitoring | 283 |
| 6.16.1.12 | Osetup | 285 |
| 6.16.1.12.1 | Apply | 289 |
| 6.16.1.12.2 | Bw | 289 |
| 6.16.1.12.2.1 | Apply | 290 |
| 6.16.1.12.3 | Hil | 291 |
| 6.16.1.12.4 | MultiInstrument | 291 |
| 6.16.1.12.4.1 | Connect | 293 |
| 6.16.1.12.4.2 | Remove | 293 |
| 6.16.1.12.4.3 | Execute | 294 |
| 6.16.1.12.4.4 | Secondary | 294 |
| 6.16.1.12.4.5 | Add | 296 |
| 6.16.1.12.4.6 | Connection | 296 |
| 6.16.1.12.4.7 | Execute | 297 |
| 6.16.1.12.4.8 | Remove | 297 |
| 6.16.1.12.5 | Swunit | 298 |
| 6.16.1.13 | Radar | 299 |
| 6.16.1.13.1 | Base | 299 |
| 6.16.1.13.2 | Power | 300 |
| 6.16.1.14 | Scenario | 300 |
| 6.16.1.14.1 | File | 303 |
| 6.16.1.14.2 | Pause | 303 |
| 6.16.1.14.3 | Position | 304 |
| 6.16.1.14.4 | Replay | 305 |
| 6.16.1.15 | Sensor<Sensor> | 306 |
| 6.16.1.15.1 | Add | 306 |
| 6.16.1.15.2 | Alias | 307 |
| 6.16.1.15.3 | Angle | 307 |
| 6.16.1.15.4 | Bw | 308 |
| 6.16.1.15.5 | Center | 309 |
| 6.16.1.15.6 | Cfactor | 310 |
| 6.16.1.15.7 | Count | 310 |
| 6.16.1.15.8 | Distance | 311 |
| 6.16.1.15.9 | Dynamic | 312 |
| 6.16.1.15.9.1 | Id | 312 |
| 6.16.1.15.10 | Id | 313 |
| 6.16.1.15.11 | Rmv | 313 |
| 6.16.1.16 | Swunit | 314 |
| 6.16.1.16.1 | CableCorr | 315 |
| 6.16.1.16.1.1 | Connector<Connector> | 316 |

| | | |
|----------------|-------------------------|-----|
| 6.16.1.16.1.2 | Rx<RxIndex> | 316 |
| 6.16.1.16.1.3 | Mode | 317 |
| 6.16.1.16.1.4 | User | 318 |
| 6.16.1.16.1.5 | Attenuation | 318 |
| 6.16.1.16.1.6 | Delay | 319 |
| 6.16.1.16.1.7 | File | 320 |
| 6.16.1.16.1.8 | Tx<TxIndexNull> | 321 |
| 6.16.1.16.1.9 | Mode | 321 |
| 6.16.1.16.1.10 | User | 322 |
| 6.16.1.16.1.11 | Attenuation | 323 |
| 6.16.1.16.1.12 | Delay | 324 |
| 6.16.1.16.1.13 | File | 325 |
| 6.16.1.16.2 | Connect | 326 |
| 6.16.1.16.3 | Disconnect | 326 |
| 6.16.1.16.4 | Mapping<MappingChannel> | 327 |
| 6.16.1.16.4.1 | SubChannel<Subchannel> | 327 |
| 6.16.1.16.4.2 | Config | 328 |
| 6.16.1.16.5 | Relays | 328 |
| 6.16.1.17 | Units | 329 |
| 6.16.2 | Bb | 332 |
| 6.16.2.1 | Path | 332 |
| 6.16.3 | InputPy | 333 |
| 6.16.3.1 | Trigger | 333 |
| 6.16.3.2 | User<UserIx> | 333 |
| 6.16.3.2.1 | Clock | 334 |
| 6.16.3.2.2 | Direction | 335 |
| 6.16.3.2.3 | Trigger | 336 |
| 6.16.4 | Modulation | 337 |
| 6.16.4.1 | All | 337 |
| 6.16.5 | Path | 338 |
| 6.16.6 | Power | 338 |
| 6.16.6.1 | Level | 339 |
| 6.16.6.1.1 | Immediate | 339 |
| 6.16.6.2 | Spc | 340 |
| 6.16.6.2.1 | Measure | 340 |
| 6.16.6.2.2 | Single | 340 |
| 6.16.7 | Roscillator | 341 |
| 6.16.7.1 | External | 342 |
| 6.16.7.1.1 | RfOff | 343 |
| 6.16.7.2 | Internal | 344 |
| 6.16.7.2.1 | Adjust | 344 |
| 6.16.7.3 | Output | 345 |
| 6.16.7.3.1 | Frequency | 345 |
| 6.17 | Status | 346 |
| 6.17.1 | Operation | 347 |
| 6.17.1.1 | Bit<BitNumberNull> | 349 |
| 6.17.1.1.1 | Condition | 350 |
| 6.17.1.1.2 | Enable | 350 |
| 6.17.1.1.3 | Event | 351 |
| 6.17.1.1.4 | Ntransition | 351 |
| 6.17.1.1.5 | Ptransition | 352 |
| 6.17.2 | Questionable | 353 |
| 6.17.2.1 | Bit<BitNumberNull> | 355 |
| 6.17.2.1.1 | Condition | 355 |

| | | | |
|------|--------------|-----------------|-----|
| | 6.17.2.1.2 | Enable | 356 |
| | 6.17.2.1.3 | Event | 357 |
| | 6.17.2.1.4 | Ntransition | 357 |
| | 6.17.2.1.5 | Ptransition | 358 |
| | 6.17.3 | Queue | 358 |
| 6.18 | System | | 359 |
| | 6.18.1 | Beeper | 365 |
| | 6.18.2 | Bios | 366 |
| | 6.18.3 | Communicate | 366 |
| | 6.18.3.1 | Gpib | 367 |
| | 6.18.3.1.1 | Self | 368 |
| | 6.18.3.2 | Hislip | 368 |
| | 6.18.3.3 | Network | 369 |
| | 6.18.3.3.1 | Common | 370 |
| | 6.18.3.3.2 | IpAddress | 371 |
| | 6.18.3.3.2.1 | Subnet | 373 |
| | 6.18.3.3.3 | Restart | 373 |
| | 6.18.3.4 | Rt | 374 |
| | 6.18.3.4.1 | Network | 374 |
| | 6.18.3.4.1.1 | Common | 375 |
| | 6.18.3.4.1.2 | IpAddress | 376 |
| | 6.18.3.4.1.3 | Subnet | 377 |
| | 6.18.3.4.1.4 | Restart | 378 |
| | 6.18.3.5 | Scpi | 378 |
| | 6.18.3.5.1 | Ethernet | 379 |
| | 6.18.3.6 | Serial | 379 |
| | 6.18.3.7 | Socket | 381 |
| | 6.18.3.8 | Syst | 381 |
| | 6.18.3.8.1 | Network | 381 |
| | 6.18.3.8.1.1 | Common | 382 |
| | 6.18.3.8.1.2 | IpAddress | 383 |
| | 6.18.3.8.1.3 | Subnet | 384 |
| | 6.18.3.8.1.4 | Restart | 385 |
| | 6.18.3.9 | Usb | 385 |
| | 6.18.4 | Date | 386 |
| | 6.18.5 | Device | 387 |
| | 6.18.6 | DeviceFootprint | 388 |
| | 6.18.6.1 | History | 388 |
| | 6.18.7 | Dexchange | 389 |
| | 6.18.7.1 | Execute | 391 |
| | 6.18.7.2 | Template | 391 |
| | 6.18.7.2.1 | Predefined | 392 |
| | 6.18.7.2.2 | User | 392 |
| | 6.18.7.3 | Transaction | 393 |
| | 6.18.8 | Error | 394 |
| | 6.18.8.1 | Code | 395 |
| | 6.18.8.2 | History | 396 |
| | 6.18.9 | ExtDevices | 396 |
| | 6.18.9.1 | Update | 397 |
| | 6.18.9.1.1 | Check | 397 |
| | 6.18.9.1.2 | Needed | 398 |
| | 6.18.9.1.3 | Tselected | 398 |
| | 6.18.10 | Fpreset | 399 |
| | 6.18.11 | Generic | 400 |

| | | |
|---------------|----------------|-----|
| 6.18.12 | Help | 400 |
| 6.18.12.1 | Syntax | 401 |
| 6.18.13 | Identification | 402 |
| 6.18.14 | Information | 403 |
| 6.18.15 | Linux | 403 |
| 6.18.15.1 | Kernel | 403 |
| 6.18.16 | Lock | 404 |
| 6.18.16.1 | Name | 405 |
| 6.18.16.2 | Owner | 405 |
| 6.18.16.3 | Release | 406 |
| 6.18.16.4 | Request | 406 |
| 6.18.16.4.1 | Shared | 407 |
| 6.18.16.5 | Shared | 407 |
| 6.18.17 | MassMemory | 408 |
| 6.18.17.1 | Path | 408 |
| 6.18.18 | Ntp | 409 |
| 6.18.19 | Package | 409 |
| 6.18.19.1 | ChartDisplay | 409 |
| 6.18.19.2 | GuiFramework | 410 |
| 6.18.19.3 | Qt | 410 |
| 6.18.20 | PciFpga | 411 |
| 6.18.20.1 | Update | 411 |
| 6.18.20.1.1 | Check | 411 |
| 6.18.20.1.2 | Needed | 412 |
| 6.18.20.1.3 | Tselected | 412 |
| 6.18.21 | Profiling | 413 |
| 6.18.21.1 | HwAccess | 414 |
| 6.18.21.2 | Logging | 415 |
| 6.18.21.3 | Module | 415 |
| 6.18.21.4 | Record | 416 |
| 6.18.21.4.1 | Count | 417 |
| 6.18.21.4.2 | Wrap | 418 |
| 6.18.21.5 | Tick | 419 |
| 6.18.21.5.1 | Enable | 419 |
| 6.18.21.6 | Tpoint | 420 |
| 6.18.21.6.1 | Catalog | 420 |
| 6.18.22 | Protect<Level> | 421 |
| 6.18.22.1 | State | 421 |
| 6.18.23 | Reboot | 422 |
| 6.18.24 | Restart | 423 |
| 6.18.25 | Script | 423 |
| 6.18.25.1 | Discard | 425 |
| 6.18.26 | Security | 425 |
| 6.18.26.1 | Mmem | 426 |
| 6.18.26.1.1 | Protect | 426 |
| 6.18.26.1.1.1 | State | 427 |
| 6.18.26.2 | Network | 427 |
| 6.18.26.2.1 | Avahi | 428 |
| 6.18.26.2.1.1 | State | 428 |
| 6.18.26.2.2 | Ftp | 429 |
| 6.18.26.2.2.1 | State | 429 |
| 6.18.26.2.3 | Http | 430 |
| 6.18.26.2.3.1 | State | 430 |
| 6.18.26.2.4 | Raw | 431 |

| | | |
|----------------|--------------------|-----|
| 6.18.26.2.4.1 | State | 431 |
| 6.18.26.2.5 | RemSupport | 432 |
| 6.18.26.2.6 | Rpc | 432 |
| 6.18.26.2.6.1 | State | 432 |
| 6.18.26.2.7 | Smb | 433 |
| 6.18.26.2.7.1 | State | 433 |
| 6.18.26.2.8 | Soe | 434 |
| 6.18.26.2.8.1 | State | 434 |
| 6.18.26.2.9 | Ssh | 435 |
| 6.18.26.2.9.1 | State | 435 |
| 6.18.26.2.10 | State | 436 |
| 6.18.26.2.11 | SwUpdate | 436 |
| 6.18.26.2.11.1 | State | 437 |
| 6.18.26.2.12 | Vnc | 437 |
| 6.18.26.2.12.1 | State | 438 |
| 6.18.26.3 | Sanitize | 438 |
| 6.18.26.3.1 | State | 439 |
| 6.18.26.4 | SuPolicy | 439 |
| 6.18.26.5 | UsbStorage | 440 |
| 6.18.26.5.1 | State | 440 |
| 6.18.26.6 | VolMode | 441 |
| 6.18.26.6.1 | State | 441 |
| 6.18.27 | Shutdown | 442 |
| 6.18.28 | SrData | 442 |
| 6.18.29 | Srexec | 443 |
| 6.18.30 | Srtime | 443 |
| 6.18.30.1 | Synchronize | 444 |
| 6.18.31 | Startup | 445 |
| 6.18.32 | Time | 445 |
| 6.18.32.1 | DaylightSavingTime | 447 |
| 6.18.32.1.1 | Rule | 448 |
| 6.18.32.2 | HrTimer | 449 |
| 6.18.32.2.1 | Absolute | 449 |
| 6.18.32.3 | Zone | 450 |
| 6.18.33 | Ulock | 451 |
| 6.18.34 | Undo | 452 |
| 6.18.34.1 | Hclear | 452 |
| 6.18.34.2 | Hid | 453 |
| 6.18.34.3 | Hlable | 453 |
| 6.19 | Test | 454 |
| 6.19.1 | All | 455 |
| 6.19.2 | Device | 456 |
| 6.19.2.1 | Internal | 456 |
| 6.19.3 | Pixel | 457 |
| 6.19.4 | Remote | 459 |
| 6.19.4.1 | Lockout | 459 |
| 6.19.5 | Res | 459 |
| 6.19.6 | Serror | 461 |
| 6.19.6.1 | Set | 461 |
| 6.19.7 | Sw | 462 |
| 6.19.7.1 | Scmd | 462 |
| 6.19.8 | Write | 463 |
| 6.20 | Unit | 463 |

| | | |
|-----------|----------------------------|------------|
| 7 | RsAreg800 Utilities | 465 |
| 8 | RsAreg800 Logger | 471 |
| 9 | RsAreg800 Events | 473 |
| 10 | Index | 475 |
| | Index | 477 |



REVISION HISTORY

1.1 RsAreg800

Rohde & Schwarz AREG800A automotive radar echo generator RsAreg800 instrument driver.

Basic Hello-World code:

```
from RsAreg800 import *

instr = RsAreg800('TCPIP::192.168.2.101::hislip0')
idn = instr.query('*IDN?')
print('Hello, I am: ' + idn)
```

Supported instruments: AREG

The package is hosted here: <https://pypi.org/project/RsAreg800/>

Documentation: <https://RsAreg800.readthedocs.io/>

Examples: <https://github.com/Rohde-Schwarz/Examples/>

1.1.1 Version history

Latest release notes summary: Update for FW 5.30.047

Version 5.30.47

- Update for FW 5.30.047

Version 5.0.57

- First release for FW 5.00.057

GETTING STARTED

2.1 Introduction



RsAreg800 is a Python remote-control communication module for Rohde & Schwarz SCPI-based Test and Measurement Instruments. It represents SCPI commands as fixed APIs and hence provides SCPI autocompletion and helps you to avoid common string typing mistakes.

Basic example of the idea:

SCPI command:

SYSTem:REFeRence:FREQuency:SOURce

Python module representation:

writing:

```
driver.system.reference.frequency.source.set()
```

reading:

```
driver.system.reference.frequency.source.get()
```

Check out this RsAreg800 example:

```
"""Getting started - how to work with RsAreg800 Python package.
This example performs basic RF settings on an R&S AREG800 instrument.
It shows the RsAreg800 calls and their corresponding SCPI commands.
Notice that the python RsAreg800 interfaces track the SCPI commands syntax."""
```

```
from RsAreg800 import *

# Open the session
areg = RsAreg('TCPIP::10.102.52.44::HISLIP', False, False)
# Greetings, stranger...
print(f'Hello, I am: {areg.utilities.idn_string}')

# SOURCE:FREQUENCY:FIXed 2230000000
areg.source.frequency.cw.set_value(223E6)

areg.source.areGenerator.radar.base.set_attenuation(10)
```

(continues on next page)

(continued from previous page)

```
# Close the session  
areg.close()
```

Couple of reasons why to choose this module over plain SCPI approach:

- Type-safe API using typing module
- You can still use the plain SCPI communication
- You can select which VISA to use or even not use any VISA at all
- Initialization of a new session is straight-forward, no need to set any other properties
- Many useful features are already implemented - reset, self-test, opc-synchronization, error checking, option checking
- Binary data blocks transfer in both directions
- Transfer of arrays of numbers in binary or ASCII format
- File transfers in both directions
- Events generation in case of error, sent data, received data, chunk data (for big files transfer)
- Multithreading session locking - you can use multiple threads talking to one instrument at the same time
- Logging feature tailored for SCPI communication - different for binary and ascii data

2.2 Installation

RsAreg800 is hosted on pypi.org. You can install it with pip (for example, `pip.exe` for Windows), or if you are using Pycharm (and you should be :-)) direct in the Pycharm **Packet Management** GUI.

Preconditions

- Installed VISA. You can skip this if you plan to use only socket LAN connection. Download the Rohde & Schwarz VISA for Windows, Linux, Mac OS from [here](#)

Option 1 - Installing with `pip.exe` under Windows

- Start the command console: WinKey + R, type `cmd` and hit ENTER
- Change the working directory to the Python installation of your choice (adjust the user name and python version in the path):

```
cd c:\Users\John\AppData\Local\Programs\Python\Python37\Scripts
```
- Install with the command: `pip install RsAreg800`

Option 2 - Installing in Pycharm

- In Pycharm Menu File->Settings->Project->Project Interpreter click on the '+' button on the top left (the last PyCharm version)
- Type RsAreg800 in the search box
- If you are behind a Proxy server, configure it in the Menu: File->Settings->Appearance->System Settings->HTTP Proxy

For more information about Rohde & Schwarz instrument remote control, check out our [Instrument Remote Control Web Series](#).

Option 3 - Offline Installation

If you are still reading the installation chapter, it is probably because the options above did not work for you - proxy problems, your boss saw the internet bill... Here are 6 steps for installing the RsAreg800 offline:

- Download this python script (**Save target as**): `rsinstrument_offline_install.py` This installs all the preconditions that the RsAreg800 needs.
- Execute the script in your offline computer (supported is python 3.6 or newer)
- Download the RsAreg800 package to your computer from the pypi.org: <https://pypi.org/project/RsAreg800/#files> to for example `c:\temp\`
- Start the command line WinKey + R, type `cmd` and hit ENTER
- Change the working directory to the Python installation of your choice (adjust the user name and python version in the path):

```
cd c:\Users\John\AppData\Local\Programs\Python\Python37\Scripts
```

- Install with the command: `pip install c:\temp\RsAreg800-5.30.47.7.tar`

2.3 Finding Available Instruments

Like the pyvisa's ResourceManager, the RsAreg800 can search for available instruments:

```
"""
Find the instruments in your environment
"""

from RsAreg800 import *

# Use the instr_list string items as resource names in the RsAreg800 constructor
instr_list = RsAreg800.list_resources("?*")
print(instr_list)
```

If you have more VISAs installed, the one actually used by default is defined by a secret widget called Visa Conflict Manager. You can force your program to use a VISA of your choice:

```
"""
Find the instruments in your environment with the defined VISA implementation
"""
```

(continues on next page)

(continued from previous page)

```

from RsAreg800 import *

# In the optional parameter visa_select you can use for example 'rs' or 'ni'
# Rs Visa also finds any NRP-Zxx USB sensors
instr_list = RsAreg800.list_resources('?*', 'rs')
print(instr_list)

```

Tip: We believe our R&S VISA is the best choice for our customers. Here are the reasons why:

- Small footprint
- Superior VXI-11 and HiSLIP performance
- Integrated legacy sensors NRP-Zxx support
- Additional VXI-11 and LXI devices search
- Availability for Windows, Linux, Mac OS

2.4 Initiating Instrument Session

RsAreg800 offers four different types of starting your remote-control session. We begin with the most typical case, and progress with more special ones.

Standard Session Initialization

Initiating new instrument session happens, when you instantiate the RsAreg800 object. Below, is a simple Hello World example. Different resource names are examples for different physical interfaces.

```

"""
Simple example on how to use the RsAreg800 module for remote-controlling your instrument
Preconditions:

- Installed RsAreg800 Python module Version 5.30.47 or newer from pypi.org
- Installed VISA, for example R&S Visa 5.12 or newer
"""

from RsAreg800 import *

# A good practice is to assure that you have a certain minimum version installed
RsAreg800.assert_minimum_version('5.30.47')
resource_string_1 = 'TCPIP::192.168.2.101::INSTR' # Standard LAN connection (also
↳ called VXI-11)
resource_string_2 = 'TCPIP::192.168.2.101::hislip0' # Hi-Speed LAN connection - see
↳ 1MA208
resource_string_3 = 'GPIB::20::INSTR' # GPIB Connection
resource_string_4 = 'USB::0x0AAD::0x0119::022019943::INSTR' # USB-TMC (Test and
↳ Measurement Class)

# Initializing the session

```

(continues on next page)

(continued from previous page)

```

driver = RsAreg800(resource_string_1)

idn = driver.utilities.query_str('*IDN?')
print(f"\nHello, I am: '{idn}'")
print(f'RsAreg800 package version: {driver.utilities.driver_version}')
print(f'Visa manufacturer: {driver.utilities.visa_manufacturer}')
print(f'Instrument full name: {driver.utilities.full_instrument_model_name}')
print(f'Instrument installed options: {",".join(driver.utilities.instrument_options)}')

# Close the session
driver.close()

```

Note: If you are wondering about the missing ASRL1::INSTR, yes, it works too, but come on... it's 2023.

Do not care about specialty of each session kind; RsAreg800 handles all the necessary session settings for you. You immediately have access to many identification properties in the interface `driver.utilities`. Here are some of them:

- `idn_string`
- `driver_version`
- `visa_manufacturer`
- `full_instrument_model_name`
- `instrument_serial_number`
- `instrument_firmware_version`
- `instrument_options`

The constructor also contains optional boolean arguments `id_query` and `reset`:

```
driver = RsAreg800('TCPIP::192.168.56.101::hislip0', id_query=True, reset=True)
```

- Setting `id_query` to `True` (default is `True`) checks, whether your instrument can be used with the RsAreg800 module.
- Setting `reset` to `True` (default is `False`) resets your instrument. It is equivalent to calling the `reset()` method.

Selecting a Specific VISA

Just like in the function `list_resources()`, the RsAreg800 allows you to choose which VISA to use:

```

"""
Choosing VISA implementation
"""

from RsAreg800 import *

# Force use of the Rs Visa. For NI Visa, use the "SelectVisa='ni'"
driver = RsAreg800('TCPIP::192.168.56.101::INSTR', True, True, "SelectVisa='rs'")

idn = driver.utilities.query_str('*IDN?')

```

(continues on next page)

(continued from previous page)

```
print(f"\nHello, I am: '{idn}')"
print(f"\nI am using the VISA from: {driver.utilities.visa_manufacturer}")

# Close the session
driver.close()
```

No VISA Session

We recommend using VISA when possible preferably with HiSlip session because of its low latency. However, if you are a strict VISA denier, RsAreg800 has something for you too - **no Visa installation raw LAN socket**:

```
"""
Using RsAreg800 without VISA for LAN Raw socket communication
"""

from RsAreg800 import *

driver = RsAreg800('TCPIP::192.168.56.101::5025::SOCKET', True, True, "SelectVisa='socket
↪'")
print(f'Visa manufacturer: {driver.utilities.visa_manufacturer}')
print(f"\nHello, I am: '{driver.utilities.idn_string}'")

# Close the session
driver.close()
```

Warning: Not using VISA can cause problems by debugging when you want to use the communication Trace Tool. The good news is, you can easily switch to use VISA and back just by changing the constructor arguments. The rest of your code stays unchanged.

Simulating Session

If a colleague is currently occupying your instrument, leave him in peace, and open a simulating session:

```
driver = RsAreg800('TCPIP::192.168.56.101::hislip0', True, True, "Simulate=True")
```

More option_string tokens are separated by comma:

```
driver = RsAreg800('TCPIP::192.168.56.101::hislip0', True, True, "SelectVisa='rs',
↪Simulate=True")
```

Shared Session

In some scenarios, you want to have two independent objects talking to the same instrument. Rather than opening a second VISA connection, share the same one between two or more RsAreg800 objects:

```
"""
Sharing the same physical VISA session by two different RsAreg800 objects
"""

from RsAreg800 import *

driver1 = RsAreg800('TCPIP::192.168.56.101::INSTR', True, True)
driver2 = RsAreg800.from_existing_session(driver1)

print(f'driver1: {driver1.utilities.idn_string}')
print(f'driver2: {driver2.utilities.idn_string}')

# Closing the driver2 session does not close the driver1 session - driver1 is the
↪ 'session master'
driver2.close()
print(f'driver2: I am closed now')

print(f'driver1: I am still opened and working: {driver1.utilities.idn_string}')
driver1.close()
print(f'driver1: Only now I am closed.')
```

Note: The driver1 is the object holding the 'master' session. If you call the driver1.close(), the driver2 loses its instrument session as well, and becomes pretty much useless.

2.5 Plain SCPI Communication

After you have opened the session, you can use the instrument-specific part described in the RsAreg800 API Structure. If for any reason you want to use the plain SCPI, use the utilities interface's two basic methods:

- write_str() - writing a command without an answer, for example *RST
- query_str() - querying your instrument, for example the *IDN? query

You may ask a question. Actually, two questions:

- Q1: Why there are not called write() and query() ?
- Q2: Where is the read() ?

Answer 1: Actually, there are - the write_str() / write() and query_str() / query() are aliases, and you can use any of them. We promote the _str names, to clearly show you want to work with strings. Strings in Python3 are Unicode, the bytes and string objects are not interchangeable, since one character might be represented by more than 1 byte. To avoid mixing string and binary communication, all the method names for binary transfer contain _bin in the name.

Answer 2: Short answer - you do not need it. Long answer - your instrument never sends unsolicited responses. If you send a set command, you use write_str(). For a query command, you use query_str(). So, you really do not need it...

Bottom line - if you are used to `write()` and `query()` methods, from `pyvisa`, the `write_str()` and `query_str()` are their equivalents.

Enough with the theory, let us look at an example. Simple write, and query:

```
"""
Basic string write_str / query_str
"""

from RsAreg800 import *

driver = RsAreg800('TCPIP::192.168.56.101::INSTR')
driver.utilities.write_str('*RST')
response = driver.utilities.query_str('*IDN?')
print(response)

# Close the session
driver.close()
```

This example is so-called “*University-Professor-Example*” - good to show a principle, but never used in praxis. The abovementioned commands are already a part of the driver’s API. Here is another example, achieving the same goal:

```
"""
Basic string write_str / query_str
"""

from RsAreg800 import *

driver = RsAreg800('TCPIP::192.168.56.101::INSTR')
driver.utilities.reset()
print(driver.utilities.idn_string)

# Close the session
driver.close()
```

One additional feature we need to mention here: **VISA timeout**. To simplify, VISA timeout plays a role in each `query_xxx()`, where the controller (your PC) has to prevent waiting forever for an answer from your instrument. VISA timeout defines that maximum waiting time. You can set/read it with the `visa_timeout` property:

```
# Timeout in milliseconds
driver.utilities.visa_timeout = 3000
```

After this time, the `RsAreg800` raises an exception. Speaking of exceptions, an important feature of the `RsAreg800` is **Instrument Status Checking**. Check out the next chapter that describes the error checking in details.

For completion, we mention other string-based `write_xxx()` and `query_xxx()` methods - all in one example. They are convenient extensions providing type-safe float/boolean/integer setting/querying features:

```
"""
Basic string write_xxx / query_xxx
"""

from RsAreg800 import *

driver = RsAreg800('TCPIP::192.168.56.101::INSTR')
```

(continues on next page)

(continued from previous page)

```

driver.utilities.visa_timeout = 5000
driver.utilities.instrument_status_checking = True
driver.utilities.write_int('SWEEP:COUNT ', 10) # sending 'SWEEP:COUNT 10'
driver.utilities.write_bool('SOURCE:RF:OUTPUT:STATE ', True) # sending
↳ 'SOURCE:RF:OUTPUT:STATE ON'
driver.utilities.write_float('SOURCE:RF:FREQUENCY ', 1E9) # sending 'SOURCE:RF:FREQUENCY_
↳ 10000000000'

sc = driver.utilities.query_int('SWEEP:COUNT?') # returning integer number sc=10
out = driver.utilities.query_bool('SOURCE:RF:OUTPUT:STATE?') # returning boolean_
↳ out=True
freq = driver.utilities.query_float('SOURCE:RF:FREQUENCY?') # returning float number_
↳ freq=1E9

# Close the session
driver.close()

```

Lastly, a method providing basic synchronization: `query_opc()`. It sends query `*OPC?` to your instrument. The instrument waits with the answer until all the tasks it currently has in a queue are finished. This way your program waits too, and this way it is synchronized with the actions in the instrument. Remember to have the VISA timeout set to an appropriate value to prevent the timeout exception. Here's the snippet:

```

driver.utilities.visa_timeout = 3000
driver.utilities.write_str("INIT")
driver.utilities.query_opc()

# The results are ready now to fetch
results = driver.utilities.query_str("FETCH:MEASUREMENT?")

```

Tip: Wait, there's more: you can send the `*OPC?` after each `write_xxx()` automatically:

```

# Default value after init is False
driver.utilities.opc_query_after_write = True

```

2.6 Error Checking

RsAreg800 pushes limits even further (internal R&S joke): It has a built-in mechanism that after each command/query checks the instrument's status subsystem, and raises an exception if it detects an error. For those who are already screaming: **Speed Performance Penalty!!!**, don't worry, you can disable it.

Instrument status checking is very useful since in case your command/query caused an error, you are immediately informed about it. Status checking has in most cases no practical effect on the speed performance of your program. However, if for example, you do many repetitions of short write/query sequences, it might make a difference to switch it off:

```

# Default value after init is True
driver.utilities.instrument_status_checking = False

```

To clear the instrument status subsystem of all errors, call this method:

```
driver.utilities.clear_status()
```

Instrument's status system error queue is clear-on-read. It means, if you query its content, you clear it at the same time. To query and clear list of all the current errors, use this snippet:

```
errors_list = driver.utilities.query_all_errors()
```

See the next chapter on how to react on errors.

2.7 Exception Handling

The base class for all the exceptions raised by the RsAreg800 is `RsInstrException`. Inherited exception classes:

- `ResourceError` raised in the constructor by problems with initiating the instrument, for example wrong or non-existing resource name
- `StatusException` raised if a command or a query generated error in the instrument's error queue
- `TimeoutException` raised if a visa timeout or an opc timeout is reached

In this example we show usage of all of them. Because it is difficult to generate an error using the instrument-specific SCPI API, we use plain SCPI commands:

```
"""
Showing how to deal with exceptions
"""

from RsAreg800 import *

driver = None
# Try-catch for initialization. If an error occurs, the ResourceError is raised
try:
    driver = RsAreg800('TCPIP::10.112.1.179::hislip0')
except ResourceError as e:
    print(e.args[0])
    print('Your instrument is probably OFF...')
    # Exit now, no point of continuing
    exit(1)

# Dealing with commands that potentially generate errors OPTION 1:
# Switching the status checking OFF temporarily
driver.utilities.instrument_status_checking = False
driver.utilities.write_str('MY:MISSpelled:COMManD')
# Clear the error queue
driver.utilities.clear_status()
# Status checking ON again
driver.utilities.instrument_status_checking = True

# Dealing with queries that potentially generate errors OPTION 2:
try:
    # You might want to reduce the VISA timeout to avoid long waiting
    driver.utilities.visa_timeout = 1000
    driver.utilities.query_str('MY:WRONG:QUERy?')
```

(continues on next page)

(continued from previous page)

```

except StatusException as e:
    # Instrument status error
    print(e.args[0])
    print('Nothing to see here, moving on...')

except TimeoutException as e:
    # Timeout error
    print(e.args[0])
    print('That took a long time...')

except RsInstrException as e:
    # RsInstrException is a base class for all the RsAreg800 exceptions
    print(e.args[0])
    print('Some other RsAreg800 error...')

finally:
    driver.utilities.visa_timeout = 5000
    # Close the session in any case
    driver.close()

```

Tip: General rules for exception handling:

- If you are sending commands that might generate errors in the instrument, for example deleting a file which does not exist, use the **OPTION 1** - temporarily disable status checking, send the command, clear the error queue and enable the status checking again.
- If you are sending queries that might generate errors or timeouts, for example querying measurement that can not be performed at the moment, use the **OPTION 2** - try/except with optionally adjusting the timeouts.

2.8 Transferring Files

Instrument -> PC

You definitely experienced it: you just did a perfect measurement, saved the results as a screenshot to an instrument's storage drive. Now you want to transfer it to your PC. With RsAreg800, no problem, just figure out where the screenshot was stored on the instrument. In our case, it is `/var/user/instr_screenshot.png`:

```

driver.utilities.read_file_from_instrument_to_pc(
    r'/var/user/instr_screenshot.png',
    r'c:\temp\pc_screenshot.png')

```

PC -> Instrument

Another common scenario: Your cool test program contains a setup file you want to transfer to your instrument: Here is the RsAreg800 one-liner split into 3 lines:

```
driver.utilities.send_file_from_pc_to_instrument(  
    r'c:\MyCoolTestProgram\instr_setup.sav',  
    r'/var/appdata/instr_setup.sav')
```

2.9 Writing Binary Data

Writing from bytes

An example where you need to send binary data is a waveform file of a vector signal generator. First, you compose your `wform_data` as bytes, and then you send it with `write_bin_block()`:

```
# MyWaveform.wv is an instrument file name under which this data is stored  
driver.utilities.write_bin_block(  
    "SOUR:BB:ARB:WAV:DATA 'MyWaveform.wv'",",  
    wform_data)
```

Note: Notice the `write_bin_block()` has two parameters:

- string parameter `cmd` for the SCPI command
 - bytes parameter `payload` for the actual binary data to send
-

Writing from PC files

Similar to querying binary data to a file, you can write binary data from a file. The second parameter is then the PC file path the content of which you want to send:

```
driver.utilities.write_bin_block_from_file(  
    "SOUR:BB:ARB:WAV:DATA 'MyWaveform.wv'",",  
    r"c:\temp\wform_data.wv")
```

2.10 Transferring Big Data with Progress

We can agree that it can be annoying using an application that shows no progress for long-lasting operations. The same is true for remote-control programs. Luckily, the RsAreg800 has this covered. And, this feature is quite universal - not just for big files transfer, but for any data in both directions.

RsAreg800 allows you to register a function (programmers fancy name is `callback`), which is then periodically invoked after transfer of one data chunk. You can define that chunk size, which gives you control over the callback invoke frequency. You can even slow down the transfer speed, if you want to process the data as they arrive (direction `instrument -> PC`).

To show this in praxis, we are going to use another *University-Professor-Example*: querying the `*IDN?` with chunk size of 2 bytes and delay of 200ms between each chunk read:

```

"""
Event handlers by reading
"""

from RsAreg800 import *
import time

def my_transfer_handler(args):
    """Function called each time a chunk of data is transferred"""
    # Total size is not always known at the beginning of the transfer
    total_size = args.total_size if args.total_size is not None else "unknown"

    print(f"Context: '{args.context}{'with opc' if args.opc_sync else ''}', "
          f"chunk {args.chunk_ix}, "
          f"transferred {args.transferred_size} bytes, "
          f"total size {total_size}, "
          f"direction {'reading' if args.reading else 'writing'}, "
          f"data '{args.data}'")

    if args.end_of_transfer:
        print('End of Transfer')
        time.sleep(0.2)

driver = RsAreg800('TCPIP::192.168.56.101::INSTR')

driver.events.on_read_handler = my_transfer_handler
# Switch on the data to be included in the event arguments
# The event arguments args.data will be updated
driver.events.io_events_include_data = True
# Set data chunk size to 2 bytes
driver.utilities.data_chunk_size = 2
driver.utilities.query_str('*IDN?')
# Unregister the event handler
driver.utilities.on_read_handler = None

# Close the session
driver.close()

```

If you start it, you might wonder (or maybe not): why is the `args.total_size = None`? The reason is, in this particular case the RsAreg800 does not know the size of the complete response up-front. However, if you use the same mechanism for transfer of a known data size (for example, file transfer), you get the information about the total size too, and hence you can calculate the progress as:

$$\text{progress [pct]} = 100 * \text{args.transferred_size} / \text{args.total_size}$$

Snippet of transferring file from PC to instrument, the rest of the code is the same as in the previous example:

```

driver.events.on_write_handler = my_transfer_handler
driver.events.io_events_include_data = True
driver.data_chunk_size = 1000
driver.utilities.send_file_from_pc_to_instrument(
    r'c:\MyCoolTestProgram\my_big_file.bin',

```

(continues on next page)

(continued from previous page)

```

    r'/var/user/my_big_file.bin')
# Unregister the event handler
driver.events.on_write_handler = None

```

2.11 Multithreading

You are at the party, many people talking over each other. Not every person can deal with such crosstalk, neither can measurement instruments. For this reason, RsAreg800 has a feature of scheduling the access to your instrument by using so-called **Locks**. Locks make sure that there can be just one client at a time *talking* to your instrument. Talking in this context means completing one communication step - one command write or write/read or write/read/error check.

To describe how it works, and where it matters, we take three typical multithread scenarios:

One instrument session, accessed from multiple threads

You are all set - the lock is a part of your instrument session. Check out the following example - it will execute properly, although the instrument gets 10 queries at the same time:

```

"""
Multiple threads are accessing one RsAreg800 object
"""

import threading
from RsAreg800 import *

def execute(session):
    """Executed in a separate thread."""
    session.utilities.query_str('*IDN?')

driver = RsAreg800('TCPIP::192.168.56.101::INSTR')
threads = []
for i in range(10):
    t = threading.Thread(target=execute, args=(driver, ))
    t.start()
    threads.append(t)
print('All threads started')

# Wait for all threads to join this main thread
for t in threads:
    t.join()
print('All threads ended')

driver.close()

```

Shared instrument session, accessed from multiple threads

Same as the previous case, you are all set. The session carries the lock with it. You have two objects, talking to the same instrument from multiple threads. Since the instrument session is shared, the same lock applies to both objects causing the exclusive access to the instrument.

Try the following example:

```

"""
Multiple threads are accessing two RsAreg800 objects with shared session
"""

import threading
from RsAreg800 import *

def execute(session: RsAreg800, session_ix, index) -> None:
    """Executed in a separate thread."""
    print(f'{index} session {session_ix} query start...')
    session.utilities.query_str('*IDN?')
    print(f'{index} session {session_ix} query end')

driver1 = RsAreg800('TCPIP::192.168.56.101::INSTR')
driver2 = RsAreg800.from_existing_session(driver1)
driver1.utilities.visa_timeout = 200
driver2.utilities.visa_timeout = 200
# To see the effect of crosstalk, uncomment this line
# driver2.utilities.clear_lock()

threads = []
for i in range(10):
    t = threading.Thread(target=execute, args=(driver1, 1, i,))
    t.start()
    threads.append(t)
    t = threading.Thread(target=execute, args=(driver2, 2, i,))
    t.start()
    threads.append(t)
print('All threads started')

# Wait for all threads to join this main thread
for t in threads:
    t.join()
print('All threads ended')

driver2.close()
driver1.close()

```

As you see, everything works fine. If you want to simulate some party crosstalk, uncomment the line `driver2.utilities.clear_lock()`. This causes the driver2 session lock to break away from the driver1 session lock. Although the driver1 still tries to schedule its instrument access, the driver2 tries to do the same at the same time, which leads to all the fun stuff happening.

Multiple instrument sessions accessed from multiple threads

Here, there are two possible scenarios depending on the instrument's VISA interface:

- You are lucky, because your instrument handles each remote session completely separately. An example of such instrument is SMW200A. In this case, you have no need for session locking.
- Your instrument handles all sessions with one set of in/out buffers. You need to lock the session for the duration of a talk. And you are lucky again, because the RsAreg800 takes care of it for you. The text below describes this scenario.

Run the following example:

```
"""
Multiple threads are accessing two RsAreg800 objects with two separate sessions
"""

import threading
from RsAreg800 import *

def execute(session: RsAreg800, session_ix, index) -> None:
    """Executed in a separate thread."""
    print(f'{index} session {session_ix} query start...')
    session.utilities.query_str('*IDN?')
    print(f'{index} session {session_ix} query end')

driver1 = RsAreg800('TCPIP::192.168.56.101::INSTR')
driver2 = RsAreg800('TCPIP::192.168.56.101::INSTR')
driver1.utilities.visa_timeout = 200
driver2.utilities.visa_timeout = 200

# Synchronise the sessions by sharing the same lock
driver2.utilities.assign_lock(driver1.utilities.get_lock()) # To see the effect of
↳ crosstalk, comment this line

threads = []
for i in range(10):
    t = threading.Thread(target=execute, args=(driver1, 1, i,))
    t.start()
    threads.append(t)
    t = threading.Thread(target=execute, args=(driver2, 2, i,))
    t.start()
    threads.append(t)
print('All threads started')

# Wait for all threads to join this main thread
for t in threads:
    t.join()
print('All threads ended')

driver2.close()
driver1.close()
```

You have two completely independent sessions that want to talk to the same instrument at the same time. This will

not go well, unless they share the same session lock. The key command to achieve this is `driver2.utilities.assign_lock(driver1.utilities.get_lock())` Try to comment it and see how it goes. If despite commenting the line the example runs without issues, you are lucky to have an instrument similar to the SMW200A.

2.12 Logging

Yes, the logging again. This one is tailored for instrument communication. You will appreciate such handy feature when you troubleshoot your program, or just want to protocol the SCPI communication for your test reports.

What can you actually do with the logger?

- Write SCPI communication to a stream-like object, for example console or file, or both simultaneously
- Log only errors and skip problem-free parts; this way you avoid going through thousands lines of texts
- Investigate duration of certain operations to optimize your program's performance
- Log custom messages from your program

Let us take this basic example:

```
"""
Basic logging example to the console
"""

from RsAreg800 import *

driver = RsAreg800('TCPIP::192.168.1.101::INSTR')

# Switch ON logging to the console.
driver.utilities.logger.log_to_console = True
driver.utilities.logger.mode = LoggingMode.On
driver.utilities.reset()

# Close the session
driver.close()
```

Console output:

| | | | |
|--------------|-----------------------------|-------------|------------------------|
| 10:29:10.819 | TCPIP::192.168.1.101::INSTR | 0.976 ms | Write: *RST |
| 10:29:10.819 | TCPIP::192.168.1.101::INSTR | 1884.985 ms | Status check: OK |
| 10:29:12.704 | TCPIP::192.168.1.101::INSTR | 0.983 ms | Query OPC: 1 |
| 10:29:12.705 | TCPIP::192.168.1.101::INSTR | 2.892 ms | Clear status: OK |
| 10:29:12.708 | TCPIP::192.168.1.101::INSTR | 3.905 ms | Status check: OK |
| 10:29:12.712 | TCPIP::192.168.1.101::INSTR | 1.952 ms | Close: Closing session |

The columns of the log are aligned for better reading. Columns meaning:

- (1) Start time of the operation
- (2) Device resource name (you can set an alias)
- (3) Duration of the operation
- (4) Log entry

Tip: You can customize the logging format with `set_format_string()`, and set the maximum log entry length with the properties:

- `abbreviated_max_len_ascii`
- `abbreviated_max_len_bin`
- `abbreviated_max_len_list`

See the full logger help [here](#).

Notice the SCPI communication starts from the line `driver.utilities.reset()`. If you want to log the initialization of the session as well, you have to switch the logging ON already in the constructor:

```
driver = RsAreg800('TCPIP::192.168.56.101::hislip0', options='LoggingMode=On')
```

Parallel to the console logging, you can log to a general stream. Do not fear the programmer's jargon... under the term **stream** you can just imagine a file. To be a little more technical, a stream in Python is any object that has two methods: `write()` and `flush()`. This example opens a file and sets it as logging target:

```
"""
Example of logging to a file
"""

from RsAreg800 import *

driver = RsAreg800('TCPIP::192.168.1.101::INSTR')

# We also want to log to the console.
driver.utilities.logger.log_to_console = True

# Logging target is our file
file = open(r'c:\temp\my_file.txt', 'w')
driver.utilities.logger.set_logging_target(file)
driver.utilities.logger.mode = LoggingMode.On

# Instead of the 'TCPIP::192.168.1.101::INSTR', show 'MyDevice'
driver.utilities.logger.device_name = 'MyDevice'

# Custom user entry
driver.utilities.logger.info_raw('----- This is my custom log entry. ---- ')

driver.utilities.reset()

# Close the session
driver.close()

# Close the log file
file.close()
```

Tip: To make the log more compact, you can skip all the lines with Status check: OK:

```
driver.utilities.logger.log_status_check_ok = False
```


Hint: You can share the logging file between multiple sessions. In such case, remember to close the file only after you have stopped logging in all your sessions, otherwise you get a log write error.

For logging to a UDP port in addition to other log targets, use one of the lines:

```
driver.utilities.logger.log_to_udp = True
driver.utilities.logger.log_to_console_and_udp = True
```

You can select the UDP port to log to, the default is 49200:

```
driver.utilities.logger.udp_port = 49200
```

Another cool feature is logging only errors. To make this mode usefull for troubleshooting, you also want to see the circumstances which lead to the errors. Each driver elementary operation, for example, `write_str()`, can generate a group of log entries - let us call them **Segment**. In the logging mode Errors, a whole segment is logged only if at least one entry of the segment is an error.

The script below demonstrates this feature. We use a direct SCPI communication to send a misspelled SCPI command `*CLS`, which leads to instrument status error:

```
"""
Logging example to the console with only errors logged
"""

from RsAreg800 import *

driver = RsAreg800('TCPIP::192.168.1.101::INSTR', options='LoggingMode=Errors')

# Switch ON logging to the console.
driver.utilities.logger.log_to_console = True

# Reset will not be logged, since no error occurred there
driver.utilities.reset()

# Now a misspelled command.
driver.utilities.write('*CLaS')

# A good command again, no logging here
idn = driver.utilities.query('*IDN?')

# Close the session
driver.close()
```

Console output:

```
12:11:02.879 TCPIP::192.168.1.101::INSTR 0.976 ms Write string: *CLaS
12:11:02.879 TCPIP::192.168.1.101::INSTR 6.833 ms Status check: StatusException:
Instrument error detected: Undefined header;
↪ *CLaS
```

Notice the following:

- Although the operation **Write string: *CLaS** finished without an error, it is still logged, because it provides the context for the actual error which occurred during the status checking right after.
- No other log entries are present, including the session initialization and close, because they were all error-free.

3.1 AregAttRcsKeepConst

```
# Example value:  
value = enums.AregAttRcsKeepConst.ATTenuation  
# All values (2x):  
ATTenuation | RCS
```

3.2 AregCableCorrSour

```
# Example value:  
value = enums.AregCableCorrSour.FACTory  
# All values (3x):  
FACTory | S2P | USER
```

3.3 AregCconfigBw

```
# Example value:  
value = enums.AregCconfigBw.BW1G  
# All values (3x):  
BW1G | BW2G | BW5G
```

3.4 AregCconfigOptMode

```
# Example value:  
value = enums.AregCconfigOptMode.FAST  
# All values (2x):  
FAST | QHIG
```

3.5 AregCconfigSystAlign

```
# Example value:
value = enums.AregCconfigSystAlign.OFF
# All values (3x):
OFF | ON | TABLE
```

3.6 AregChanMappingGui

```
# First value:
value = enums.AregChanMappingGui.CFE1
# Last value:
value = enums.AregChanMappingGui.TRX4
# All values (82x):
CFE1 | CFE2 | CFE3 | CFE4 | CFE5 | CFE6 | CFE7 | CFE8
FE1 | FE2 | FE3 | FE4 | IFONly | NONE | QAT1CH1 | QAT1CH2
QAT1CH3 | QAT1CH4 | QAT1CH5 | QAT1CH6 | QAT1CH7 | QAT1CH8 | QAT2CH1 | QAT2CH2
QAT2CH3 | QAT2CH4 | QAT2CH5 | QAT2CH6 | QAT2CH7 | QAT2CH8 | QAT3CH1 | QAT3CH2
QAT3CH3 | QAT3CH4 | QAT3CH5 | QAT3CH6 | QAT3CH7 | QAT3CH8 | QAT4CH1 | QAT4CH2
QAT4CH3 | QAT4CH4 | QAT4CH5 | QAT4CH6 | QAT4CH7 | QAT4CH8 | QAT5CH1 | QAT5CH2
QAT5CH3 | QAT5CH4 | QAT5CH5 | QAT5CH6 | QAT5CH7 | QAT5CH8 | QAT6CH1 | QAT6CH2
QAT6CH3 | QAT6CH4 | QAT6CH5 | QAT6CH6 | QAT6CH7 | QAT6CH8 | QAT7CH1 | QAT7CH2
QAT7CH3 | QAT7CH4 | QAT7CH5 | QAT7CH6 | QAT7CH7 | QAT7CH8 | QAT8CH1 | QAT8CH2
QAT8CH3 | QAT8CH4 | QAT8CH5 | QAT8CH6 | QAT8CH7 | QAT8CH8 | TRX1 | TRX2
TRX3 | TRX4
```

3.7 AregChanMappingSensor

```
# First value:
value = enums.AregChanMappingSensor.NONE
# Last value:
value = enums.AregChanMappingSensor.SEN8
# All values (9x):
NONE | SEN1 | SEN2 | SEN3 | SEN4 | SEN5 | SEN6 | SEN7
SEN8
```

3.8 AregDopplerUnit

```
# Example value:
value = enums.AregDopplerUnit.FREquency
# All values (2x):
FREquency | SPEed
```

3.9 AregDynLoggLevel

```
# Example value:  
value = enums.AregDynLoggLevel.ALL  
# All values (3x):  
ALL | EAWarning | ERROR
```

3.10 AregFconfUseCustAntAreg800

```
# Example value:  
value = enums.AregFconfUseCustAntAreg800.LIST  
# All values (2x):  
LIST | NONE
```

3.11 AregFeQatConnMode

```
# Example value:  
value = enums.AregFeQatConnMode.CERROR  
# All values (6x):  
CERROR | CONNECTED | DIALING | DISCONNECTED | UERROR | UPDATE
```

3.12 AregFeQatMode

```
# Example value:  
value = enums.AregFeQatMode.MULTI  
# All values (2x):  
MULTI | SINGLE
```

3.13 AregFeQatOrientation

```
# Example value:  
value = enums.AregFeQatOrientation.HORIZONTAL  
# All values (2x):  
HORIZONTAL | VERTICAL
```

3.14 AregFeType

```
# Example value:  
value = enums.AregFeType.CFE  
# All values (5x):  
CFE | FE | NONE | QAT | TRX
```

3.15 AregHilUpdateMode

```
# Example value:  
value = enums.AregHilUpdateMode.IMMediate  
# All values (2x):  
IMMediate | TIMestamp
```

3.16 AregMeasPort

```
# Example value:  
value = enums.AregMeasPort.AUX  
# All values (2x):  
AUX | POW
```

3.17 AregMultiInstCnctStatus

```
# Example value:  
value = enums.AregMultiInstCnctStatus.CERRor  
# All values (5x):  
CERRor | CONNected | DISConnected | TCONnecnting | TDISconnecting
```

3.18 AregMultiInstMode

```
# Example value:  
value = enums.AregMultiInstMode.OFF  
# All values (3x):  
OFF | PRIMary | SECondary
```

3.19 AregObjMarkSource

```
# Example value:  
value = enums.AregObjMarkSource.HIL  
# All values (3x):  
HIL | SCENario | SETTing
```

3.20 AregPIEd

```
# Example value:  
value = enums.AregPIEd.ERRORr  
# All values (4x):  
ERRORr | INACTive | OK | WARNing
```

3.21 AregPowSens

```
# Example value:  
value = enums.AregPowSens.SEN1  
# All values (5x):  
SEN1 | SEN2 | SEN3 | SEN4 | UDEFined
```

3.22 AregRadarPowIndicator

```
# Example value:  
value = enums.AregRadarPowIndicator.BAD  
# All values (4x):  
BAD | GOOD | OFF | WEAK
```

3.23 AregSetupTimeBase

```
# Example value:  
value = enums.AregSetupTimeBase.SIMulation  
# All values (2x):  
SIMulation | SYSTem
```

3.24 ByteOrder

```
# Example value:  
value = enums.ByteOrder.NORMAL  
# All values (2x):  
NORMAL | SWAPped
```

3.25 CalDataMode

```
# Example value:  
value = enums.CalDataMode.CUSTOMer  
# All values (2x):  
CUSTOMer | FACTory
```

3.26 CalDataUpdate

```
# Example value:  
value = enums.CalDataUpdate.BBFRC  
# All values (6x):  
BBFRC | FREquency | IALL | LEVel | LEVForced | RFFRC
```

3.27 Colour

```
# Example value:  
value = enums.Colour.GREen  
# All values (4x):  
GREen | NONE | RED | YELLOw
```

3.28 ConnDirection

```
# Example value:  
value = enums.ConnDirection.INPut  
# All values (3x):  
INPut | OUTPut | UNUSed
```


3.29 CustAntFormat

```
# Example value:  
value = enums.CustAntFormat.CSV  
# All values (2x):  
CSV | TXT
```

3.30 DevExpFormat

```
# Example value:  
value = enums.DevExpFormat.CGPRedefined  
# All values (4x):  
CGPRedefined | CGUSer | SCPI | XML
```

3.31 DispKeybLockMode

```
# Example value:  
value = enums.DispKeybLockMode.DISabled  
# All values (5x):  
DISABLEd | DONLy | ENABLEd | TOFF | VNOnly
```

3.32 ErFpowSensMapping

```
# First value:  
value = enums.ErFpowSensMapping.SENS1  
# Last value:  
value = enums.ErFpowSensMapping.UNMapped  
# All values (9x):  
SENS1 | SENS2 | SENS3 | SENS4 | SENSor1 | SENSor2 | SENSor3 | SENSor4  
UNMapped
```

3.33 ErFpowSensSourceAreg

```
# Example value:  
value = enums.ErFpowSensSourceAreg.USER  
# All values (1x):  
USER
```

3.34 FormData

```
# Example value:  
value = enums.FormData.ASCii  
# All values (2x):  
ASCii | PACKed
```

3.35 FormStatReg

```
# Example value:  
value = enums.FormStatReg.ASCii  
# All values (4x):  
ASCii | BINary | HEXadecimal | OCTal
```

3.36 FrontPanelLayout

```
# Example value:  
value = enums.FrontPanelLayout.DIGits  
# All values (2x):  
DIGits | LETTers
```

3.37 HardCopyImageFormat

```
# Example value:  
value = enums.HardCopyImageFormat.BMP  
# All values (4x):  
BMP | JPG | PNG | XPM
```

3.38 HardCopyRegion

```
# Example value:  
value = enums.HardCopyRegion.ALL  
# All values (2x):  
ALL | DIALog
```

3.39 HilDataReceive

```
# Example value:  
value = enums.HilDataReceive.NOData  
# All values (3x):  
NOData | NOTHil | RECeived
```

3.40 IecDevId

```
# Example value:  
value = enums.IecDevId.AUTO  
# All values (2x):  
AUTO | USER
```

3.41 IecTermMode

```
# Example value:  
value = enums.IecTermMode.EOI  
# All values (2x):  
EOI | STANdard
```

3.42 ImpG50G1KcoerceG10K

```
# Example value:  
value = enums.ImpG50G1KcoerceG10K.G1K  
# All values (2x):  
G1K | G50
```

3.43 InclExcl

```
# Example value:  
value = enums.InclExcl.EXCLude  
# All values (2x):  
EXCLude | INCLUDE
```

3.44 KbLayout

```
# First value:  
value = enums.KbLayout.CHINese  
# Last value:  
value = enums.KbLayout.SWEDish  
# All values (20x):  
CHINese | DANish | DUTBe | DUTCh | ENGLish | ENGUK | ENGUS | FINNish  
FREBe | FRECa | FRENch | GERMan | ITALian | JAPanese | KOREan | NORWegian  
PORTuguese | RUSSian | SPANish | SWEDish
```

3.45 NetMode

```
# Example value:  
value = enums.NetMode.AUTO  
# All values (2x):  
AUTO | STATic
```

3.46 OsetupBw

```
# Example value:  
value = enums.OsetupBw.BW1G  
# All values (4x):  
BW1G | BW2G | BW5G | SERVice
```

3.47 OsetupConfiguration

```
# Example value:  
value = enums.OsetupConfiguration.NR  
# All values (2x):  
NR | STD
```

3.48 OsetupDataSource

```
# Example value:  
value = enums.OsetupDataSource.HIL  
# All values (2x):  
HIL | SCENario
```

3.49 OsetupHilProtocol

```
# Example value:
value = enums.OsetupHilProtocol.DCP
# All values (4x):
DCP | UDP | UDPR | ZMQ
```

3.50 OsetupMode

```
# Example value:
value = enums.OsetupMode.DYNamic
# All values (2x):
DYNamic | STATic
```

3.51 OsetupObjRef

```
# Example value:
value = enums.OsetupObjRef.MAPPed
# All values (2x):
MAPPed | ORIGin
```

3.52 OutpConnGlbSignalAreg800A

```
# Example value:
value = enums.OutpConnGlbSignalAreg800A.OBJect
# All values (2x):
OBJect | SWUNit
```

3.53 Parity

```
# Example value:
value = enums.Parity.EVEN
# All values (3x):
EVEN | NONE | ODD
```

3.54 PixelTestPredefined

```
# First value:  
value = enums.PixelTestPredefined.AUTO  
# Last value:  
value = enums.PixelTestPredefined.WHITe  
# All values (9x):  
AUTO | BLACk | BLUE | GR25 | GR50 | GR75 | GREen | RED  
WHITe
```

3.55 PowSensDisplayPriority

```
# Example value:  
value = enums.PowSensDisplayPriority.AVERage  
# All values (2x):  
AVERage | PEAK
```

3.56 PowSensFiltType

```
# Example value:  
value = enums.PowSensFiltType.AUTO  
# All values (3x):  
AUTO | NSRatio | USER
```

3.57 RecScpiCmdMode

```
# Example value:  
value = enums.RecScpiCmdMode.AUTO  
# All values (4x):  
AUTO | DAUTo | MANual | OFF
```

3.58 RoscBandWidtExt

```
# Example value:  
value = enums.RoscBandWidtExt.NARRow  
# All values (2x):  
NARRow | WIDE
```

3.59 RoscFreqExtAreg800A

```
# Example value:
value = enums.RoscFreqExtAreg800A._10MHZ
# All values (2x):
_10MHZ | _3200MHZ
```

3.60 RoscOutpFreqModeSmbb

```
# Example value:
value = enums.RoscOutpFreqModeSmbb.DER10M
# All values (3x):
DER10M | LOOPthrough | OFF
```

3.61 RoscSourSetup

```
# Example value:
value = enums.RoscSourSetup.ELoop
# All values (3x):
ELoop | EXTERNAL | INTERNAL
```

3.62 Rs232BdRate

```
# Example value:
value = enums.Rs232BdRate._115200
# All values (7x):
_115200 | _19200 | _2400 | _38400 | _4800 | _57600 | _9600
```

3.63 Rs232StopBits

```
# Example value:
value = enums.Rs232StopBits._1
# All values (2x):
_1 | _2
```

3.64 ScenarioReplyMode

```
# Example value:  
value = enums.ScenarioReplyMode.LOOP  
# All values (2x):  
LOOP | SINGLE
```

3.65 ScenarioStatus

```
# Example value:  
value = enums.ScenarioStatus.RUNNING  
# All values (2x):  
RUNNING | STOPPED
```

3.66 SelftLev

```
# Example value:  
value = enums.SelftLev.CUSTOMER  
# All values (3x):  
CUSTOMER | PRODUCTION | SERVICE
```

3.67 SelftLevWrite

```
# Example value:  
value = enums.SelftLevWrite.CUSTOMER  
# All values (4x):  
CUSTOMER | NONE | PRODUCTION | SERVICE
```

3.68 SlopeType

```
# Example value:  
value = enums.SlopeType.NEGATIVE  
# All values (2x):  
NEGATIVE | POSITIVE
```


3.69 StateExtended

```
# Example value:
value = enums.StateExtended.DEFAULT
# All values (3x):
DEFAULT | OFF | ON
```

3.70 Test

```
# Example value:
value = enums.Test._0
# All values (4x):
_0 | _1 | RUNNING | STOPPED
```

3.71 TestCalSelected

```
# Example value:
value = enums.TestCalSelected._0
# All values (2x):
_0 | _1
```

3.72 TimeProtocolWithGptp

```
# Example value:
value = enums.TimeProtocolWithGptp._0
# All values (7x):
_0 | _1 | GPTP | NONE | NTP | OFF | ON
```

3.73 UnitAngle

```
# Example value:
value = enums.UnitAngle.DEGREE
# All values (3x):
DEGREE | DEGREE | RADIAN
```

3.74 UnitAngleAreg

```
# Example value:  
value = enums.UnitAngleAreg.DEGree  
# All values (2x):  
DEGREE | RADIAN
```

3.75 UnitLengthAreg

```
# Example value:  
value = enums.UnitLengthAreg.CM  
# All values (3x):  
CM | FT | M
```

3.76 UnitPower

```
# Example value:  
value = enums.UnitPower.DBM  
# All values (3x):  
DBM | DBUV | V
```

3.77 UnitPowSens

```
# Example value:  
value = enums.UnitPowSens.DBM  
# All values (3x):  
DBM | DBUV | WATT
```

3.78 UnitRcsAreg

```
# Example value:  
value = enums.UnitRcsAreg.DBSM  
# All values (2x):  
DBSM | SM
```

3.79 UnitShiftAreg

```
# Example value:  
value = enums.UnitShiftAreg.HZ  
# All values (3x):  
HZ | KHZ | MHZ
```

3.80 UnitSpeed

```
# Example value:  
value = enums.UnitSpeed.KMH  
# All values (4x):  
KMh | MPH | MPS | NMPH
```

3.81 UnitSpeedAreg

```
# Example value:  
value = enums.UnitSpeedAreg.KMH  
# All values (3x):  
KMh | MPH | MPS
```

3.82 UpdPolicyMode

```
# Example value:  
value = enums.UpdPolicyMode.CONFirm  
# All values (3x):  
CONFirm | IGNore | STRict
```


REPCAPS

4.1 HwInstance (Global)

```
# Setting:
driver.repcap_hwInstance_set(repcap.HwInstance.InstA)
# Range:
InstA .. InstH
# All values (8x):
InstA | InstB | InstC | InstD | InstE | InstF | InstG | InstH
```

4.2 BitNumberNull

```
# First value:
value = repcap.BitNumberNull.Nr0
# Range:
Nr0 .. Nr15
# All values (16x):
Nr0 | Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7
Nr8 | Nr9 | Nr10 | Nr11 | Nr12 | Nr13 | Nr14 | Nr15
```

4.3 Channel

```
# First value:
value = repcap.Channel.Nr1
# Range:
Nr1 .. Nr64
# All values (64x):
Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7 | Nr8
Nr9 | Nr10 | Nr11 | Nr12 | Nr13 | Nr14 | Nr15 | Nr16
Nr17 | Nr18 | Nr19 | Nr20 | Nr21 | Nr22 | Nr23 | Nr24
Nr25 | Nr26 | Nr27 | Nr28 | Nr29 | Nr30 | Nr31 | Nr32
Nr33 | Nr34 | Nr35 | Nr36 | Nr37 | Nr38 | Nr39 | Nr40
Nr41 | Nr42 | Nr43 | Nr44 | Nr45 | Nr46 | Nr47 | Nr48
Nr49 | Nr50 | Nr51 | Nr52 | Nr53 | Nr54 | Nr55 | Nr56
Nr57 | Nr58 | Nr59 | Nr60 | Nr61 | Nr62 | Nr63 | Nr64
```

4.4 ChannelNull

```
# First value:
value = repcap.ChannelNull.Nr0
# Range:
Nr0 .. Nr63
# All values (64x):
Nr0 | Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7
Nr8 | Nr9 | Nr10 | Nr11 | Nr12 | Nr13 | Nr14 | Nr15
Nr16 | Nr17 | Nr18 | Nr19 | Nr20 | Nr21 | Nr22 | Nr23
Nr24 | Nr25 | Nr26 | Nr27 | Nr28 | Nr29 | Nr30 | Nr31
Nr32 | Nr33 | Nr34 | Nr35 | Nr36 | Nr37 | Nr38 | Nr39
Nr40 | Nr41 | Nr42 | Nr43 | Nr44 | Nr45 | Nr46 | Nr47
Nr48 | Nr49 | Nr50 | Nr51 | Nr52 | Nr53 | Nr54 | Nr55
Nr56 | Nr57 | Nr58 | Nr59 | Nr60 | Nr61 | Nr62 | Nr63
```

4.5 Connector

```
# First value:
value = repcap.Connector.Nr1
# Range:
Nr1 .. Nr8
# All values (8x):
Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7 | Nr8
```

4.6 Index

```
# First value:
value = repcap.Index.Nr1
# Range:
Nr1 .. Nr64
# All values (64x):
Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7 | Nr8
Nr9 | Nr10 | Nr11 | Nr12 | Nr13 | Nr14 | Nr15 | Nr16
Nr17 | Nr18 | Nr19 | Nr20 | Nr21 | Nr22 | Nr23 | Nr24
Nr25 | Nr26 | Nr27 | Nr28 | Nr29 | Nr30 | Nr31 | Nr32
Nr33 | Nr34 | Nr35 | Nr36 | Nr37 | Nr38 | Nr39 | Nr40
Nr41 | Nr42 | Nr43 | Nr44 | Nr45 | Nr46 | Nr47 | Nr48
Nr49 | Nr50 | Nr51 | Nr52 | Nr53 | Nr54 | Nr55 | Nr56
Nr57 | Nr58 | Nr59 | Nr60 | Nr61 | Nr62 | Nr63 | Nr64
```

4.7 Level

```
# First value:
value = repcap.Level.Nr1
# Range:
Nr1 .. Nr16
# All values (16x):
Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7 | Nr8
Nr9 | Nr10 | Nr11 | Nr12 | Nr13 | Nr14 | Nr15 | Nr16
```

4.8 MappingChannel

```
# First value:
value = repcap.MappingChannel.Nr1
# Range:
Nr1 .. Nr8
# All values (8x):
Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7 | Nr8
```

4.9 ObjectIx

```
# First value:
value = repcap.ObjectIx.Nr1
# Range:
Nr1 .. Nr12
# All values (12x):
Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7 | Nr8
Nr9 | Nr10 | Nr11 | Nr12
```

4.10 QatFrontent

```
# First value:
value = repcap.QatFrontent.Nr1
# Range:
Nr1 .. Nr8
# All values (8x):
Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7 | Nr8
```

4.11 RxIndex

```
# First value:  
value = repcap.RxIndex.Nr1  
# Range:  
Nr1 .. Nr16  
# All values (16x):  
Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7 | Nr8  
Nr9 | Nr10 | Nr11 | Nr12 | Nr13 | Nr14 | Nr15 | Nr16
```

4.12 Sensor

```
# First value:  
value = repcap.Sensor.Nr1  
# Range:  
Nr1 .. Nr8  
# All values (8x):  
Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7 | Nr8
```

4.13 Subchannel

```
# First value:  
value = repcap.Subchannel.Nr1  
# Range:  
Nr1 .. Nr16  
# All values (16x):  
Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7 | Nr8  
Nr9 | Nr10 | Nr11 | Nr12 | Nr13 | Nr14 | Nr15 | Nr16
```


4.14 TrxFrontent

```
# First value:
value = repcap.TrxFrontent.Nr1
# Values (4x):
Nr1 | Nr2 | Nr3 | Nr4
```

4.15 TxIndexNull

```
# First value:
value = repcap.TxIndexNull.Nr0
# Range:
Nr0 .. Nr15
# All values (16x):
Nr0 | Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7
Nr8 | Nr9 | Nr10 | Nr11 | Nr12 | Nr13 | Nr14 | Nr15
```

4.16 UserIx

```
# First value:
value = repcap.UserIx.Nr1
# Range:
Nr1 .. Nr48
# All values (48x):
Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7 | Nr8
Nr9 | Nr10 | Nr11 | Nr12 | Nr13 | Nr14 | Nr15 | Nr16
Nr17 | Nr18 | Nr19 | Nr20 | Nr21 | Nr22 | Nr23 | Nr24
Nr25 | Nr26 | Nr27 | Nr28 | Nr29 | Nr30 | Nr31 | Nr32
Nr33 | Nr34 | Nr35 | Nr36 | Nr37 | Nr38 | Nr39 | Nr40
Nr41 | Nr42 | Nr43 | Nr44 | Nr45 | Nr46 | Nr47 | Nr48
```


EXAMPLES

For more examples, visit our [Rohde & Schwarz Github repository](#).

```
"""Getting started - how to work with RsAreg800 Python package.
This example performs basic RF settings on an R&S AREG800 instrument.
It shows the RsAreg800 calls and their corresponding SCPI commands.
Notice that the python RsAreg800 interfaces track the SCPI commands syntax."""

from RsAreg800 import *

# Open the session
areg = RsAreg('TCPIP::10.102.52.44::HISLIP', False, False)
# Greetings, stranger...
print(f'Hello, I am: {areg.utilities.idn_string}')

# SOURCE:FREQUENCY:FIXed 2230000000
areg.source.frequency.cw.set_value(223E6)

areg.source.areGenerator.radar.base.set_attenuation(10)

# Close the session
areg.close()
```


RSAREG800 API STRUCTURE

Global RepCaps

```
driver = RsAreg800('TCPIP::192.168.2.101::hislip0')
# HwInstance range: InstA .. InstH
rc = driver.repcap_hwInstance_get()
driver.repcap_hwInstance_set(repcap.HwInstance.InstA)
```

class RsAreg800(*resource_name: str, id_query: bool = True, reset: bool = False, options: str = None, direct_session: object = None*)

661 total commands, 20 Subgroups, 0 group commands

Initializes new RsAreg800 session.

Parameter options tokens examples:

- **Simulate=True** - starts the session in simulation mode. Default: **False**
- **SelectVisa=socket** - uses no VISA implementation for socket connections - you do not need any VISA-C installation
- **SelectVisa=rs** - forces usage of RohdeSchwarz Visa
- **SelectVisa=ivi** - forces usage of National Instruments Visa
- **QueryInstrumentStatus = False** - same as **driver.utilities.instrument_status_checking = False**. Default: **True**
- **WriteDelay = 20, ReadDelay = 5** - Introduces delay of 20ms before each write and 5ms before each read. Default: **0ms** for both
- **OpcWaitMode = OpcQuery** - mode for all the opc-synchronised write/reads. Other modes: **StbPolling, StbPollingSlow, StbPollingSuperSlow**. Default: **StbPolling**
- **AddTermCharToWriteBinBlock = True** - Adds one additional LF to the end of the binary data (some instruments require that). Default: **False**
- **AssureWriteWithTermChar = True** - Makes sure each command/query is terminated with termination character. Default: Interface dependent
- **TerminationCharacter = "\r"** - Sets the termination character for reading. Default: **\n** (LineFeed or LF)
- **DataChunkSize = 10E3** - Maximum size of one write/read segment. If transferred data is bigger, it is split to more segments. Default: **1E6** bytes
- **OpcTimeout = 10000** - same as **driver.utilities.opc_timeout = 10000**. Default: **30000ms**
- **VisaTimeout = 5000** - same as **driver.utilities.visa_timeout = 5000**. Default: **10000ms**

- `ViClearExeMode` = Disabled - `viClear()` execution mode. Default: `execute_on_all`
- `OpcQueryAfterWrite` = True - same as `driver.utilities.opc_query_after_write` = True. Default: False
- `StbInErrorCheck` = False - if true, the driver checks errors with `*STB?` If false, it uses `SYST:ERR?`. Default: True
- `ScpiQuotes` = double'. - for SCPI commands, you can define how strings are quoted. With single or double quotes. Possible values: `single` | `double` | `{char}`. Default: ```single`
- `LoggingMode` = On - Sets the logging status right from the start. Default: Off
- `LoggingName` = 'MyDevice' - Sets the name to represent the session in the log entries. Default: 'resource_name'
- `LogToGlobalTarget` = True - Sets the logging target to the class-property previously set with `RsAreg800.set_global_logging_target()` Default: False
- `LoggingToConsole` = True - Immediately starts logging to the console. Default: False
- `LoggingToUdp` = True - Immediately starts logging to the UDP port. Default: False
- `LoggingUdpPort` = 49200 - UDP port to log to. Default: 49200

Parameters

- **resource_name** – VISA resource name, e.g. 'TCPIP::192.168.2.1::INSTR'
- **id_query** – if True, the instrument's model name is verified against the models supported by the driver and eventually throws an exception.
- **reset** – Resets the instrument (sends `*RST` command) and clears its status subsystem.
- **options** – string tokens alternating the driver settings.
- **direct_session** – Another driver object or pyVisa object to reuse the session instead of opening a new session.

static `assert_minimum_version(min_version: str) → None`

Asserts that the driver version fulfills the minimum required version you have entered. This way you make sure your installed driver is of the entered version or newer.

classmethod `clear_global_logging_relative_timestamp() → None`

Clears the global relative timestamp. After this, all the instances using the global relative timestamp continue logging with the absolute timestamps.

close() → None

Closes the active RsAreg800 session.

classmethod `from_existing_session(session: object, options: str = None) → RsAreg800`

Creates a new RsAreg800 object with the entered 'session' reused.

Parameters

- **session** – can be another driver or a direct pyvisa session.
- **options** – string tokens alternating the driver settings.

classmethod `get_global_logging_relative_timestamp() → datetime`

Returns global common relative timestamp for log entries.

classmethod `get_global_logging_target()`

Returns global common target stream.

get_session_handle() → object

Returns the underlying session handle.

get_total_execution_time() → timedelta

Returns total time spent by the library on communicating with the instrument. This time is always shorter than `get_total_time()`, since it does not include gaps between the communication. You can reset this counter with `reset_time_statistics()`.

get_total_time() → timedelta

Returns total time spent by the library on communicating with the instrument. This time is always shorter than `get_total_time()`, since it does not include gaps between the communication. You can reset this counter with `reset_time_statistics()`.

static `list_resources(expression: str = '?*::INSTR', visa_select: str = None)` → List[str]

Finds all the resources defined by the expression

- `'?*' - matches all the available instruments`
- `'USB::?*' - matches all the USB instruments`
- `'TCPIP::192?*' - matches all the LAN instruments with the IP address starting with 192`

Parameters

- **expression** – see the examples in the function
- **visa_select** – optional parameter selecting a specific VISA. Examples: `'@ivi'`, `'@rs'`

reset_time_statistics() → None

Resets all execution and total time counters. Affects the results of `get_total_time()` and `get_total_execution_time()`

restore_all_repcaps_to_default() → None

Sets all the Group and Global repcaps to their initial values

classmethod `set_global_logging_relative_timestamp(timestamp: datetime)` → None

Sets global common relative timestamp for log entries. To use it, call the following:
`io.utilities.logger.set_relative_timestamp_global()`

classmethod `set_global_logging_relative_timestamp_now()` → None

Sets global common relative timestamp for log entries to this moment. To use it, call the following:
`io.utilities.logger.set_relative_timestamp_global()`.

classmethod `set_global_logging_target(target)` → None

Sets global common target stream that each instance can use. To use it, call the following:
`io.utilities.logger.set_logging_target_global()`. If an instance uses global logging target, it automatically uses the global relative timestamp (if set). You can set the target to None to invalidate it.

Subgroups

6.1 Calibration

SCPI Commands :

```
CALibration<HW>:CONTinueonerror  
CALibration<HW>:DEBug
```

class CalibrationCls

Calibration commands group definition. 24 total commands, 8 Subgroups, 2 group commands

get_continue_on_error() → bool

```
# SCPI: CALibration<HW>:CONTinueonerror  
value: bool = driver.calibration.get_continue_on_error()
```

Continues the calibration even though an error was detected. By default adjustments are aborted on error.

return
state: 1| ON| 0| OFF

set_continue_on_error(state: bool) → None

```
# SCPI: CALibration<HW>:CONTinueonerror  
driver.calibration.set_continue_on_error(state = False)
```

Continues the calibration even though an error was detected. By default adjustments are aborted on error.

param state
1| ON| 0| OFF

set_debug(state: bool) → None

```
# SCPI: CALibration<HW>:DEBug  
driver.calibration.set_debug(state = False)
```

No command help available

param state
No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently  
group2 = driver.calibration.clone()
```


Subgroups

6.1.1 All

SCPI Commands :

```
CALibration<HW>:ALL:DATE
CALibration<HW>:ALL:INformation
CALibration<HW>:ALL:TEMP
CALibration<HW>:ALL:TIME
```

class AllCls

All commands group definition. 5 total commands, 1 Subgroups, 4 group commands

get_date() → str

```
# SCPI: CALibration<HW>:ALL:DATE
value: str = driver.calibration.all.get_date()
```

Queries the date of the most recently executed full adjustment.

```
return
    date: string
```

get_information() → str

```
# SCPI: CALibration<HW>:ALL:INformation
value: str = driver.calibration.all.get_information()
```

Queries the current state of the internal adjustment.

```
return
    cal_info_text: string
```

get_temp() → str

```
# SCPI: CALibration<HW>:ALL:TEMP
value: str = driver.calibration.all.get_temp()
```

Queries the temperature deviation compared to the calibration temperature.

```
return
    temperature: string
```

get_time() → str

```
# SCPI: CALibration<HW>:ALL:TIME
value: str = driver.calibration.all.get_time()
```

Queries the time elapsed since the last full adjustment.

```
return
    time: string
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.calibration.all.clone()
```

Subgroups

6.1.1.1 Measure

SCPI Command :

```
CALibration:ALL:[MEASure]
```

class MeasureCls

Measure commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(force: str = None) → bool

```
# SCPI: CALibration:ALL:[MEASure]
value: bool = driver.calibration.all.measure.get(force = 'abc')
```

Starts all internal adjustments that do not need external measuring equipment.

param force
string

return
measure: 1| ON| 0| OFF

6.1.2 Data

SCPI Command :

```
CALibration:DATA:EXPort
```

class DataCls

Data commands group definition. 4 total commands, 2 Subgroups, 1 group commands

export() → None

```
# SCPI: CALibration:DATA:EXPort
driver.calibration.data.export()
```

Collects the internal adjustment data and provides the data for export in a zip file. You can export the data for service and evaluation purposes.

export_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: CALibration:DATA:EXPort
driver.calibration.data.export_with_opc()
```

Collects the internal adjustment data and provides the data for export in a zip file. You can export the data for service and evaluation purposes.

Same as export, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.calibration.data.clone()
```

Subgroups

6.1.2.1 Factory

SCPI Command :

```
CALibration:DATA:FACTory:DATE
```

class FactoryCls

Factory commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_date() → str

```
# SCPI: CALibration:DATA:FACTory:DATE
value: str = driver.calibration.data.factory.get_date()
```

Queries the date of the last factory calibration.

return
date: string

6.1.2.2 Update

SCPI Command :

```
CALibration<HW>:DATA:UPDate
```

class UpdateCls

Update commands group definition. 2 total commands, 1 Subgroups, 1 group commands

set_value(action_sel: CalDataUpdate) → None

```
# SCPI: CALibration<HW>:DATA:UPDate
driver.calibration.data.update.set_value(action_sel = enums.CalDataUpdate.BBFRC)
```

No command help available

param action_sel
No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.calibration.data.update.clone()
```

Subgroups

6.1.2.2.1 Level

class LevelCls

Level commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.calibration.data.update.level.clone()
```

Subgroups

6.1.2.2.1.1 Force

SCPI Command :

```
CALibration<HW>:DATA:UPDate:LEVel:FORCe
```

class ForceCls

Force commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: CALibration<HW>:DATA:UPDate:LEVel:FORCe
driver.calibration.data.update.level.force.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: CALibration<HW>:DATA:UPDate:LEVel:FORCe
driver.calibration.data.update.level.force.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.1.3 Delay

SCPI Commands :

```
CALibration:DElay:MINutes
CALibration:DElay:[MEASure]
```

class DelayCls

Delay commands group definition. 3 total commands, 1 Subgroups, 2 group commands

get_measure() → bool

```
# SCPI: CALibration:DElay:[MEASure]
value: bool = driver.calibration.delay.get_measure()
```

Starts the delayed adjustment process. When the warm-up time has elapsed (see method RsAreg800.CALibration.Delay.minutes, it executes the internal adjustments. If you have enabled automatic shutdown, CALibration:DElay:SHUTdown[:STATe] ON, the instrument shuts down when the adjustments are completed.

return
error: 1| ON| 0| OFF

get_minutes() → int

```
# SCPI: CALibration:DElay:MINutes
value: int = driver.calibration.delay.get_minutes()
```

Sets the warm-up time to wait before internal adjustment starts automatically. Automatic execution starts only, if you have enabled the calibration with command ON.

return
minutes: integer Range: 30 to 120

set_minutes(minutes: int) → None

```
# SCPI: CALibration:DElay:MINutes
driver.calibration.delay.set_minutes(minutes = 1)
```

Sets the warm-up time to wait before internal adjustment starts automatically. Automatic execution starts only, if you have enabled the calibration with command ON.

param minutes
integer Range: 30 to 120

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.calibration.delay.clone()
```

Subgroups

6.1.3.1 Shutdown

SCPI Command :

CALibration:DElay:SHUTdown: [STATe]

class ShutdownCls

Shutdown commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: CALibration:DElay:SHUTdown: [STATe]
value: bool = driver.calibration.delay.shutdown.get_state()
```

Enables the instrument to shut down automatically after calibration.

return
shutdown: 1| ON| 0| OFF

set_state(shutdown: bool) → None

```
# SCPI: CALibration:DElay:SHUTdown: [STATe]
driver.calibration.delay.shutdown.set_state(shutdown = False)
```

Enables the instrument to shut down automatically after calibration.

param shutdown
1| ON| 0| OFF

6.1.4 Frequency

SCPI Command :

CALibration:FREquency:SWPoints

class FrequencyCls

Frequency commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_sw_points() → str

```
# SCPI: CALibration:FREquency:SWPoints
value: str = driver.calibration.frequency.get_sw_points()
```

No command help available

return
freq_switch_point: No help available

set_sw_points(freq_switch_point: str) → None

```
# SCPI: CALibration:FREquency:SWPoints
driver.calibration.frequency.set_sw_points(freq_switch_point = 'abc')
```

No command help available

param freq_switch_point

No help available

6.1.5 Level

SCPI Command :

CALibration<HW>:LEVel:STATe

class LevelCls

Level commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get_state() → StateExtended

```
# SCPI: CALibration<HW>:LEVel:STATe
value: enums.StateExtended = driver.calibration.level.get_state()
```

No command help available

return

areg_cal_pow_ext_us: No help available

set_state(areg_cal_pow_ext_us: StateExtended) → None

```
# SCPI: CALibration<HW>:LEVel:STATe
driver.calibration.level.set_state(areg_cal_pow_ext_us = enums.StateExtended.
↳DEFAULT)
```

No command help available

param areg_cal_pow_ext_us

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.calibration.level.clone()
```

Subgroups

6.1.5.1 Attenuator

SCPI Command :

CALibration<HW>:LEVel:ATTenuator:STAGe

class AttenuatorCls

Attenuator commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_stage() → int

```
# SCPI: CALibration<HW>:LEVel:ATTenuator:STAGe
value: int = driver.calibration.level.attenuator.get_stage()
```

No command help available

return
stage: No help available

set_stage(stage: int) → None

```
# SCPI: CALibration<HW>:LEVel:ATTenuator:STAGe
driver.calibration.level.attenuator.set_stage(stage = 1)
```

No command help available

param stage
No help available

6.1.6 Roscillator

class RoscillatorCls

Roscillator commands group definition. 3 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.calibration.roscillator.clone()
```

Subgroups

6.1.6.1 Data

SCPI Commands :

```
CALibration:ROSCillator:DATA:MODE
CALibration:ROSCillator:[DATA]
```

class DataCls

Data commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_mode() → CalDataMode

```
# SCPI: CALibration:ROSCillator:DATA:MODE
value: enums.CalDataMode = driver.calibration.roscillator.data.get_mode()
```

No command help available

return
mode: No help available

get_value() → int

```
# SCPI: CALibration:ROSCillator:[DATA]
value: int = driver.calibration.roscillator.data.get_value()
```

No command help available

return
data: No help available

set_mode(mode: CalDataMode) → None

```
# SCPI: CALibration:ROSCillator:DATA:MODE
driver.calibration.roscillator.data.set_mode(mode = enums.CalDataMode.CUSTOMer)
```

No command help available

param mode
No help available

set_value(data: int) → None

```
# SCPI: CALibration:ROSCillator:[DATA]
driver.calibration.roscillator.data.set_value(data = 1)
```

No command help available

param data
No help available

6.1.6.2 Store

SCPI Command :

CALibration:ROSCillator:STORe

class StoreCls

Store commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: CALibration:ROSCillator:STORe
driver.calibration.roscillator.store.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: CALibration:ROSCillator:STORe
driver.calibration.roscillator.store.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms
Maximum time to wait in milliseconds, valid only for this call.

6.1.7 Selected

class SelectedCls

Selected commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.calibration.selected.clone()
```

Subgroups

6.1.7.1 Measure

SCPI Command :

```
CALibration:SElected:[MEASure]
```

class MeasureCls

Measure commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(to_test_args: str) → TestCalSelected

```
# SCPI: CALibration:SElected:[MEASure]
value: enums.TestCalSelected = driver.calibration.selected.measure.get(to_test_
↪args = 'abc')
```

No command help available

param to_test_args
No help available

return
test_result: No help available

6.1.8 Tselected

SCPI Commands :

```
CALibration:TSElected:CATalog
CALibration:TSElected:STEP
CALibration:TSElected:[MEASure]
```

class TselectedCls

Tselected commands group definition. 3 total commands, 0 Subgroups, 3 group commands

get_catalog() → str

```
# SCPI: CALibration:TSElected:CATalog
value: str = driver.calibration.tselected.get_catalog()
```

No command help available

```

return
    catalog: No help available

```

get_measure() → bool

```

# SCPI: CALibration:TSElected:[MEASure]
value: bool = driver.calibration.tselected.get_measure()

```

No command help available

```

return
    meas: No help available

```

get_step() → str

```

# SCPI: CALibration:TSElected:STEP
value: str = driver.calibration.tselected.get_step()

```

No command help available

```

return
    sel_string: No help available

```

set_step(sel_string: str) → None

```

# SCPI: CALibration:TSElected:STEP
driver.calibration.tselected.set_step(sel_string = 'abc')

```

No command help available

```

param sel_string
    No help available

```

6.2 Device

SCPI Command :

DEvice:PRESet

class DeviceCls

Device commands group definition. 3 total commands, 1 Subgroups, 1 group commands

preset() → None

```

# SCPI: DEvice:PRESet
driver.device.preset()

```

Presets all parameters which are not related to the signal path, including the LF generator.

preset_with_opc(opc_timeout_ms: int = -1) → None

```

# SCPI: DEvice:PRESet
driver.device.preset_with_opc()

```

Presets all parameters which are not related to the signal path, including the LF generator.

Same as preset, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.device.clone()
```

Subgroups

6.2.1 Settings

class SettingsCls

Settings commands group definition. 2 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.device.settings.clone()
```

Subgroups

6.2.1.1 Backup

SCPI Command :

```
DEvice:SETTings:BACKup
```

class BackupCls

Backup commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: DEvice:SETTings:BACKup
driver.device.settings.backup.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: DEvice:SETTings:BACKup
driver.device.settings.backup.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.2.1.2 Restore

SCPI Command :

```
DEVIce:SETTIngs:REStore
```

class RestoreCls

Restore commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: DEVIce:SETTIngs:REStore
driver.device.settings.restore.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: DEVIce:SETTIngs:REStore
driver.device.settings.restore.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.3 Diagnostic

class DiagnosticCls

Diagnostic commands group definition. 17 total commands, 7 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.diagnostic.clone()
```

Subgroups

6.3.1 BgInfo

SCPI Commands :

```
DIAGnostic<HW>:BGInfo
DIAGnostic<HW>:BGInfo:CATalog
```

class BgInfoCls

BgInfo commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get(board: str = None) → str

```
# SCPI: DIAGnostic<HW>:BGInfo
value: str = driver.diagnostic.bgInfo.get(board = 'abc')
```

Queries information on the modules available in the instrument, using the variant and revision state.

param board

string Module name, as queried with the command method RsAreg800.Diagnostic.BgInfo.catalog. To retrieve a complete list of all modules, omit the parameter. The length of the list is variable and depends on the instrument equipment configuration.

return

bg_info: Module name Module stock number incl. variant Module revision Module serial number List of comma-separated entries, one entry per module. Each entry for one module consists of four parts that are separated by space characters.

get_catalog() → List[str]

```
# SCPI: DIAGnostic<HW>:BGInfo:CATalog
value: List[str] = driver.diagnostic.bgInfo.get_catalog()
```

Queries the names of the assemblies available in the instrument.

return

catalog: string List of all assemblies; the values are separated by commas The length of the list is variable and depends on the instrument equipment configuration.

6.3.2 Debug

class DebugCls

Debug commands group definition. 2 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.diagnostic.debug.clone()
```

Subgroups

6.3.2.1 Page

SCPI Commands :

```
DIAGnostic<HW>:DEBug:PAGE
DIAGnostic<HW>:DEBug:PAGE:CATalog
```

class PageCls

Page commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_catalog() → List[str]

```
# SCPI: DIAGnostic<HW>:DEBug:PAGE:CATalog
value: List[str] = driver.diagnostic.debug.page.get_catalog()
```

No command help available

```
return
diag_debug_page_id_cat: No help available
```

set() → None

```
# SCPI: DIAGnostic<HW>:DEBug:PAGE
driver.diagnostic.debug.page.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: DIAGnostic<HW>:DEBug:PAGE
driver.diagnostic.debug.page.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

```
param opc_timeout_ms
Maximum time to wait in milliseconds, valid only for this call.
```

6.3.3 Eeprom<Channel>

RepCap Settings

```
# Range: Nr1 .. Nr64
rc = driver.diagnostic.eeprom.repcap_channel_get()
driver.diagnostic.eeprom.repcap_channel_set(repcap.Channel.Nr1)
```

SCPI Command :

```
DIAGnostic<HW>:EEPROM<CH>:DElete
```

class EepromCls

Eeprom commands group definition. 4 total commands, 3 Subgroups, 1 group commands Repeated Capability: Channel, default value after init: Channel.Nr1

delete(channel=Channel.Default) → None

```
# SCPI: DIAGnostic<HW>:EEPROM<CH>:DElete
driver.diagnostic.eeprom.delete(channel = repcap.Channel.Default)
```

No command help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Eeprom')

delete_with_opc(channel=Channel.Default, opc_timeout_ms: int = -1) → None

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.diagnostic.eeprom.clone()
```

Subgroups

6.3.3.1 Bidentifier

class BidentifierCls

Bidentifier commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.diagnostic.eeprom.bidentifier.clone()
```

Subgroups

6.3.3.1.1 Catalog

SCPI Command :

```
DIAGnostic<HW>:EEPROM<CH>:BIDentifier:CATalog
```

class CatalogCls

Catalog commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(board_id: List[str], channel=Channel.Default) → List[str]

```
# SCPI: DIAGnostic<HW>:EEPROM<CH>:BIDentifier:CATalog
value: List[str] = driver.diagnostic.eeprom.bidentifier.catalog.get(board_id = [
    ↪ 'abc1', 'abc2', 'abc3'], channel = repcap.Channel.Default)
```

No command help available

param board_id

No help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Eeprom')

return

board_id: No help available

6.3.3.2 Customize

SCPI Command :

```
DIAGnostic<HW>:EEPROM<CH>:CUSTomize
```

class CustomizeCls

Customize commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(board: str, index: int, sub_board: int, channel=Channel.Default) → None

```
# SCPI: DIAGnostic<HW>:EEPROM<CH>:CUSTomize
driver.diagnostic.eeprom.customize.set(board = 'abc', index = 1, sub_board = 1,
    ↪ channel = repcap.Channel.Default)
```

No command help available

param board

No help available

param index

No help available

param sub_board

No help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Eeprom')

6.3.3.3 Data

class DataCls

Data commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.diagnostic.eeprom.data.clone()
```

Subgroups

6.3.3.3.1 Points

SCPI Command :

```
DIAGnostic<HW>:EEPROM<CH>:DATA:POINTS
```

class PointsCls

Points commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(board: str, sub_board: str, channel=Channel.Default) → int

```
# SCPI: DIAGnostic<HW>:EEPROM<CH>:DATA:POINTS
value: int = driver.diagnostic.eeprom.data.points.get(board = 'abc', sub_board_
↳ 'abc', channel = repcap.Channel.Default)
```

No command help available

param board

No help available

param sub_board

No help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Eeprom')

return

points: No help available

6.3.4 Info

class InfoCls

Info commands group definition. 4 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.diagnostic.info.clone()
```

Subgroups

6.3.4.1 Otime

SCPI Commands :

```
DIAGnostic:INFO:OTIME:SET
DIAGnostic:INFO:OTIME
```

class OtimeCls

Otime commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_set() → int

```
# SCPI: DIAGnostic:INFO:OTIME:SET
value: int = driver.diagnostic.info.otime.get_set()
```

No command help available

```
return
    set_py: No help available
```

get_value() → int

```
# SCPI: DIAGnostic:INFO:OTIME
value: int = driver.diagnostic.info.otime.get_value()
```

Queries the operating hours of the instrument so far.

```
return
    operation_time: integer Range: 0 to INT_MAX
```

set_set(set_py: int) → None

```
# SCPI: DIAGnostic:INFO:OTIME:SET
driver.diagnostic.info.otime.set_set(set_py = 1)
```

No command help available

```
param set_py
    No help available
```

6.3.4.2 PoCount

SCPI Commands :

```
DIAGnostic:INFO:POCount:SET
DIAGnostic:INFO:POCount
```

class PoCountCls

PoCount commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_set() → int

```
# SCPI: DIAGnostic:INFO:POCount:SET
value: int = driver.diagnostic.info.poCount.get_set()
```

No command help available

```
return
    set_py: No help available
```

get_value() → int

```
# SCPI: DIAGnostic:INFO:POCount
value: int = driver.diagnostic.info.poCount.get_value()
```

Queris how often the instrument has been turned on so far.

```
return
    power_on_count: integer Range: 0 to INT_MAX
```

set_set(set_py: int) → None

```
# SCPI: DIAGnostic:INFO:POCount:SET
driver.diagnostic.info.poCount.set_set(set_py = 1)
```

No command help available

```
param set_py
    No help available
```

6.3.5 Measure

class MeasureCls

Measure commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.diagnostic.measure.clone()
```

Subgroups

6.3.5.1 Point

SCPI Command :

```
DIAGnostic<HW>:[MEASure]:POINT
```

class PointCls

Point commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(name: str) → str

```
# SCPI: DIAGnostic<HW>:[MEASure]:POINT
value: str = driver.diagnostic.measure.point.get(name = 'abc')
```

Triggers the voltage measurement at the specified test point and returns the measured voltage. For more information, see R&S AREG800A Service Manual.

param name

test point identifier Test point name, as queried with the command method
RsAreg800.Diagnostic.Point.catalog

return

value: valueunit

6.3.6 Point

SCPI Command :

```
DIAGnostic<HW>:POINT:CATalog
```

class PointCls

Point commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get_catalog() → List[str]

```
# SCPI: DIAGnostic<HW>:POINT:CATalog
value: List[str] = driver.diagnostic.point.get_catalog()
```

Queries the test points available in the instrument. For more information, see R&S AREG800A Service Manual.

return

catalog: string List of comma-separated values, each representing a test point

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.diagnostic.point.clone()
```

Subgroups

6.3.6.1 Configuration

SCPI Command :

```
DIAGnostic<HW>:POINT:CONfiguration
```

class ConfigurationCls

Configuration commands group definition. 1 total commands, 0 Subgroups, 1 group commands

class GetStruct

Response structure. Fields:

- Dev_Board: str: No parameter help available
- Point: str: No parameter help available

get() → GetStruct

```
# SCPI: DIAGnostic<HW>:POINT:CONfiguration
value: GetStruct = driver.diagnostic.point.configuration.get()
```

No command help available

return

structure: for return value, see the help for GetStruct structure arguments.

set(dev_board: str, point: str, data: str) → None

```
# SCPI: DIAGnostic<HW>:POINT:CONfiguration
driver.diagnostic.point.configuration.set(dev_board = 'abc', point = 'abc',
↳data = 'abc')
```

No command help available

param dev_board

No help available

param point

No help available

param data

No help available

6.3.7 Service

SCPI Commands :

```
DIAGnostic<HW>:Service:SFunction
DIAGnostic:Service
```

class ServiceCls

Service commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_sfunction() → str

```
# SCPI: DIAGnostic<HW>:Service:SFunction
value: str = driver.diagnostic.service.get_sfunction()
```

No command help available

```
return
    direct_string: No help available
```

get_value() → bool

```
# SCPI: DIAGnostic:Service
value: bool = driver.diagnostic.service.get_value()
```

No command help available

```
return
    service: No help available
```

set_sfunction(direct_string: str) → None

```
# SCPI: DIAGnostic<HW>:Service:SFunction
driver.diagnostic.service.set_sfunction(direct_string = 'abc')
```

No command help available

```
param direct_string
    No help available
```

set_value(service: bool) → None

```
# SCPI: DIAGnostic:Service
driver.diagnostic.service.set_value(service = False)
```

No command help available

```
param service
    No help available
```

6.4 Display

SCPI Commands :

```
DISPlay:BRIGhtness
DISPlay:FOCusobject
DISPlay:MESSage
```

class DisplayCls

Display commands group definition. 17 total commands, 7 Subgroups, 3 group commands

get_brightness() → float

```
# SCPI: DISPlay:BRIGhtness
value: float = driver.display.get_brightness()
```

Sets the brightness of the dispaly.

return
brightness: float Range: 1.0 to 20.0

set_brightness(brightness: float) → None

```
# SCPI: DISPlay:BRIGhtness
driver.display.set_brightness(brightness = 1.0)
```

Sets the brightness of the dispaly.

param brightness
float Range: 1.0 to 20.0

set_focus_object(obj_name: str) → None

```
# SCPI: DISPlay:FOCusobject
driver.display.set_focus_object(obj_name = 'abc')
```

No command help available

param obj_name
No help available

set_message(message: str) → None

```
# SCPI: DISPlay:MESSage
driver.display.set_message(message = 'abc')
```

No command help available

param message
No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.display.clone()
```

Subgroups

6.4.1 Annotation

SCPI Command :

```
DISPlay:ANNotation:[ALL]
```

class AnnotationCls

Annotation commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_all() → bool

```
# SCPI: DISPlay:ANNotation:[ALL]
value: bool = driver.display.annotation.get_all()
```

Displays asterisks instead of the level and frequency values in the status bar of the instrument. We recommend that you use this mode if you operate the instrument in remote control.

```
return
state: 1| ON| 0| OFF
```

set_all(state: bool) → None

```
# SCPI: DISPlay:ANNotation:[ALL]
driver.display.annotation.set_all(state = False)
```

Displays asterisks instead of the level and frequency values in the status bar of the instrument. We recommend that you use this mode if you operate the instrument in remote control.

```
param state
1| ON| 0| OFF
```

6.4.2 Button

SCPI Command :

```
DISPlay:BUtTon:BRIGhtness
```

class ButtonCls

Button commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_brightness() → int

```
# SCPI: DISPlay:BUtTon:BRIGhtness
value: int = driver.display.button.get_brightness()
```

Sets the brightness of the [RF On/Off] key.

return
button_brightnes: integer Range: 1 to 20

set_brightness(button_brightnes: int) → None

```
# SCPI: DISPlay:BUtTon:BRiGhtness
driver.display.button.set_brightness(button_brightnes = 1)
```

Sets the brightness of the [RF On/Off] key.

param button_brightnes
integer Range: 1 to 20

6.4.3 Dialog

SCPI Commands :

```
DISPlay:DIALog:CLOSe
DISPlay:DIALog:CLOSe:ALL
DISPlay:DIALog:ID
DISPlay:DIALog:OPEN
```

class DialogCls

Dialog commands group definition. 4 total commands, 0 Subgroups, 4 group commands

close(dialog_id: str) → None

```
# SCPI: DISPlay:DIALog:CLOSe
driver.display.dialog.close(dialog_id = 'abc')
```

Closes the specified dialog.

param dialog_id
string To find out the dialog identifier, use the query method RsAreg800.Display.Dialog.id. The DialogName part of the query result is sufficient.

close_all() → None

```
# SCPI: DISPlay:DIALog:CLOSe:ALL
driver.display.dialog.close_all()
```

Closes all open dialogs.

close_all_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: DISPlay:DIALog:CLOSe:ALL
driver.display.dialog.close_all_with_opc()
```

Closes all open dialogs.

Same as close_all, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

get_id() → str

```
# SCPI: DISPlay:DIALog:ID
value: str = driver.display.dialog.get_id()
```

Returns the dialog identifiers of the open dialogs in a string separated by blanks.

return

dialog_id_list: DialogID#1 DialogID#2 ... DialogID#n Dialog identifiers are string without blanks. Blanks are represented as \$. Dialog identifiers DialogID are composed of two main parts: DialogName[OptionalParts] DialogName Meaningful information, mandatory input parameter for the commands: method RsAreg800.Display.Dialog.open method RsAreg800.Display.Dialog.close Optional parts String of \$X values, where X is a character, interpreted as follows: \$qDialogQualifier: optional dialog qualifier, usually the letter A or B, as displayed in the dialog title. \$iInstances: comma-separated list of instance indexes, given in the order h,c,s,d,g,u,0. Default is zero; the terminating '0' can be omitted. \$tTabIds: comma-separated indexes or tab names; required, if a dialog is composed of several tabs. \$xLeft\$yTop\$hLeft\$wTop: position and size; superfluous information.

open(dialog_id: str) → None

```
# SCPI: DISPlay:DIALog:OPEN
driver.display.dialog.open(dialog_id = 'abc')
```

Opens the specified dialog.

param dialog_id

string To find out the dialog identifier, use the query method RsAreg800.Display.Dialog.id. The DialogName part of the query result is mandatory.

6.4.4 Psave

SCPI Commands :

```
DISPlay:PSAVe:HOLDoff
DISPlay:PSAVe:[STATe]
```

class PsaveCls

Psave commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_holdoff() → int

```
# SCPI: DISPlay:PSAVe:HOLDoff
value: int = driver.display.psave.get_holdoff()
```

Sets the wait time for the screen saver mode of the display.

return

holdoff_time_min: integer Range: 1 to 60, Unit: minute

get_state() → bool

```
# SCPI: DISPLAY:PSAVE:[STATE]
value: bool = driver.display.psave.get_state()
```

Activates the screen saver mode of the display. We recommend that you use this mode to protect the display, if you operate the instrument in remote control. To define the wait time, use the command method RsAreg800.Display.Psave.holdoff.

return
state: 1| ON| 0| OFF

set_holdoff(holdoff_time_min: int) → None

```
# SCPI: DISPLAY:PSAVE:HOLDoff
driver.display.psave.set_holdoff(holdoff_time_min = 1)
```

Sets the wait time for the screen saver mode of the display.

param holdoff_time_min
integer Range: 1 to 60, Unit: minute

set_state(state: bool) → None

```
# SCPI: DISPLAY:PSAVE:[STATE]
driver.display.psave.set_state(state = False)
```

Activates the screen saver mode of the display. We recommend that you use this mode to protect the display, if you operate the instrument in remote control. To define the wait time, use the command method RsAreg800.Display.Psave.holdoff.

param state
1| ON| 0| OFF

6.4.5 Touch

class TouchCls

Touch commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.display.touch.clone()
```

Subgroups

6.4.5.1 Time

SCPI Command :

```
DISPlay:TOUCh:TIME:CHARge
```

class TimeCls

Time commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set_charge(*charge_time: int*) → None

```
# SCPI: DISPlay:TOUCh:TIME:CHARge
driver.display.touch.time.set_charge(charge_time = 1)
```

No command help available

param charge_time

No help available

6.4.6 Ukey

SCPI Commands :

```
DISPlay:UKEY:NAME
DISPlay:UKEY:SCPI
```

class UkeyCls

Ukey commands group definition. 3 total commands, 1 Subgroups, 2 group commands

set_name(*name: str*) → None

```
# SCPI: DISPlay:UKEY:NAME
driver.display.ukey.set_name(name = 'abc')
```

No command help available

param name

No help available

set_scpi(*scpi: str*) → None

```
# SCPI: DISPlay:UKEY:SCPI
driver.display.ukey.set_scpi(scpi = 'abc')
```

No command help available

param scpi

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.display.ukey.clone()
```

Subgroups

6.4.6.1 Add

SCPI Command :

```
DISPlay:UKEY:ADD
```

class AddCls

Add commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: DISPlay:UKEY:ADD
driver.display.ukey.add.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: DISPlay:UKEY:ADD
driver.display.ukey.add.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.4.7 Update

SCPI Commands :

```
DISPlay:UPDate:HOLD
DISPlay:UPDate:[STATe]
```

class UpdateCls

Update commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_hold() → bool

```
# SCPI: DISPlay:UPDate:HOLD
value: bool = driver.display.update.get_hold()
```

No command help available

return

hold: No help available

get_state() → bool

```
# SCPI: DISPlay:UPDate:[STATe]
value: bool = driver.display.update.get_state()
```

Activates the refresh mode of the display.

return

update: 1| ON| 0| OFF

set_hold(hold: bool) → None

```
# SCPI: DISPlay:UPDate:HOLD
driver.display.update.set_hold(hold = False)
```

No command help available

param hold

No help available

set_state(update: bool) → None

```
# SCPI: DISPlay:UPDate:[STATe]
driver.display.update.set_state(update = False)
```

Activates the refresh mode of the display.

param update

1| ON| 0| OFF

6.5 FormatPy

SCPI Commands :

```
FORMat:BORDER
FORMat:SREGister
FORMat:[DATA]
```

class FormatPyCls

FormatPy commands group definition. 3 total commands, 0 Subgroups, 3 group commands

get_border() → ByteOrder

```
# SCPI: FORMat:BORDER
value: enums.ByteOrder = driver.formatPy.get_border()
```

Determines the sequence of bytes within a binary block. This only affects blocks which use the IEEE754 format internally.

return

border: NORMal| SWAPped NORMal Expects/sends the least significant byte of each

IEEE754 floating-point number first and the most significant byte last. SWAPped Expects/sends the most significant byte of each IEEE754 floating-point number first and the least significant byte last.

get_data() → *FormData*

```
# SCPI: FORMat:[DATA]
value: enums.FormData = driver.formatPy.get_data()
```

Determines the data format the instrument uses to return data via the IEC/IEEE bus. The instrument automatically detects the data format used by the controller, and assigns it accordingly. Data format determined by this SCPI command is in this case irrelevant.

return

data: ASCII| PACKed ASCII Transfers numerical data as plain text separated by commas. PACKed Transfers numerical data as binary block data. The format within the binary data depends on the command. The various binary data formats are explained in the description of the parameter types.

get_sregister() → *FormStatReg*

```
# SCPI: FORMat:SREGister
value: enums.FormStatReg = driver.formatPy.get_sregister()
```

Determines the numeric format for responses of the status register.

return

format_py: ASCII| BINary| HEXadecimal| OCTal ASCII Returns the register content as a decimal number. BINary|HEXadecimal|OCTal Returns the register content either as a binary, hexadecimal or octal number. According to the selected format, the number starts with #B (binary) , #H (hexadecimal) or #O (octal) .

set_border(*border: ByteOrder*) → *None*

```
# SCPI: FORMat:BORDER
driver.formatPy.set_border(border = enums.ByteOrder.NORMAL)
```

Determines the sequence of bytes within a binary block. This only affects blocks which use the IEEE754 format internally.

param border

NORMAL| SWAPped NORMAL Expects/sends the least significant byte of each IEEE754 floating-point number first and the most significant byte last. SWAPped Expects/sends the most significant byte of each IEEE754 floating-point number first and the least significant byte last.

set_data(*data: FormData*) → *None*

```
# SCPI: FORMat:[DATA]
driver.formatPy.set_data(data = enums.FormData.ASCII)
```

Determines the data format the instrument uses to return data via the IEC/IEEE bus. The instrument automatically detects the data format used by the controller, and assigns it accordingly. Data format determined by this SCPI command is in this case irrelevant.

param data

ASCII| PACKed ASCII Transfers numerical data as plain text separated by commas. PACKed Transfers numerical data as binary block data. The format within the binary

data depends on the command. The various binary data formats are explained in the description of the parameter types.

set_sregister(*format_py: FormStatReg*) → None

```
# SCPI: FORMat:SREgister
driver.formatPy.set_sregister(format_py = enums.FormStatReg.ASCii)
```

Determines the numeric format for responses of the status register.

param format_py

ASCii| BINary| HEXadecimal| OCTal ASCii Returns the register content as a decimal number. BINary|HEXadecimal|OCTal Returns the register content either as a binary, hexadecimal or octal number. According to the selected format, the number starts with #B (binary) , #H (hexadecimal) or #O (octal) .

6.6 Fpanel

class FpanelCls

Fpanel commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.fpanel.clone()
```

Subgroups

6.6.1 Keyboard

SCPI Command :

```
FPANel:KEYBoard:LAYout
```

class KeyboardCls

Keyboard commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_layout() → FrontPanelLayout

```
# SCPI: FPANel:KEYBoard:LAYout
value: enums.FrontPanelLayout = driver.fpanel.keyboard.get_layout()
```

No command help available

return

layout: No help available

set_layout(*layout: FrontPanelLayout*) → None

```
# SCPI: FPANel:KEYBoard:LAYout
driver.fpanel.keyboard.set_layout(layout = enums.FrontPanelLayout.DIGits)
```

No command help available

param layout

No help available

6.7 HardCopy

SCPI Commands :

```
HCOPY:DATA  
HCOPY:REGION
```

class HardCopyCls

HardCopy commands group definition. 17 total commands, 4 Subgroups, 2 group commands

get_data() → bytes

```
# SCPI: HCOpy:DATA  
value: bytes = driver.hardCopy.get_data()
```

Transfers the hard copy data directly as a NByte stream to the remote client.

return
data: block data

get_region() → HardCopyRegion

```
# SCPI: HCOpy:REGION  
value: enums.HardCopyRegion = driver.hardCopy.get_region()
```

Selects the area to be copied. You can create a snapshot of the screen or an active dialog.

return
region: ALL|DIALOG

set_region(region: HardCopyRegion) → None

```
# SCPI: HCOpy:REGION  
driver.hardCopy.set_region(region = enums.HardCopyRegion.ALL)
```

Selects the area to be copied. You can create a snapshot of the screen or an active dialog.

param region
ALL|DIALOG

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.hardCopy.clone()
```

Subgroups

6.7.1 Device

SCPI Command :

```
HCOPy:DEVIce:LANGuage
```

class DeviceCls

Device commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_language() → HardCopyImageFormat

```
# SCPI: HCOPy:DEVIce:LANGuage
value: enums.HardCopyImageFormat = driver.hardCopy.device.get_language()
```

Selects the graphic format for the hard copy. You can use both commands alternatively.

```
return
    language: BMP|JPG|XPM|PNG
```

set_language(language: HardCopyImageFormat) → None

```
# SCPI: HCOPy:DEVIce:LANGuage
driver.hardCopy.device.set_language(language = enums.HardCopyImageFormat.BMP)
```

Selects the graphic format for the hard copy. You can use both commands alternatively.

```
param language
    BMP|JPG|XPM|PNG
```

6.7.2 Execute

SCPI Command :

```
HCOPy:[EXECute]
```

class ExecuteCls

Execute commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: HCOPy:[EXECute]
driver.hardCopy.execute.set()
```

Generates a hard copy of the current display. The output destination is a file.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: HCOpy:[EXECute]
driver.hardCopy.execute.set_with_opc()
```

Generates a hard copy of the current display. The output destination is a file.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.7.3 File

class FileCls

File commands group definition. 12 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.hardCopy.file.clone()
```

Subgroups

6.7.3.1 Name

SCPI Command :

```
HCOPY:FILE:[NAME]
```

class NameCls

Name commands group definition. 12 total commands, 1 Subgroups, 1 group commands

get_value() → str

```
# SCPI: HCOpy:FILE:[NAME]
value: str = driver.hardCopy.file.name.get_value()
```

Determines the file name and path to save the hard copy, provided automatic naming is disabled. Note: If you have enabled automatic naming, the instrument automatically generates the file name and directory, see 'Automatic naming'.

return

name: string

set_value(name: str) → None

```
# SCPI: HCOpy:FILE:[NAME]
driver.hardCopy.file.name.set_value(name = 'abc')
```

Determines the file name and path to save the hard copy, provided automatic naming is disabled. Note: If you have enabled automatic naming, the instrument automatically generates the file name and directory, see 'Automatic naming'.

param name
string

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.hardCopy.file.name.clone()
```

Subgroups

6.7.3.1.1 Auto

SCPI Commands :

```
HCOPY:FILE:[NAME]:AUTO:STATE
HCOPY:FILE:[NAME]:AUTO
```

class AutoCls

Auto commands group definition. 11 total commands, 2 Subgroups, 2 group commands

get_state() → bool

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:STATE
value: bool = driver.hardCopy.file.name.auto.get_state()
```

Activates automatic naming of the hard copy files.

return
state: 1| ON| 0| OFF

get_value() → str

```
# SCPI: HCOpy:FILE:[NAME]:AUTO
value: str = driver.hardCopy.file.name.auto.get_value()
```

Queries path and file name of the hardcopy file, if you have enabled Automatic Naming.

return
auto: string

set_state(state: bool) → None

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:STATE
driver.hardCopy.file.name.auto.set_state(state = False)
```

Activates automatic naming of the hard copy files.

param state
1| ON| 0| OFF

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.hardCopy.file.name.auto.clone()
```

Subgroups

6.7.3.1.1.1 Directory

SCPI Commands :

```
HCOPY:FILE:[NAME]:AUTO:DIRectory:CLEar
HCOPY:FILE:[NAME]:AUTO:DIRectory
```

class DirectoryCls

Directory commands group definition. 2 total commands, 0 Subgroups, 2 group commands

clear() → None

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:DIRectory:CLEar
driver.hardCopy.file.name.auto.directory.clear()
```

Deletes all files with extensions *.bmp, *.jpg, *.png and *.xpm in the directory set for automatic naming.

clear_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:DIRectory:CLEar
driver.hardCopy.file.name.auto.directory.clear_with_opc()
```

Deletes all files with extensions *.bmp, *.jpg, *.png and *.xpm in the directory set for automatic naming.

Same as clear, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

get_value() → str

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:DIRectory
value: str = driver.hardCopy.file.name.auto.directory.get_value()
```

Determines the path to save the hard copy, if you have enabled Automatic Naming. If the directory does not yet exist, the instrument automatically creates a new directory, using the instrument name and /var/user/ by default.

return

directory: string

set_value(directory: str) → None

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:DIRectory
driver.hardCopy.file.name.auto.directory.set_value(directory = 'abc')
```

Determines the path to save the hard copy, if you have enabled Automatic Naming. If the directory does not yet exist, the instrument automatically creates a new directory, using the instrument name and /var/user/ by default.

param directory
string

6.7.3.1.1.2 File

SCPI Commands :

```
HCOPY:FILE:[NAME]:AUTO:[FILE]:NUMBER
HCOPY:FILE:[NAME]:AUTO:FILE
```

class FileCls

File commands group definition. 7 total commands, 4 Subgroups, 2 group commands

get_number() → int

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:NUMBER
value: int = driver.hardCopy.file.name.auto.file.get_number()
```

Queries the number that is used as part of the file name for the next hard copy in automatic mode. At the beginning, the count starts at 0. The R&S AREG800A searches the specified output directory for the highest number in the stored files. It increases this number by one to achieve a unique name for the new file. The resulting auto number is appended to the resulting file name with at least three digits.

return
number: integer Range: 0 to 999999

get_value() → str

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:FILE
value: str = driver.hardCopy.file.name.auto.file.get_value()
```

Queries the name of the automatically named hard copy file. An automatically generated file name consists of: <Prefix><YYYY><MM><DD><Number>.<Format>. You can activate each component separately, to individually design the file name.

return
file: string

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.hardCopy.file.name.auto.file.clone()
```

Subgroups

6.7.3.1.1.3 Day

SCPI Command :

```
HCOPY:FILE:[NAME]:AUTO:[FILE]:DAY:STATe
```

class DayCls

Day commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:DAY:STATe
value: bool = driver.hardCopy.file.name.auto.file.day.get_state()
```

Uses the date parameters (year, month or day) for the automatic naming. You can activate each of the date parameters separately.

return
state: 1| ON| 0| OFF

set_state(state: bool) → None

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:DAY:STATe
driver.hardCopy.file.name.auto.file.day.set_state(state = False)
```

Uses the date parameters (year, month or day) for the automatic naming. You can activate each of the date parameters separately.

param state
1| ON| 0| OFF

6.7.3.1.1.4 Month

SCPI Command :

```
HCOPY:FILE:[NAME]:AUTO:[FILE]:MONTH:STATe
```

class MonthCls

Month commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:MONTH:STATe
value: bool = driver.hardCopy.file.name.auto.file.month.get_state()
```

Uses the date parameters (year, month or day) for the automatic naming. You can activate each of the date parameters separately.

return
state: 1| ON| 0| OFF

set_state(state: bool) → None

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:MONTH:STATe
driver.hardCopy.file.name.auto.file.month.set_state(state = False)
```

Uses the date parameters (year, month or day) for the automatic naming. You can activate each of the date parameters separately.

param state
1| ON| 0| OFF

6.7.3.1.1.5 Prefix

SCPI Commands :

```
HCOpy:FILE:[NAME]:AUTO:[FILE]:PREFIX:STATe
HCOpy:FILE:[NAME]:AUTO:[FILE]:PREFIX
```

class PrefixCls

Prefix commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_state() → bool

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:PREFIX:STATe
value: bool = driver.hardCopy.file.name.auto.file.prefix.get_state()
```

Uses the prefix for the automatic generation of the file name, provided PREF:STAT is activated.

return
state: 1| ON| 0| OFF

get_value() → str

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:PREFIX
value: str = driver.hardCopy.file.name.auto.file.prefix.get_value()
```

Uses the prefix for the automatic generation of the file name, provided PREF:STAT is activated.

return
prefix: No help available

set_state(state: bool) → None

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:PREFIX:STATe
driver.hardCopy.file.name.auto.file.prefix.set_state(state = False)
```

Uses the prefix for the automatic generation of the file name, provided PREF:STAT is activated.

param state
1| ON| 0| OFF

set_value(prefix: str) → None

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:PREFIX
driver.hardCopy.file.name.auto.file.prefix.set_value(prefix = 'abc')
```

Uses the prefix for the automatic generation of the file name, provided PREF:STAT is activated.

param prefix
1| ON| 0| OFF

6.7.3.1.1.6 Year

SCPI Command :

HCOPY:FILE:[NAME]:AUTO:[FILE]:YEAR:STATE

class YearCls

Year commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:YEAR:STATE
value: bool = driver.hardCopy.file.name.auto.file.year.get_state()
```

Uses the date parameters (year, month or day) for the automatic naming. You can activate each of the date parameters separately.

return
state: 1| ON| 0| OFF

set_state(state: bool) → None

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:YEAR:STATE
driver.hardCopy.file.name.auto.file.year.set_state(state = False)
```

Uses the date parameters (year, month or day) for the automatic naming. You can activate each of the date parameters separately.

param state
1| ON| 0| OFF

6.7.4 Image

SCPI Command :

HCOPY:IMAGE:FORMAT

class ImageCls

Image commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_format_py() → HardCopyImageFormat

```
# SCPI: HCOpy:IMAGE:FORMAT
value: enums.HardCopyImageFormat = driver.hardCopy.image.get_format_py()
```

Selects the graphic format for the hard copy. You can use both commands alternatively.

return
format_py: No help available

set_format_py(format_py: *HardCopyImageFormat*) → None

```
# SCPI: HCOpy:IMAGe:FORMat
driver.hardCopy.image.set_format_py(format_py = enums.HardCopyImageFormat.BMP)
```

Selects the graphic format for the hard copy. You can use both commands alternatively.

param format_py
BMP|JPG|XPM|PNG

6.8 Initiate<Channel>

RepCap Settings

```
# Range: Nr1 .. Nr64
rc = driver.initiate.repcap_channel_get()
driver.initiate.repcap_channel_set(repcap.Channel.Nr1)
```

class InitiateCls

Initiate commands group definition. 1 total commands, 1 Subgroups, 0 group commands Repeated Capability: Channel, default value after init: Channel.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.initiate.clone()
```

Subgroups

6.8.1 Power

class PowerCls

Power commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.initiate.power.clone()
```

Subgroups

6.8.1.1 Continuous

SCPI Command :

```
INITiate<HW>:[POWer]:CONTinuous
```

class ContinuousCls

Continuous commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → bool

```
# SCPI: INITiate<HW>:[POWer]:CONTinuous
value: bool = driver.initiate.power.continuous.get(channel = repcap.Channel.
↳Default)
```

Switches the local state of the continuous power measurement by R&S NRP power sensors on and off. Switching off local state enhances the measurement performance during remote control. The remote measurement is triggered with method **RsAreg800.Read.Power.get_()**. This command also returns the measurement results. The local state is not affected, measurement results can be retrieved with local state on or off.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Initiate')

return

continuous: 1| ON| 0| OFF

set(continuous: bool, channel=Channel.Default) → None

```
# SCPI: INITiate<HW>:[POWer]:CONTinuous
driver.initiate.power.continuous.set(continuous = False, channel = repcap.
↳Channel.Default)
```

Switches the local state of the continuous power measurement by R&S NRP power sensors on and off. Switching off local state enhances the measurement performance during remote control. The remote measurement is triggered with method **RsAreg800.Read.Power.get_()**. This command also returns the measurement results. The local state is not affected, measurement results can be retrieved with local state on or off.

param continuous

1| ON| 0| OFF

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Initiate')

6.9 Kboard

SCPI Command :

KBOard:LAYout

class KboardCls

Kboard commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_layout() → KbLayout

```
# SCPI: KBOard:LAYout
value: enums.KbLayout = driver.kboard.get_layout()
```

Selects the language for an external keyboard and assigns the keys accordingly.

return

layout: CHINese| DANish| DUTCh| DUTBe| ENGLish| ENGUK| FINNish| FRENch| FREBe| FRECa| GERMan| ITALian| JAPanese| KOREan| NORWegian| PORTuguese| RUSSian| SPANish| SWEDish| ENGUS

set_layout(layout: KbLayout) → None

```
# SCPI: KBOard:LAYout
driver.kboard.set_layout(layout = enums.KbLayout.CHINese)
```

Selects the language for an external keyboard and assigns the keys accordingly.

param layout

CHINese| DANish| DUTCh| DUTBe| ENGLish| ENGUK| FINNish| FRENch| FREBe| FRECa| GERMan| ITALian| JAPanese| KOREan| NORWegian| PORTuguese| RUSSian| SPANish| SWEDish| ENGUS

6.10 MassMemory

SCPI Commands :

```
MMEMory:CDIRectory
MMEMory:COPY
MMEMory:DELeTe
MMEMory:DRIVes
MMEMory:MDIRectory
MMEMory:MOVE
MMEMory:MSIS
MMEMory:RDIRectory
MMEMory:RDIRectory:RECURSive
```

class MassMemoryCls

MassMemory commands group definition. 15 total commands, 4 Subgroups, 9 group commands

copy(source_file: str, destination_file: str) → None

```
# SCPI: MMEMory:COpy
driver.massMemory.copy(source_file = 'abc', destination_file = 'abc')
```

Copies an existing file to a new file. Instead of just a file, this command can also be used to copy a complete directory together with all its files.

param source_file

string String containing the path and file name of the source file

param destination_file

string String containing the path and name of the target file. The path can be relative or absolute. If DestinationFile is not specified, the SourceFile is copied to the current directory, queried with the method RsAreg800.MassMemory.currentDirectory command. Note: Existing files with the same name in the destination directory are overwritten without an error message.

delete(filename: str) → None

```
# SCPI: MMEMory:DElete
driver.massMemory.delete(filename = 'abc')
```

Removes a file from the specified directory.

param filename

string String parameter to specify the name and directory of the file to be removed.

delete_directory(directory: str) → None

```
# SCPI: MMEMory:RDIRECTory
driver.massMemory.delete_directory(directory = 'abc')
```

Removes an empty directory from the mass memory storage system. If no directory is specified, the subdirectory with the specified name is deleted in the default directory. To remove a directory with contents, use command method RsAreg800.MassMemory.deleteDirectoryRecursive.

param directory

string String parameter to specify the directory to be deleted.

delete_directory_recursive(directory: str) → None

```
# SCPI: MMEMory:RDIRECTory:RECURSive
driver.massMemory.delete_directory_recursive(directory = 'abc')
```

Removes the specified directory, including files and subdirectories from the mass memory storage system. If no directory is specified, the command removes the subdirectories of the default directory. The command the entire directory without further prompt or notification.

param directory

string String parameter to specify the directory to be deleted.

get_current_directory() → str

```
# SCPI: MMEMory:CDIRECTory
value: str = driver.massMemory.get_current_directory()
```

Changes the default directory for mass memory storage. The directory is used for all subsequent MMEM commands if no path is specified with them.

return

directory: directory_name String containing the path to another directory. The path can be relative or absolute. To change to a higher directory, use two dots '..'.

get_drives() → str

```
# SCPI: MMEemory:DRIVES
value: str = driver.massMemory.get_drives()
```

No command help available

return

drive_list: No help available

get_msis() → str

```
# SCPI: MMEemory:MSIS
value: str = driver.massMemory.get_msis()
```

Defines the drive or network resource (in the case of networks) for instruments with windows operating system, using msis (MSIS = Mass Storage Identification String) . Note: Instruments with Linux operating system ignore this command, since Linux does not use drive letter assignment.

return

path: No help available

make_directory(directory: str) → None

```
# SCPI: MMEemory:MDIRECTORY
driver.massMemory.make_directory(directory = 'abc')
```

Creates a subdirectory for mass memory storage in the specified directory. If no directory is specified, a subdirectory is created in the default directory. This command can also be used to create a directory tree.

param directory

string String parameter to specify the new directory.

move(source_file: str, destination_file: str) → None

```
# SCPI: MMEemory:MOVE
driver.massMemory.move(source_file = 'abc', destination_file = 'abc')
```

Moves an existing file to a new location or, if no path is specified, renames an existing file.

param source_file

string String parameter to specify the name of the file to be moved.

param destination_file

string String parameters to specify the name of the new file.

set_current_directory(directory: str) → None

```
# SCPI: MMEemory:CDIRECTORY
driver.massMemory.set_current_directory(directory = 'abc')
```

Changes the default directory for mass memory storage. The directory is used for all subsequent MMEM commands if no path is specified with them.

param directory

directory_name String containing the path to another directory. The path can be relative or absolute. To change to a higher directory, use two dots '..' .

set_msis(path: str) → None

```
# SCPI: MMEemory:MSIS
driver.massMemory.set_msis(path = 'abc')
```

Defines the drive or network resource (in the case of networks) for instruments with windows operating system, using msis (MSIS = Mass Storage Identification String) . Note: Instruments with Linux operating system ignore this command, since Linux does not use drive letter assignment.

param path

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.massMemory.clone()
```

Subgroups

6.10.1 Catalog

SCPI Command :

```
MMEemory:CATalog
```

class CatalogCls

Catalog commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get_value() → str

```
# SCPI: MMEemory:CATalog
value: str = driver.massMemory.catalog.get_value()
```

Returns the content of a particular directory.

return

catalog: No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.massMemory.catalog.clone()
```


Subgroups

6.10.1.1 Length

SCPI Command :

```
MMEMory:CATalog:LENGth
```

class LengthCls

Length commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(path: str = None) → int

```
# SCPI: MMEMory:CATalog:LENGth
value: int = driver.massMemory.catalog.length.get(path = 'abc')
```

Returns the number of files in the current or in the specified directory.

param path

string String parameter to specify the directory. If the directory is omitted, the command queries the content of the current directory, queried with method RsAreg800.MassMemory.currentDirectory command.

return

file_count: integer Number of files.

6.10.2 Dcatalog

SCPI Command :

```
MMEMory:DCATalog
```

class DcatalogCls

Dcatalog commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get_value() → str

```
# SCPI: MMEMory:DCATalog
value: str = driver.massMemory.dcatalog.get_value()
```

Returns the subdirectories of a particular directory.

return

dcatalog: No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.massMemory.dcatalog.clone()
```

Subgroups

6.10.2.1 Length

SCPI Command :

```
MMEMory:DCATalog:LENGth
```

class LengthCls

Length commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(path: str = None) → int

```
# SCPI: MMEMory:DCATalog:LENGth
value: int = driver.massMemory.dcatalog.length.get(path = 'abc')
```

Returns the number of subdirectories in the current or specified directory.

param path

String parameter to specify the directory. If the directory is omitted, the command queries the contents of the current directory, to be queried with method RsAreg800.MassMemory.currentDirectory command.

return

directory_count: integer Number of parent and subdirectories.

6.10.3 Load

class LoadCls

Load commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.massMemory.load.clone()
```

Subgroups

6.10.3.1 State

SCPI Command :

```
MMEMory:LOAD:STATe
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(data_set: int, source_file: str) → None

```
# SCPI: MMEMory:LOAD:STATe
driver.massMemory.load.state.set(data_set = 1, source_file = 'abc')
```

Loads the specified file stored under the specified name in an internal memory. After the file has been loaded, the instrument setting must be activated using an **RCL* command.

param data_set
No help available

param source_file
No help available

6.10.4 Store

class StoreCls

Store commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.massMemory.store.clone()
```

Subgroups

6.10.4.1 State

SCPI Command :

```
MMEMory:STORe:STATe
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(data_set: int, destination_file: str) → None

```
# SCPI: MMEMory:STORe:STATe
driver.massMemory.store.state.set(data_set = 1, destination_file = 'abc')
```

Stores the current instrument setting in the specified file. The instrument setting must first be stored in an internal memory with the same number using the common command **SAV*.

param data_set

No help available

param destination_file

No help available

6.11 Memory

SCPI Command :

MEMory:HFRee

class MemoryCls

Memory commands group definition. 1 total commands, 0 Subgroups, 1 group commands

class HfreeStruct

Structure for reading output parameters. Fields:

- Total_Phys_Mem_Kb: List[int]: integer Total physical memory.
- Applic_Mem_Kb: int: integer Application memory.
- Heap_Used_Kb: int: integer Used heap memory.
- Heap_Available_Kb: int: integer Available heap memory.

get_hfree() → HfreeStruct

```
# SCPI: MEMory:HFRee
value: HfreeStruct = driver.memory.get_hfree()
```

Returns the used and available memory in Kb.

return

structure: for return value, see the help for HfreeStruct structure arguments.

6.12 Output

class OutputCls

Output commands group definition. 2 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.output.clone()
```

Subgroups

6.12.1 User<UserIx>

RepCap Settings

```
# Range: Nr1 .. Nr48
rc = driver.output.user.repcap_userIx_get()
driver.output.user.repcap_userIx_set(repcap.UserIx.Nr1)
```

class UserCls

User commands group definition. 2 total commands, 2 Subgroups, 0 group commands Repeated Capability: UserIx, default value after init: UserIx.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.output.user.clone()
```

Subgroups

6.12.1.1 Direction

SCPI Command :

```
OUTPut<HW>:USER<CH>:DIRection
```

class DirectionCls

Direction commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(userIx=UserIx.Default) → ConnDirection

```
# SCPI: OUTPut<HW>:USER<CH>:DIRection
value: enums.ConnDirection = driver.output.user.direction.get(userIx = repcap.
↳UserIx.Default)
```

No command help available

param userIx

optional repeated capability selector. Default value: Nr1 (settable in the interface 'User')

return

direction: No help available

set(*direction: ConnDirection, userIx=UserIx.Default*) → None

```
# SCPI: OUTPut<HW>:USER<CH>:DIRection
driver.output.user.direction.set(direction = enums.ConnDirection.INPut, userIx =
↳repcap.UserIx.Default)
```

No command help available

param direction

No help available

param userIx

optional repeated capability selector. Default value: Nr1 (settable in the interface 'User')

6.12.1.2 Signal

SCPI Command :

```
OUTPut<HW>:USER<CH>:SIGNa1
```

class SignalCls

Signal commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*userIx=UserIx.Default*) → OutpConnGlbSignalAreg800A

```
# SCPI: OUTPut<HW>:USER<CH>:SIGNa1
value: enums.OutpConnGlbSignalAreg800A = driver.output.user.signal.get(userIx =
↳repcap.UserIx.Default)
```

Selects the signal marker for the connector.

param userIx

optional repeated capability selector. Default value: Nr1 (settable in the interface 'User')

return

signal: Object Object A marker signal is generated when an object setting event occurs.

set(*signal: OutpConnGlbSignalAreg800A, userIx=UserIx.Default*) → None

```
# SCPI: OUTPut<HW>:USER<CH>:SIGNa1
driver.output.user.signal.set(signal = enums.OutpConnGlbSignalAreg800A.Object,
↳userIx = repcap.UserIx.Default)
```

Selects the signal marker for the connector.

param signal

Object Object A marker signal is generated when an object setting event occurs.

param userIx

optional repeated capability selector. Default value: Nr1 (settable in the interface 'User')

6.13 Read<Channel>

RepCap Settings

```
# Range: Nr1 .. Nr64
rc = driver.read.repcap_channel_get()
driver.read.repcap_channel_set(repcap.Channel.Nr1)
```

class ReadCls

Read commands group definition. 1 total commands, 1 Subgroups, 0 group commands Repeated Capability: Channel, default value after init: Channel.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.read.clone()
```

Subgroups

6.13.1 Power

SCPI Command :

```
READ<CH>:[POWer]
```

class PowerCls

Power commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → List[float]

```
# SCPI: READ<CH>:[POWer]
value: List[float] = driver.read.power.get(channel = repcap.Channel.Default)
```

Triggers power measurement and displays the results. Note: This command does not affect the local state, i.e. you can get results with local state on or off. For long measurement times, we recommend that you use an SRQ for command synchronization (MAV bit) .

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Read')

return

power: float or float,float The sensor returns the result in the unit set with command method RsAreg800.Sense.Unit.Power.set Certain power sensors, such as the R&S NRP-Z81, return two values, first the value of the average level and - separated by a comma - the peak value.

6.14 Sense<Channel>

RepCap Settings

```
# Range: Nr1 .. Nr64
rc = driver.sense.repcap_channel_get()
driver.sense.repcap_channel_set(repcap.Channel.Nr1)
```

class SenseCls

Sense commands group definition. 25 total commands, 2 Subgroups, 0 group commands Repeated Capability: Channel, default value after init: Channel.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.clone()
```

Subgroups

6.14.1 Power

class PowerCls

Power commands group definition. 24 total commands, 14 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.clone()
```

Subgroups

6.14.1.1 Aperture

class ApertureCls

Aperture commands group definition. 2 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.aperture.clone()
```


Subgroups

6.14.1.1.1 Default

class DefaultCls

Default commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.aperture.default.clone()
```

Subgroups

6.14.1.1.1.1 State

SCPI Command :

```
SENSe<CH>:[POWer]:APERture:DEFault:STATe
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → bool

```
# SCPI: SENSE<CH>:[POWer]:APERture:DEFault:STATe
value: bool = driver.sense.power.aperture.default.state.get(channel = repcap.
↳ Channel.Default)
```

Deactivates the default aperture time of the respective sensor. To specify a user-defined value, use the command method RsAreg800.Sense.Power.Aperture.Time.set.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

use_def_ap: 1| ON| 0| OFF

set(use_def_ap: bool, channel=Channel.Default) → None

```
# SCPI: SENSE<CH>:[POWer]:APERture:DEFault:STATe
driver.sense.power.aperture.default.state.set(use_def_ap = False, channel =
↳ repcap.Channel.Default)
```

Deactivates the default aperture time of the respective sensor. To specify a user-defined value, use the command method RsAreg800.Sense.Power.Aperture.Time.set.

param use_def_ap

1| ON| 0| OFF

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.14.1.1.2 Time

SCPI Command :

```
SENSe<CH>:[POWer]:APERture:TIME
```

class TimeCls

Time commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → float

```
# SCPI: SENSE<CH>:[POWer]:APERture:TIME
value: float = driver.sense.power.aperture.time.get(channel = repcap.Channel.
↳Default)
```

Defines the aperture time (size of the acquisition interval) for the corresponding sensor.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

ap_time: float Range: depends on connected power sensor

set(ap_time: float, channel=Channel.Default) → None

```
# SCPI: SENSE<CH>:[POWer]:APERture:TIME
driver.sense.power.aperture.time.set(ap_time = 1.0, channel = repcap.Channel.
↳Default)
```

Defines the aperture time (size of the acquisition interval) for the corresponding sensor.

param ap_time

float Range: depends on connected power sensor

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.14.1.2 Correction

class CorrectionCls

Correction commands group definition. 3 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.correction.clone()
```

Subgroups

6.14.1.2.1 SpDevice

class SpDeviceCls

SpDevice commands group definition. 3 total commands, 3 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.correction.spDevice.clone()
```

Subgroups

6.14.1.2.1.1 ListPy

SCPI Command :

```
SENSe<CH>:[POWer]:CORRection:SPDevice:LIST
```

class ListPyCls

ListPy commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → List[str]

```
# SCPI: SENSE<CH>:[POWer]:CORRection:SPDevice:LIST
value: List[str] = driver.sense.power.correction.spDevice.listPy.get(channel =
↳repcap.Channel.Default)
```

Queries the list of the S-parameter data sets that have been loaded to the power sensor.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

list_py: string list

6.14.1.2.1.2 Select

SCPI Command :

```
SENSe<CH>:[POWer]:CORRection:SPDevice:SElect
```

class SelectCls

Select commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → float

```
# SCPI: SENSE<CH>:[POWer]:CORRection:SPDevice:SElect
value: float = driver.sense.power.correction.spDevice.select.get(channel = ↵
↵repcap.Channel.Default)
```

Several S-parameter tables can be stored in a sensor. The command selects a loaded data set for S-parameter correction for the corresponding sensor.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

select: float

set(select: float, channel=Channel.Default) → None

```
# SCPI: SENSE<CH>:[POWer]:CORRection:SPDevice:SElect
driver.sense.power.correction.spDevice.select.set(select = 1.0, channel = ↵
↵repcap.Channel.Default)
```

Several S-parameter tables can be stored in a sensor. The command selects a loaded data set for S-parameter correction for the corresponding sensor.

param select

float

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.14.1.2.1.3 State

SCPI Command :

```
SENSe<CH>:[POWer]:CORRection:SPDevice:STATe
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → bool

```
# SCPI: SENSE<CH>:[POWer]:CORRection:SPDevice:STATe
value: bool = driver.sense.power.correction.spDevice.state.get(channel = ↵
↵Channel.Default)
```

Activates the use of the S-parameter correction data. Note: If you use power sensors with attenuator, the instrument automatically activates the use of S-parameter data.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

state: 1| ON| 0| OFF

set(state: bool, channel=Channel.Default) → None

```
# SCPI: SENSE<CH>:[POWer]:CORRection:SPDevice:STATE
driver.sense.power.correction.spDevice.state.set(state = False, channel =
↳repcap.Channel.Default)
```

Activates the use of the S-parameter correction data. Note: If you use power sensors with attenuator, the instrument automatically activates the use of S-parameter data.

param state

1| ON| 0| OFF

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.14.1.3 Direct

SCPI Command :

```
SENSe<CH>:[POWer]:DIRect
```

class DirectCls

Direct commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(command: str, channel=Channel.Default) → None

```
# SCPI: SENSE<CH>:[POWer]:DIRect
driver.sense.power.direct.set(command = 'abc', channel = repcap.Channel.Default)
```

No command help available

param command

No help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.14.1.4 Display

class DisplayCls

Display commands group definition. 2 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.display.clone()
```

Subgroups

6.14.1.4.1 Permanent

class PermanentCls

Permanent commands group definition. 2 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.display.permanent.clone()
```

Subgroups

6.14.1.4.1.1 Priority

SCPI Command :

```
SENSe<CH>:[POWer]:DISPlay:PERManent:PRIority
```

class PriorityCls

Priority commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → PowSensDisplayPriority

```
# SCPI: SENSe<CH>:[POWer]:DISPlay:PERManent:PRIority
value: enums.PowSensDisplayPriority = driver.sense.power.display.permanent.
↳ priority.get(channel = repcap.Channel.Default)
```

Selects average or peak power for permanent display.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

priority: AVERage|PEAK

set(priority: PowSensDisplayPriority, channel=Channel.Default) → None

```
# SCPI: SENSe<CH>:[POWer]:DISPlay:PERManent:PRIority
driver.sense.power.display.permanent.priority.set(priority = enums.
↳ PowSensDisplayPriority.AVERage, channel = repcap.Channel.Default)
```

Selects average or peak power for permanent display.

param priority

AVERage|PEAK

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.14.1.4.1.2 State

SCPI Command :

```
SENSe<CH>:[POWer]:DISPlay:PERManent:STATe
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*channel=Channel.Default*) → bool

```
# SCPI: SENSe<CH>:[POWer]:DISPlay:PERManent:STATe
value: bool = driver.sense.power.display.permanent.state.get(channel = repcap.
↳Channel.Default)
```

Activates the permanent display of the measured power level results. The instrument also indicates the sensor type, the connection, the measurement source and the offset if set.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

state: 1| ON| 0| OFF

set(*state: bool, channel=Channel.Default*) → None

```
# SCPI: SENSe<CH>:[POWer]:DISPlay:PERManent:STATe
driver.sense.power.display.permanent.state.set(state = False, channel = repcap.
↳Channel.Default)
```

Activates the permanent display of the measured power level results. The instrument also indicates the sensor type, the connection, the measurement source and the offset if set.

param state

1| ON| 0| OFF

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.14.1.5 FilterPy

class FilterPyCls

FilterPy commands group definition. 6 total commands, 4 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.filterPy.clone()
```

Subgroups

6.14.1.5.1 Length

class LengthCls

Length commands group definition. 2 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.filterPy.length.clone()
```

Subgroups

6.14.1.5.1.1 Auto

SCPI Command :

```
SENSe<CH>:[POWer]:FILTer:LENGth:AUTO
```

class AutoCls

Auto commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → float

```
# SCPI: SENSe<CH>:[POWer]:FILTer:LENGth:AUTO
value: float = driver.sense.power.filterPy.length.auto.get(channel = repcap.
↳ Channel.Default)
```

Queries the current filter length in filter mode AUTO (method RsAreg800.Sense.Power.FilterPy.TypePy.set)

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

auto: float Range: 1 to 65536

6.14.1.5.1.2 User

SCPI Command :

```
SENSe<CH>:[POWer]:FILTer:LENGth:[USER]
```

class UserCls

User commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → float

```
# SCPI: SENSE<CH>:[POWer]:FILTer:LENGth:[USER]
value: float = driver.sense.power.filterPy.length.user.get(channel = repcap.
↳Channel.Default)
```

Selects the filter length for SENS:POW:FILT:’TYPE USER. As the filter length works as a multiplier for the time window, a constant filter length results in a constant measurement time (see also ‘About the measuring principle, averaging filter, filter length, and achieving stable results’).

INTRO_CMD_HELP: The R&S NRP power sensors provide different resolutions for setting the filter length, depending on the used sensor type:

- Resolution = 1 for R&S NRPxx power sensors
- Resolution = 2n for sensors of the R&S NRP-Zxx family, with n = 1 to 16

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Sense’)

return

user: float Range: 1 to 65536

set(user: float, channel=Channel.Default) → None

```
# SCPI: SENSE<CH>:[POWer]:FILTer:LENGth:[USER]
driver.sense.power.filterPy.length.user.set(user = 1.0, channel = repcap.
↳Channel.Default)
```

Selects the filter length for SENS:POW:FILT:’TYPE USER. As the filter length works as a multiplier for the time window, a constant filter length results in a constant measurement time (see also ‘About the measuring principle, averaging filter, filter length, and achieving stable results’).

INTRO_CMD_HELP: The R&S NRP power sensors provide different resolutions for setting the filter length, depending on the used sensor type:

- Resolution = 1 for R&S NRPxx power sensors
- Resolution = 2n for sensors of the R&S NRP-Zxx family, with n = 1 to 16

param user

float Range: 1 to 65536

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Sense’)

6.14.1.5.2 NsRatio

SCPI Command :

```
SENSe<CH>:[POWer]:FILTer:NSRatio
```

class NsRatioCls

NsRatio commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get(channel=Channel.Default) → float

```
# SCPI: SENSE<CH>:[POWer]:FILTer:NSRatio
value: float = driver.sense.power.filterPy.nsRatio.get(channel = repcap.Channel.
↳Default)
```

Sets an upper limit for the relative noise content in fixed noise filter mode (method RsAreg800.Sense.Power.FilterPy. TypePy.set) . This value determines the proportion of intrinsic noise in the measurement results.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

ns_ratio: float Range: 0.001 to 1

set(ns_ratio: float, channel=Channel.Default) → None

```
# SCPI: SENSE<CH>:[POWer]:FILTer:NSRatio
driver.sense.power.filterPy.nsRatio.set(ns_ratio = 1.0, channel = repcap.
↳Channel.Default)
```

Sets an upper limit for the relative noise content in fixed noise filter mode (method RsAreg800.Sense.Power.FilterPy. TypePy.set) . This value determines the proportion of intrinsic noise in the measurement results.

param ns_ratio

float Range: 0.001 to 1

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.filterPy.nsRatio.clone()
```

Subgroups

6.14.1.5.2.1 Mtime

SCPI Command :

```
SENSe<CH>:[POWer]:FILTer:NSRatio:MTIME
```

class MtimeCls

Mtime commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → float

```
# SCPI: SENSE<CH>:[POWer]:FILTer:NSRatio:MTIME
value: float = driver.sense.power.filterPy.nsRatio.mtime.get(channel = repcap.
↳Channel.Default)
```

Sets an upper limit for the settling time of the auto-averaging filter in the NSRatio mode and thus limits the length of the filter. The filter type is set with command method RsAreg800.Sense.Power.FilterPy.TypePy.set.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

mtime: float Range: 1 to 999.99

set(mtime: float, channel=Channel.Default) → None

```
# SCPI: SENSE<CH>:[POWer]:FILTer:NSRatio:MTIME
driver.sense.power.filterPy.nsRatio.mtime.set(mtime = 1.0, channel = repcap.
↳Channel.Default)
```

Sets an upper limit for the settling time of the auto-averaging filter in the NSRatio mode and thus limits the length of the filter. The filter type is set with command method RsAreg800.Sense.Power.FilterPy.TypePy.set.

param mtime

float Range: 1 to 999.99

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.14.1.5.3 Sonce

SCPI Command :

```
SENSe<CH>:[POWer]:FILTer:SONCe
```

class SonceCls

Sonce commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(*channel=Channel.Default*) → None

```
# SCPI: SENSE<CH>:[POWer]:FILTer:SONCe
driver.sense.power.filterPy.sonce.set(channel = repcap.Channel.Default)
```

Starts searching the optimum filter length for the current measurement conditions. You can check the result with command SENS1:POW:FILT:LENG:USER? in filter mode USER (method RsAreg800.Sense.Power.FilterPy.TypePy.set) .

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

set_with_opc(*channel=Channel.Default, opc_timeout_ms: int = -1*) → None

6.14.1.5.4 TypePy

SCPI Command :

```
SENSe<CH>:[POWer]:FILTer:TYPE
```

class TypePyCls

TypePy commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*channel=Channel.Default*) → PowSensFiltType

```
# SCPI: SENSE<CH>:[POWer]:FILTer:TYPE
value: enums.PowSensFiltType = driver.sense.power.filterPy.typePy.get(channel = repcap.Channel.Default)
```

Selects the filter mode. The filter length is the multiplier for the time window and thus directly affects the measurement time.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

type_py: AUTO| USER| NSRatio AUTO Automatically selects the filter length, depending on the measured value. The higher the power, the shorter the filter length, and vice versa. USER Allows you to set the filter length manually. As the filter-length takes effect as a multiplier of the measurement time, you can achieve constant measurement times. NSRatio Selects the filter length (averaging factor) according to the criterion that the intrinsic noise of the sensor (2 standard deviations) does not exceed the specified noise content. You can define the noise content with command method RsAreg800.Sense.Power.FilterPy.NsRatio.set. Note: To avoid long settling times when the power is low, you can limit the averaging factor limited with the 'time-out' parameter (method RsAreg800.Sense.Power.FilterPy.NsRatio.Mtime.set) .

set(*type_py: PowSensFiltType, channel=Channel.Default*) → None

```
# SCPI: SENSE<CH>:[POWer]:FILTer:TYPE
driver.sense.power.filterPy.typePy.set(type_py = enums.PowSensFiltType.AUTO, channel = repcap.Channel.Default)
```

Selects the filter mode. The filter length is the multiplier for the time window and thus directly affects the measurement time.

param type_py

AUTO| USER| NSRatio AUTO Automatically selects the filter length, depending on the measured value. The higher the power, the shorter the filter length, and vice versa. USER Allows you to set the filter length manually. As the filter-length takes effect as a multiplier of the measurement time, you can achieve constant measurement times. NSRatio Selects the filter length (averaging factor) according to the criterion that the intrinsic noise of the sensor (2 standard deviations) does not exceed the specified noise content. You can define the noise content with command method RsAreg800.Sense.Power.FilterPy.NsRatio.set. Note: To avoid long settling times when the power is low, you can limit the averaging factor limited with the 'time-out' parameter (method RsAreg800.Sense.Power.FilterPy.NsRatio.Mtime.set) .

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.14.1.6 Frequency

SCPI Command :

```
SENSe<CH>:[POWer]:FREQuency
```

class FrequencyCls

Frequency commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → float

```
# SCPI: SENSe<CH>:[POWer]:FREQuency
value: float = driver.sense.power.frequency.get(channel = repcap.Channel.
↳Default)
```

Sets the RF frequency of the signal, if signal source SENSe<ch>:[POWer]:SOURce USER is selected.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

frequency: float

set(frequency: float, channel=Channel.Default) → None

```
# SCPI: SENSe<CH>:[POWer]:FREQuency
driver.sense.power.frequency.set(frequency = 1.0, channel = repcap.Channel.
↳Default)
```

Sets the RF frequency of the signal, if signal source SENSe<ch>:[POWer]:SOURce USER is selected.

param frequency

float

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.14.1.7 Logging

class LoggingCls

Logging commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.logging.clone()
```

Subgroups

6.14.1.7.1 State

SCPI Command :

```
SENSe<CH>:[POWer]:LOGGing:STATe
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → bool

```
# SCPI: SENSe<CH>:[POWer]:LOGGing:STATe
value: bool = driver.sense.power.logging.state.get(channel = repcap.Channel.
↳Default)
```

Activates the recording of the power values, measured by a connected R&S NRP power sensor.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

state: 1| ON| 0| OFF

set(state: bool, channel=Channel.Default) → None

```
# SCPI: SENSe<CH>:[POWer]:LOGGing:STATe
driver.sense.power.logging.state.set(state = False, channel = repcap.Channel.
↳Default)
```

Activates the recording of the power values, measured by a connected R&S NRP power sensor.

param state

1| ON| 0| OFF

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.14.1.8 Offset

SCPI Command :

```
SENSe<CH>:[POWer]:OFFSet
```

class OffsetCls

Offset commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get(channel=Channel.Default) → float

```
# SCPI: SENSe<CH>:[POWer]:OFFSet
value: float = driver.sense.power.offset.get(channel = repcap.Channel.Default)
```

Sets a level offset which is added to the measured level value after activation with command method RsAreg800.Sense.Power. Offset.State.set. The level offset allows, e.g. to consider an attenuator in the signal path.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

offset: float Range: -100.0 to 100.0, Unit: dB

set(offset: float, channel=Channel.Default) → None

```
# SCPI: SENSe<CH>:[POWer]:OFFSet
driver.sense.power.offset.set(offset = 1.0, channel = repcap.Channel.Default)
```

Sets a level offset which is added to the measured level value after activation with command method RsAreg800.Sense.Power. Offset.State.set. The level offset allows, e.g. to consider an attenuator in the signal path.

param offset

float Range: -100.0 to 100.0, Unit: dB

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.offset.clone()
```

Subgroups

6.14.1.8.1 State

SCPI Command :

SENSe<CH>:[POWer]:OFFSet:STATe

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → bool

```
# SCPI: SENSE<CH>:[POWer]:OFFSet:STATe
value: bool = driver.sense.power.offset.state.get(channel = repcap.Channel.
↳Default)
```

Activates the addition of the level offset to the measured value. The level offset value is set with command method RsAreg800.Sense.Power.Offset.set.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

state: 1| ON| 0| OFF

set(state: bool, channel=Channel.Default) → None

```
# SCPI: SENSE<CH>:[POWer]:OFFSet:STATe
driver.sense.power.offset.state.set(state = False, channel = repcap.Channel.
↳Default)
```

Activates the addition of the level offset to the measured value. The level offset value is set with command method RsAreg800.Sense.Power.Offset.set.

param state

1| ON| 0| OFF

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.14.1.9 Snumber

SCPI Command :

SENSe<CH>:[POWer]:SNUMber

class SnumberCls

Snumber commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*channel=Channel.Default*) → str

```
# SCPI: SENSE<CH>:[POWer]:SNUMber
value: str = driver.sense.power.snumber.get(channel = repcap.Channel.Default)
```

Queries the serial number of the sensor.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

snumber: string

6.14.1.10 Source

SCPI Command :

```
SENSe<CH>:[POWer]:SOURce
```

class SourceCls

Source commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*channel=Channel.Default*) → ErFpowSensSourceAreg

```
# SCPI: SENSE<CH>:[POWer]:SOURce
value: enums.ErFpowSensSourceAreg = driver.sense.power.source.get(channel =
↳ repcap.Channel.Default)
```

Determines the signal to be measured. Note: When measuring the RF signal, the sensor considers the corresponding correction factor at that frequency, and uses the level setting of the instrument as reference level.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

source: USER

set(*source: ErFpowSensSourceAreg, channel=Channel.Default*) → None

```
# SCPI: SENSE<CH>:[POWer]:SOURce
driver.sense.power.source.set(source = enums.ErFpowSensSourceAreg.USER, channel_
↳ repcap.Channel.Default)
```

Determines the signal to be measured. Note: When measuring the RF signal, the sensor considers the corresponding correction factor at that frequency, and uses the level setting of the instrument as reference level.

param source

USER

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.14.1.11 Status

class StatusCls

Status commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.status.clone()
```

Subgroups

6.14.1.11.1 Device

SCPI Command :

```
SENSe<CH>:[POWer]:STATus:[DEVIce]
```

class DeviceCls

Device commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → bool

```
# SCPI: SENSE<CH>:[POWer]:STATus:[DEVIce]
value: bool = driver.sense.power.status.device.get(channel = repcap.Channel.
↳Default)
```

Queries if a sensor is connected to the instrument.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

status: 1| ON| 0| OFF

6.14.1.12 Sversion

SCPI Command :

```
SENSe<CH>:[POWer]:SVERsion
```

class SversionCls

Sversion commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → str

```
# SCPI: SENSE<CH>:[POWer]:SVERsion
value: str = driver.sense.power.sversion.get(channel = repcap.Channel.Default)
```

No command help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

sversion: No help available

6.14.1.13 TypePy**SCPI Command :**

```
SENSe<CH>:[POWer]:TYPE
```

class TypePyCls

TypePy commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → str

```
# SCPI: SENSe<CH>:[POWer]:TYPE
value: str = driver.sense.power.typePy.get(channel = repcap.Channel.Default)
```

Queries the sensor type. The type is automatically detected.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

type_py: string

6.14.1.14 Zero**SCPI Command :**

```
SENSe<CH>:[POWer]:ZERO
```

class ZeroCls

Zero commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(channel=Channel.Default) → None

```
# SCPI: SENSe<CH>:[POWer]:ZERO
driver.sense.power.zero.set(channel = repcap.Channel.Default)
```

Performs zeroing of the sensor. Zeroing is required after warm-up, i.e. after connecting the sensor. Note: Switch off or disconnect the RF power source from the sensor before zeroing.

INTRO_CMD_HELP: We recommend that you zero in regular intervals (at least once a day) , if:

- The temperature has varied more than about 5 Deg.
- The sensor has been replaced.
- You want to measure very low power.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

set_with_opc(channel=Channel.Default, opc_timeout_ms: int = -1) → None

6.14.2 Unit

class UnitCls

Unit commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.unit.clone()
```

Subgroups

6.14.2.1 Power

SCPI Command :

```
SENSe<CH>:UNIT:[POWer]
```

class PowerCls

Power commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → UnitPowSens

```
# SCPI: SENSe<CH>:UNIT:[POWer]
value: enums.UnitPowSens = driver.sense.unit.power.get(channel = repcap.Channel.
↳Default)
```

Selects the unit (Watt, dBm or dBuV) of measurement result display, queried with method **RsAreg800.Read.Power.get_**.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

power: DBM| DBUV| WATT

set(power: UnitPowSens, channel=Channel.Default) → None

```
# SCPI: SENSe<CH>:UNIT:[POWer]
driver.sense.unit.power.set(power = enums.UnitPowSens.DBM, channel = repcap.
↳Channel.Default)
```

Selects the unit (Watt, dBm or dBuV) of measurement result display, queried with method **RsAreg800.Read.Power.get_**.

param power

DBM| DBUV| WATT

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.15 Slist

SCPI Commands :

```
SLISt:CLEAr:[ALL]
SLISt:[LIST]
```

class SlistCls

Slist commands group definition. 9 total commands, 4 Subgroups, 2 group commands

clear_all() → None

```
# SCPI: SLISt:CLEAr:[ALL]
driver.slist.clear_all()
```

Removes all R&S NRP power sensors from the list.

clear_all_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SLISt:CLEAr:[ALL]
driver.slist.clear_all_with_opc()
```

Removes all R&S NRP power sensors from the list.

Same as clear_all, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

get_list_py() → List[str]

```
# SCPI: SLISt:[LIST]
value: List[str] = driver.slist.get_list_py()
```

Returns a list of all detected sensors in a comma-separated string.

return

sensor_list: String of comma-separated entries Each entry contains information on the sensor type, serial number and interface. The order of the entries does not correspond to the order the sensors are displayed in the 'NRP Sensor Mapping' dialog.

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.slist.clone()
```

Subgroups

6.15.1 Clear

class ClearCls

Clear commands group definition. 2 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.slist.clear.clone()
```

Subgroups

6.15.1.1 Lan

SCPI Command :

```
SLISt:CLEAr:LAN
```

class LanCls

Lan commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SLISt:CLEAr:LAN
driver.slist.clear.lan.set()
```

Removes all R&S NRP power sensors connected in the LAN from the list.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SLISt:CLEAr:LAN
driver.slist.clear.lan.set_with_opc()
```

Removes all R&S NRP power sensors connected in the LAN from the list.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.15.1.2 Usb

SCPI Command :

```
SLIST:CLEar:USB
```

class UsbCls

Usb commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SLIST:CLEar:USB
driver.slist.clear.usb.set()
```

Removes all R&S NRP power sensors connected over USB from the list.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SLIST:CLEar:USB
driver.slist.clear.usb.set_with_opc()
```

Removes all R&S NRP power sensors connected over USB from the list.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.15.2 Element<Channel>

RepCap Settings

```
# Range: Nr1 .. Nr64
rc = driver.slist.element.repcap_channel_get()
driver.slist.element.repcap_channel_set(repcap.Channel.Nr1)
```

class ElementCls

Element commands group definition. 1 total commands, 1 Subgroups, 0 group commands Repeated Capability: Channel, default value after init: Channel.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.slist.element.clone()
```

Subgroups

6.15.2.1 Mapping

SCPI Command :

```
SLIST:ELEMENT<CH>:MAPPING
```

class MappingCls

Mapping commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*channel=Channel.Default*) → ErFpowSensMapping

```
# SCPI: SLIST:ELEMENT<CH>:MAPPING
value: enums.ErFpowSensMapping = driver.slist.element.mapping.get(channel = ↵
↵repcap.Channel.Default)
```

Assigns an entry from the method RsAreg800.Slist.listPy to one of the four sensor channels.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Element’)

return

mapping: SENS1| SENSor1| SENS2| SENSor2| SENS3| SENSor3| SENS4| SENSor4| UNMapped Sensor channel.

set(*mapping: ErFpowSensMapping, channel=Channel.Default*) → None

```
# SCPI: SLIST:ELEMENT<CH>:MAPPING
driver.slist.element.mapping.set(mapping = enums.ErFpowSensMapping.SENS1, ↵
↵channel = repcap.Channel.Default)
```

Assigns an entry from the method RsAreg800.Slist.listPy to one of the four sensor channels.

param mapping

SENS1| SENSor1| SENS2| SENSor2| SENS3| SENSor3| SENS4| SENSor4| UNMapped Sensor channel.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Element’)

6.15.3 Scan

SCPI Commands :

```
SLIST:SCAN:LENSor
SLIST:SCAN:[STATe]
```

class ScanCls

Scan commands group definition. 3 total commands, 1 Subgroups, 2 group commands

get_state() → bool

```
# SCPI: SLISt:SCAN:[STAtE]
value: bool = driver.slist.scan.get_state()
```

Starts the search for R&S NRP power sensors, connected in the LAN or via the USBTMC protocol.

return
state: 1| ON| 0| OFF

set_lsensor(ip: str) → None

```
# SCPI: SLISt:SCAN:LENSor
driver.slist.scan.set_lsensor(ip = 'abc')
```

Scans for R&S NRP power sensors connected in the LAN.

param ip
string

set_state(state: bool) → None

```
# SCPI: SLISt:SCAN:[STAtE]
driver.slist.scan.set_state(state = False)
```

Starts the search for R&S NRP power sensors, connected in the LAN or via the USBTMC protocol.

param state
1| ON| 0| OFF

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.slist.scan.clone()
```

Subgroups

6.15.3.1 Usensor

SCPI Command :

```
SLISt:SCAN:USENSor
```

class UsensorCls

Usensor commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(device_id: str, serial: int) → None

```
# SCPI: SLISt:SCAN:USENSor
driver.slist.scan.usensor.set(device_id = 'abc', serial = 1)
```

Scans for R&S NRP power sensors connected over a USB interface.

param device_id
String or Integer Range: 0 to 999999

param serial
integer Range: 0 to 999999

6.15.4 Sensor

class SensorCls

Sensor commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.slist.sensor.clone()
```

Subgroups

6.15.4.1 Map

SCPI Command :

```
SLISt:SENSor:MAP
```

class MapCls

Map commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(sensor_id: str, mapping: ErFpowSensMapping) → None

```
# SCPI: SLISt:SENSor:MAP
driver.slist.sensor.map.set(sensor_id = 'abc', mapping = enums.
↳ErFpowSensMapping.SENS1)
```

Assigns a sensor directly to one of the sensor channels, using the sensor name and serial number. To find out the the sensor name and ID, you can get it from the label of the R&S NRP, or using the command method RsAreg800.Slist.Scan.state. This command detects all R&S NRP power sensors connected in the LAN or via 'USBTMC protocol.

param sensor_id
string

param mapping
enum

6.16 Source

SCPI Command :

```
SOURce<HW>:PRESet
```

class SourceCls

Source commands group definition. 281 total commands, 7 Subgroups, 1 group commands

preset() → None

```
# SCPI: SOURCE<HW>:PRESet
driver.source.preset()
```

Presets all parameters which are related to the selected signal path.

preset_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SOURCE<HW>:PRESet
driver.source.preset_with_opc()
```

Presets all parameters which are related to the selected signal path.

Same as preset, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.clone()
```

Subgroups

6.16.1 AreGenerator

class AreGeneratorCls

AreGenerator commands group definition. 258 total commands, 17 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.clone()
```

Subgroups

6.16.1.1 Channel

SCPI Commands :

```
[SOURCE<HW>]:AREGenerator:CHANnel:BW
[SOURCE<HW>]:AREGenerator:CHANnel:CATalog
[SOURCE<HW>]:AREGenerator:CHANnel:ID
[SOURCE<HW>]:AREGenerator:CHANnel:NAME
[SOURCE<HW>]:AREGenerator:CHANnel:[STATe]
```

class ChannelCls

Channel commands group definition. 13 total commands, 6 Subgroups, 5 group commands

get_bw() → AregCconfigBw

```
# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:BW
value: enums.AregCconfigBw = driver.source.areGenerator.channel.get_bw()
```

Queries the channel bandwidth. The channel bandwidth depends on the installed options.

```
return
    areg_chan_bw: BW1G| BW2G| BW5G BW1G Bandwidth = 1 GHz BW1G2 Band-
    width = 2 GHz BW5G Bandwidth = 5 GHz
```

get_catalog() → List[str]

```
# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:CATalog
value: List[str] = driver.source.areGenerator.channel.get_catalog()
```

Queries the available channels and lists the respective channel IDs.

```
return
    areg_cconf_cat: No help available
```

get_id() → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:ID
value: str = driver.source.areGenerator.channel.get_id()
```

Displays the identification name of the radar channel. The radar channel is designated with a letter and a number, e.g. 'A1'.

```
return
    areg_chan_id: string
```

get_name() → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:NAME
value: str = driver.source.areGenerator.channel.get_name()
```

Sets the alias of the radar channel, that is the channel name.

```
return
    areg_channel_name: string
```

get_state() → bool

```
# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:[STATe]
value: bool = driver.source.areGenerator.channel.get_state()
```

Acitvates the radar channel.

```
return
    areg_chan_state: 1| ON| 0| OFF
```

set_name(areg_channel_name: str) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:NAME
driver.source.areGenerator.channel.set_name(areg_channel_name = 'abc')
```

Sets the alias of the radar channel, that is the channel name.

```
param areg_channel_name
    string
```

```
set_state(areg_chan_state: bool) → None
```

```
# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:[STAtE]
driver.source.areGenerator.channel.set_state(areg_chan_state = False)
```

Activates the radar channel.

```
param areg_chan_state
    1| ON| 0| OFF
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.channel.clone()
```

Subgroups

6.16.1.1.1 Condition

SCPI Commands :

```
[SOURCE<HW>]:AREGenerator:CHANnel:CONDition:INFO
[SOURCE<HW>]:AREGenerator:CHANnel:CONDition
```

class ConditionCls

Condition commands group definition. 2 total commands, 0 Subgroups, 2 group commands

```
get_info() → str
```

```
# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:CONDition:INFO
value: str = driver.source.areGenerator.channel.condition.get_info()
```

Displays a status message for the input power for the related radar channel.

```
return
    areg_pow_led_info: string
```

```
get_value() → AregPIEd
```

```
# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:CONDition
value: enums.AregPIEd = driver.source.areGenerator.channel.condition.get_value()
```

Displays the status of the power LED for the related radar channel.

```
return
    areg_pow_led_statu: INActive| WARNing| ERRor| OK INActive
    The channel is inactive. The power LED lights grey.
    WARNing Displays a warning for the channel. The power LED lights yellow.
    ERRor Displays an error for the channel. The power LED lights red.
    OK The channel is active and works properly. The power LED lights green.
```

set_info(areg_pow_led_info: str) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:CONDition:INFO
driver.source.areGenerator.channel.condition.set_info(areg_pow_led_info = 'abc')
```

Displays a status message for the input power for the related radar channel.

param areg_pow_led_info
string

set_value(areg_pow_led_statu: AregPIEd) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:CONDition
driver.source.areGenerator.channel.condition.set_value(areg_pow_led_statu =   
↳enums.AregPIEd.ERROR)
```

Displays the status of the power LED for the related radar channel.

param areg_pow_led_statu
INActive| WARNIng| ERRor| OK INActive The channel is inactive. The power LED lights grey. WARNIng Displays a warning for the channel. The power LED lights yellow. ERRor Displays an error for the channel. The power LED lights red. OK The channel is active and works properly. The power LED lights green.

6.16.1.1.2 InputPy

SCPI Commands :

```
[SOURCE<HW>]:AREGenerator:CHANnel:INPut:NOMGain  
[SOURCE<HW>]:AREGenerator:CHANnel:INPut:RELLevel
```

class InputPyCls

InputPy commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_nom_gain() → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:INPut:NOMGain
value: float = driver.source.areGenerator.channel.inputPy.get_nom_gain()
```

Sets a value to adjust the input gain of the channel manually. The R&S AREG800A sets the nominal input gain automatically by using the [:SOURCE<hw>]:AREGenerator:MAPPING<ch>:ADJUST:LEVEL function in the channel mapping. You can set the input gain manually, for example to restore the value.

return
areg_chan_nom_gain: float Range: -50 to 35

get_rel_level() → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:INPut:RELLevel
value: float = driver.source.areGenerator.channel.inputPy.get_rel_level()
```

Queries the actual input level of the analog to digital converter of the R&S AREG800A in relation to full scale. This value is the maximum measured during the defined [:SOURCE<hw>]:AREGenerator:MAPPING<ch>:ADJUST:LEVEL:OTIME (observation time for peak detection) . If the value is not steady enough, we recommend prolonging the observation time.

```

    return
    areg_chan_rel_lev: float Range: -50 to 35

set_nom_gain(areg_chan_nom_gain: float) → None

```

```

# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:INPut:NOMGain
driver.source.areGenerator.channel.inputPy.set_nom_gain(areg_chan_nom_gain = 1.
↪0)

```

Sets a value to adjust the input gain of the channel manually. The R&S AREG800A sets the nominal input gain automatically by using the [:SOURCE<hw>]:AREGenerator:MAPPING<ch>:ADJUST:LEVEL function in the channel mapping. You can set the input gain manually, for example to restore the value.

```

param areg_chan_nom_gain
    float Range: -50 to 35

```

6.16.1.1.3 Level

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:CHANnel:LEVEL:MEASured
```

class LevelCls

Level commands group definition. 1 total commands, 0 Subgroups, 1 group commands

```
get_measured() → float
```

```

# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:LEVEL:MEASured
value: float = driver.source.areGenerator.channel.level.get_measured()

```

No command help available

```

return
    areg_chan_level: No help available

```

6.16.1.1.4 Optimization

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:CHANnel:OPTimization:MODE
```

class OptimizationCls

Optimization commands group definition. 1 total commands, 0 Subgroups, 1 group commands

```
get_mode() → AregCconfigOptMode
```

```

# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:OPTimization:MODE
value: enums.AregCconfigOptMode = driver.source.areGenerator.channel.
↪optimization.get_mode()

```

Selects the optimization mode of the radar channel.

return

areg_chan_mode: FAST| QHIG FAST Fast optimization mode This mode compensates I/Q skews and is suitable in time sensitive environments and for narrowband signals. QHIG High-quality optimization mode This mode compensates I/Q skews and uses frequency response correction data. The mode generates flat signals over large bandwidth but requires longer setting time and leads to signal interruption.

set_mode(areg_chan_mode: AregCconfigOptMode) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:OPTimization:MODE
driver.source.areGenerator.channel.optimization.set_mode(areg_chan_mode = enums.
↪AregCconfigOptMode.FAST)
```

Selects the optimization mode of the radar channel.

param areg_chan_mode

FAST| QHIG FAST Fast optimization mode This mode compensates I/Q skews and is suitable in time sensitive environments and for narrowband signals. QHIG High-quality optimization mode This mode compensates I/Q skews and uses frequency response correction data. The mode generates flat signals over large bandwidth but requires longer setting time and leads to signal interruption.

6.16.1.1.5 Output**SCPI Command :**

```
[SOURCE<HW>]:AREGenerator:CHANnel:OUTPut:NOMGain
```

class OutputCls

Output commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_nom_gain() → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:OUTPut:NOMGain
value: float = driver.source.areGenerator.channel.output.get_nom_gain()
```

No command help available

return

areg_chan_nom_gain: No help available

set_nom_gain(areg_chan_nom_gain: float) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:OUTPut:NOMGain
driver.source.areGenerator.channel.output.set_nom_gain(areg_chan_nom_gain = 1.0)
```

No command help available

param areg_chan_nom_gain

No help available

6.16.1.1.6 System

SCPI Command :

```
[SOURce<HW>]:AREGenerator:CHANnel:SYSTem:ALIGnment
```

class SystemCls

System commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_alignment() → AregCconfigSystAlign

```
# SCPI: [SOURce<HW>]:AREGenerator:CHANnel:SYSTem:ALIGnment
value: enums.AregCconfigSystAlign = driver.source.areGenerator.channel.system.
↪get_alignment()
```

Enables the system alignment If the required option is available in the pre-configured system.

return

syst_align: OFF| TABLE| ON OFF Default state. No option installed. System alignment is not used. ON Requires R&S AREG8 -B97. System alignment is executed. All frontends included in the test setup are mapped according to the factory alignment. TABLE Requires R&S AREG8 -B98. System alignment is executed. Same mapping as for state'ON'. In addition, you can define a table of certain center frequencies and bandwidths for an additional alignment procedure which has an increased level linearity. The definitions in the table limit the possible settings for the radar sensor settings in the 'Sensor/DUT Config' dialog. The frontend center frequency is set read-only and selected according to the configured radar sensor frequency..

set_alignment(syst_align: AregCconfigSystAlign) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:CHANnel:SYSTem:ALIGnment
driver.source.areGenerator.channel.system.set_alignment(syst_align = enums.
↪AregCconfigSystAlign.OFF)
```

Enables the system alignment If the required option is available in the pre-configured system.

param syst_align

OFF| TABLE| ON OFF Default state. No option installed. System alignment is not used. ON Requires R&S AREG8 -B97. System alignment is executed. All frontends included in the test setup are mapped according to the factory alignment. TABLE Requires R&S AREG8 -B98. System alignment is executed. Same mapping as for state'ON'. In addition, you can define a table of certain center frequencies and bandwidths for an additional alignment procedure which has an increased level linearity. The definitions in the table limit the possible settings for the radar sensor settings in the 'Sensor/DUT Config' dialog. The frontend center frequency is set read-only and selected according to the configured radar sensor frequency..

6.16.1.2 Dlogging

SCPI Commands :

```
[SOURCE<HW>]:AREGenerator:DLOGging:CLEar
[SOURCE<HW>]:AREGenerator:DLOGging:DATA
[SOURCE<HW>]:AREGenerator:DLOGging:LEVel
[SOURCE<HW>]:AREGenerator:DLOGging:NErRor
[SOURCE<HW>]:AREGenerator:DLOGging:NIInfo
[SOURCE<HW>]:AREGenerator:DLOGging:NWARning
[SOURCE<HW>]:AREGenerator:DLOGging:SAVE
[SOURCE<HW>]:AREGenerator:DLOGging:[STATe]
```

class DloggingCls

Dlogging commands group definition. 8 total commands, 0 Subgroups, 8 group commands

clear() → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:DLOGging:CLEar
driver.source.areGenerator.dlogging.clear()
```

Removes all logging information, that is collected in the logging data. Query logging data via the command [:SOURCE<hw>]:AREGenerator:DLOGging:DATA.

clear_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:DLOGging:CLEar
driver.source.areGenerator.dlogging.clear_with_opc()
```

Removes all logging information, that is collected in the logging data. Query logging data via the command [:SOURCE<hw>]:AREGenerator:DLOGging:DATA.

Same as clear, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

get_data() → List[str]

```
# SCPI: [SOURCE<HW>]:AREGenerator:DLOGging:DATA
value: List[str] = driver.source.areGenerator.dlogging.get_data()
```

Queries all logging information in the logged data.

return

areg_dyn_logg_data: No help available

get_level() → AregDynLoggLevel

```
# SCPI: [SOURCE<HW>]:AREGenerator:DLOGging:LEVel
value: enums.AregDynLoggLevel = driver.source.areGenerator.dlogging.get_level()
```

Defines the scope of logged data. Only logging information is collected, that corresponds to this scope.

return

dyn_logg_level: ALL| EAWarning| ERRor All Logged data includes information on

errors, warnings and info messages. EAWarning Logged data includes information on errors and warnings. ERRor Logged data includes information on errors.

get_nerror() → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:DLOGging:NError
value: int = driver.source.areGenerator.dlogging.get_nerror()
```

Queries the number of errors within the logged data.

```
return
    dyn_logg_num_of_err: integer Range: 0 to 100
```

get_ninfo() → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:DLOGging:NINfo
value: int = driver.source.areGenerator.dlogging.get_ninfo()
```

Queries the number of info messages within the logged data.

```
return
    dyn_logg_num_of_inf: integer Range: 0 to 100
```

get_nwarning() → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:DLOGging:NWARning
value: int = driver.source.areGenerator.dlogging.get_nwarning()
```

Queries the number of warnings within the logged data.

```
return
    dyn_logg_num_of_war: integer Range: 0 to 100
```

get_save() → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:DLOGging:SAVE
value: str = driver.source.areGenerator.dlogging.get_save()
```

Saves logged data to a file with file extension *.csv. The file extension is added automatically.

```
return
    dyn_logg_save: string
```

get_state() → bool

```
# SCPI: [SOURCE<HW>]:AREGenerator:DLOGging:[STATE]
value: bool = driver.source.areGenerator.dlogging.get_state()
```

Activates logging.

```
return
    dyn_logg_state: 1| ON| 0| OFF
```

set_level()(dyn_logg_level: AregDynLoggLevel) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:DLOGging:LEVel
driver.source.areGenerator.dlogging.set_level(dyn_logg_level = enums.
    AregDynLoggLevel.ALL)
```

Defines the scope of logged data. Only logging information is collected, that corresponds to this scope.

param dyn_logg_level

ALL| EAWarning| ERROR All Logged data includes information on errors, warnings and info messages. EAWarning Logged data includes information on errors and warnings. ERROR Logged data includes information on errors.

set_save(dyn_logg_save: str) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:DLOGging:SAVE
driver.source.areGenerator.dlogging.set_save(dyn_logg_save = 'abc')
```

Saves logged data to a file with file extension *.csv. The file extension is added automatically.

param dyn_logg_save

string

set_state(dyn_logg_state: bool) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:DLOGging:[STATE]
driver.source.areGenerator.dlogging.set_state(dyn_logg_state = False)
```

Activates logging.

param dyn_logg_state

1| ON| 0| OFF

6.16.1.3 Frontend

class FrontendCls

Frontend commands group definition. 134 total commands, 6 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.clone()
```

Subgroups

6.16.1.3.1 Antenna

class AntennaCls

Antenna commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.antenna.clone()
```

Subgroups

6.16.1.3.1.1 Custom

class CustomCls

Custom commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.antenna.custom.clone()
```

Subgroups

6.16.1.3.1.2 ImportPy

class ImportPyCls

ImportPy commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.antenna.custom.importPy.clone()
```

Subgroups

6.16.1.3.1.3 Predefined

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:ANTenna:CUSTom:IMPort:PREDefined:CATalog
```

class PredefinedCls

Predefined commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_catalog() → List[str]

```
# SCPI: [SOURCE<HW>
↪]:AREGenerator:FRONTend:ANTenna:CUSTom:IMPort:PREDefined:CATalog
value: List[str] = driver.source.areGenerator.frontend.antenna.custom.importPy.
↪predefined.get_catalog()
```

Queries all predefined files for standard antennas stored on the R&S AREG800A.

```
return
    areg_fconf_antenna_gain_file_predefined_cat: No help available
```

6.16.1.3.2 Cfe<Channel>

RepCap Settings

```
# Range: Nr1 .. Nr64
rc = driver.source.areGenerator.frontend.cfe.repcap_channel_get()
driver.source.areGenerator.frontend.cfe.repcap_channel_set(repcap.Channel.Nr1)
```

class CfeCls

Cfe commands group definition. 30 total commands, 12 Subgroups, 0 group commands Repeated Capability: Channel, default value after init: Channel.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.cfe.clone()
```

Subgroups

6.16.1.3.2.1 Add

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONTend:CFE<CH>:ADD
```

class AddCls

Add commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(channel=Channel.Default) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONTend:CFE<CH>:ADD
driver.source.areGenerator.frontend.cfe.add.set(channel = repcap.Channel.
↳Default)
```

Adds a configuration for a custom frontend. A line with contiguous numeration is added.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

set_with_opc(channel=Channel.Default, opc_timeout_ms: int = -1) → None

6.16.1.3.2.2 Alias

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONTend:CFE<CH>:ALias
```

class AliasCls

Alias commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → str

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONTend:CFE<CH>:ALias
value: str = driver.source.areGenerator.frontend.cfe.alias.get(channel = repcap.
↳Channel.Default)
```

Sets the alias of the frontend.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

return

areg_fe_alias: string

set(areg_fe_alias: str, channel=Channel.Default) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONTend:CFE<CH>:ALias
driver.source.areGenerator.frontend.cfe.alias.set(areg_fe_alias = 'abc',
↳channel = repcap.Channel.Default)
```

Sets the alias of the frontend.

param areg_fe_alias

string

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

6.16.1.3.2.3 Antenna

class AntennaCls

Antenna commands group definition. 10 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.cfe.antenna.clone()
```

Subgroups

6.16.1.3.2.4 Custom

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:EXPort
```

class CustomCls

Custom commands group definition. 10 total commands, 5 Subgroups, 1 group commands

export_file(*export_filename: str, channel=Channel.Default*) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:EXPort
driver.source.areGenerator.frontend.cfe.antenna.custom.export_file(export_
↪ filename = 'abc', channel = repcap.Channel.Default)
```

Exports the defined frequency table to an external list file with file extension *.txt in a directory.

param export_filename
string

param channel
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.cfe.antenna.custom.clone()
```

Subgroups

6.16.1.3.2.5 Flist

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:FLISt
```

class FlistCls

Flist commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get(*channel=Channel.Default*) → List[float]

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:FLISt
value: List[float] = driver.source.areGenerator.frontend.cfe.antenna.custom.
↪ flist.get(channel = repcap.Channel.Default)
```

For TRX-type frontend: Requires [:SOURce<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] LIST. Sets the values for frequency in the list. Enter all values of the list separated by comma.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

return

areg_fconf_use_cust_ant_freq_list: No help available

set(areg_fconf_use_cust_ant_freq_list: List[float], channel=Channel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:FLISt
driver.source.areGenerator.frontend.cfe.antenna.custom.flist.set(areg_fconf_use_
→cust_ant_freq_list = [1.1, 2.2, 3.3], channel = repcap.Channel.Default)
```

For TRX-type frontend: Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] LIST. Sets the values for frequency in the list. Enter all values of the list separated by comma.

param areg_fconf_use_cust_ant_freq_list

No help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.cfe.antenna.custom.flist.clone()
```

Subgroups**6.16.1.3.2.6 Row<Index>****RepCap Settings**

```
# Range: Nr1 .. Nr64
rc = driver.source.areGenerator.frontend.cfe.antenna.custom.flist.row.repcap_index_get()
driver.source.areGenerator.frontend.cfe.antenna.custom.flist.row.repcap_index_set(repcap.
→Index.Nr1)
```

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:FLISt:ROW<DI>
```

class RowCls

Row commands group definition. 1 total commands, 0 Subgroups, 1 group commands Repeated Capability: Index, default value after init: Index.Nr1

get(channel=Channel.Default, index=Index.Default) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:FLISt:ROW<DI>
value: int = driver.source.areGenerator.frontend.cfe.antenna.custom.flist.row.
→get(channel = repcap.Channel.Default, index = repcap.Index.Default)
```

Sets the frequency value in the selected row of the list.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param index

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Row')

return

frequency: integer Range: 500E6 to 1E12

set(frequency: int, channel=Channel.Default, index=Index.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:FLISt:ROW<DI>
driver.source.areGenerator.frontend.cfe.antenna.custom.flist.row.set(frequency,
↪= 1, channel = repcap.Channel.Default, index = repcap.Index.Default)
```

Sets the frequency value in the selected row of the list.

param frequency

integer Range: 500E6 to 1E12

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param index

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Row')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.cfe.antenna.custom.flist.row.clone()
```

6.16.1.3.2.7 Fpoints

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:FPOints
```

class FpointsCls

Fpoints commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:FPOints
value: int = driver.source.areGenerator.frontend.cfe.antenna.custom.fpoints.
↪get(channel = repcap.Channel.Default)
```

Sets the number of frequencies that you want to define in the list.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

return

areg_fe_cust_ant_fp: integer Range: 1 to 512

set(areg_fe_cust_ant_fp: int, channel=Channel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:FPOints
driver.source.areGenerator.frontend.cfe.antenna.custom.fpoints.set(areg_fe_cust_
↪ ant_fp = 1, channel = repcap.Channel.Default)
```

Sets the number of frequencies that you want to define in the list.

param areg_fe_cust_ant_fp

integer Range: 1 to 512

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

6.16.1.3.2.8 ImportPy

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:IMPort
```

class ImportPyCls

ImportPy commands group definition. 2 total commands, 1 Subgroups, 1 group commands

set(import_filename: str, channel=Channel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:IMPort
driver.source.areGenerator.frontend.cfe.antenna.custom.importPy.set(import_
↪ filename = 'abc', channel = repcap.Channel.Default)
```

Imports an external list with file extension *.txt from a directory. The file format is a text file as comma-separated list with the list elements frequency, RX gain and TX gain.

param import_filename

string

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.cfe.antenna.custom.importPy.clone()
```

Subgroups

6.16.1.3.2.9 Predefined

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:IMPort:PREDefined
```

class PredefinedCls

Predefined commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(import_filename: str, channel=Channel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>
↳:ANTenna:CUSTom:IMPort:PREDefined
driver.source.areGenerator.frontend.cfe.antenna.custom.importPy.predefined.
↳set(import_filename = 'abc', channel = repcap.Channel.Default)
```

Imports a predefined file for standard antennas, stored on the R&S AREG800A.

param import_filename

string

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

6.16.1.3.2.10 Rx<RxIndex>

RepCap Settings

```
# Range: Nr1 .. Nr16
rc = driver.source.areGenerator.frontend.cfe.antenna.custom.rx.repcap_rxIndex_get()
driver.source.areGenerator.frontend.cfe.antenna.custom.rx.repcap_rxIndex_set(repcap.
↳RxIndex.Nr1)
```

class RxCls

Rx commands group definition. 2 total commands, 1 Subgroups, 0 group commands Repeated Capability: RxIndex, default value after init: RxIndex.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.cfe.antenna.custom.rx.clone()
```

Subgroups

6.16.1.3.2.11 Glist

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:RX<ST>:GLISt
```

class GlistCls

Glist commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get(channel=Channel.Default, rxIndex=RxIndex.Default) → List[float]

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:RX<ST>:GLISt
value: List[float] = driver.source.areGenerator.frontend.cfe.antenna.custom.rx.
↳glist.get(channel = repcap.Channel.Default, rxIndex = repcap.RxIndex.Default)
```

For TRX-type frontend: Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] LIST. Sets the values for antenna gain RX/TX in the list. Enter all values of the list separated by comma.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

areg_fconf_use_cust_ant_gain_list: No help available

set(areg_fconf_use_cust_ant_gain_list: List[float], channel=Channel.Default, rxIndex=RxIndex.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:RX<ST>:GLISt
driver.source.areGenerator.frontend.cfe.antenna.custom.rx.glist.set(areg_fconf_
↳use_cust_ant_gain_list = [1.1, 2.2, 3.3], channel = repcap.Channel.Default,
↳rxIndex = repcap.RxIndex.Default)
```

For TRX-type frontend: Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] LIST. Sets the values for antenna gain RX/TX in the list. Enter all values of the list separated by comma.

param areg_fconf_use_cust_ant_gain_list

No help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.cfe.antenna.custom.rx.glist.clone()
```

Subgroups

6.16.1.3.2.12 Row<Index>

RepCap Settings

```
# Range: Nr1 .. Nr64
rc = driver.source.areGenerator.frontend.cfe.antenna.custom.rx.glist.row.repcap_index_
    ↪ get()
driver.source.areGenerator.frontend.cfe.antenna.custom.rx.glist.row.repcap_index_
    ↪ set(repcap.Index.Nr1)
```

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONtend:CFE<CH>:ANTenna:CUSTom:RX<ST>:GLISt:ROW<DI>
```

class RowCls

Row commands group definition. 1 total commands, 0 Subgroups, 1 group commands Repeated Capability: Index, default value after init: Index.Nr1

get(channel=Channel.Default, rxIndex=RxIndex.Default, index=Index.Default) → int

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONtend:CFE<CH>:ANTenna:CUSTom:RX<ST>
    ↪ :GLISt:ROW<DI>
value: int = driver.source.areGenerator.frontend.cfe.antenna.custom.rx.glist.
    ↪ row.get(channel = repcap.Channel.Default, rxIndex = repcap.RxIndex.Default,
    ↪ index = repcap.Index.Default)
```

Sets the value for antenna gain RX/TX in the selected row of the list.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

param index

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Row')

return

gain: integer Range: -50 to 50

set(gain: int, channel=Channel.Default, rxIndex=RxIndex.Default, index=Index.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTOM:RX<ST>
↳:GLIST:ROW<DI>
driver.source.areGenerator.frontend.cfe.antenna.custom.rx.glist.row.set(gain =
↳1, channel = repcap.Channel.Default, rxIndex = repcap.RxIndex.Default, index
↳= repcap.Index.Default)
```

Sets the value for antenna gain RX/TX in the selected row of the list.

param gain

integer Range: -50 to 50

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

param index

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Row')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.cfe.antenna.custom.rx.glist.row.clone()
```

6.16.1.3.2.13 Tx<TxIndexNull>

RepCap Settings

```
# Range: Nr0 .. Nr15
rc = driver.source.areGenerator.frontend.cfe.antenna.custom.tx.repcap_txIndexNull_get()
driver.source.areGenerator.frontend.cfe.antenna.custom.tx.repcap_txIndexNull_set(repcap.
↳TxIndexNull.Nr0)
```

class TxCls

Tx commands group definition. 2 total commands, 1 Subgroups, 0 group commands Repeated Capability: TxIndexNull, default value after init: TxIndexNull.Nr0

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.cfe.antenna.custom.tx.clone()
```

Subgroups

6.16.1.3.2.14 Glist

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:TX<ST0>:GLIST
```

class GlistCls

Glist commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get(channel=Channel.Default, txIndexNull=TxIndexNull.Default) → List[float]

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:TX<ST0>:GLIST
value: List[float] = driver.source.areGenerator.frontend.cfe.antenna.custom.tx.
↳glist.get(channel = repcap.Channel.Default, txIndexNull = repcap.TxIndexNull.
↳Default)
```

For TRX-type frontend: Requires [:SOURce<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] LIST. Sets the values for antenna gain RX/TX in the list. Enter all values of the list separated by comma.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

areg_fconf_use_cust_ant_gain_list: No help available

set(areg_fconf_use_cust_ant_gain_list: List[float], channel=Channel.Default, txIndexNull=TxIndexNull.Default) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:TX<ST0>:GLIST
driver.source.areGenerator.frontend.cfe.antenna.custom.tx.glist.set(areg_fconf_
↳use_cust_ant_gain_list = [1.1, 2.2, 3.3], channel = repcap.Channel.Default,
↳txIndexNull = repcap.TxIndexNull.Default)
```

For TRX-type frontend: Requires [:SOURce<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] LIST. Sets the values for antenna gain RX/TX in the list. Enter all values of the list separated by comma.

param areg_fconf_use_cust_ant_gain_list

No help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.cfe.antenna.custom.tx.glist.clone()
```

Subgroups

6.16.1.3.2.15 Row<Index>

RepCap Settings

```
# Range: Nr1 .. Nr64
rc = driver.source.areGenerator.frontend.cfe.antenna.custom.tx.glist.row.repcap_index_
    ↪ get()
driver.source.areGenerator.frontend.cfe.antenna.custom.tx.glist.row.repcap_index_
    ↪ set(repcap.Index.Nr1)
```

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONtend:CFE<CH>:ANTenna:CUSTom:TX<ST0>:GLISt:ROW<DI>
```

class RowCls

Row commands group definition. 1 total commands, 0 Subgroups, 1 group commands Repeated Capability: Index, default value after init: Index.Nr1

get(channel=Channel.Default, txIndexNull=TxIndexNull.Default, index=Index.Default) → int

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONtend:CFE<CH>:ANTenna:CUSTom:TX<ST0>
    ↪ :GLISt:ROW<DI>
value: int = driver.source.areGenerator.frontend.cfe.antenna.custom.tx.glist.
    ↪ row.get(channel = repcap.Channel.Default, txIndexNull = repcap.TxIndexNull.
    ↪ Default, index = repcap.Index.Default)
```

Sets the value for antenna gain RX/TX in the selected row of the list.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

param index

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Row')

return

gain: integer Range: -50 to 50

set(gain: int, channel=Channel.Default, txIndexNull=TxIndexNull.Default, index=Index.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:TX<ST0>
↳:GLIST:ROW<DI>
driver.source.areGenerator.frontend.cfe.antenna.custom.tx.glist.row.set(gain =
↳1, channel = repcap.Channel.Default, txIndexNull = repcap.TxIndexNull.Default,
↳ index = repcap.Index.Default)
```

Sets the value for antenna gain RX/TX in the selected row of the list.

param gain

integer Range: -50 to 50

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

param index

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Row')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.cfe.antenna.custom.tx.glist.row.clone()
```

6.16.1.3.2.16 Ats

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ATS
```

class AtsCls

Ats commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ATS
value: float = driver.source.areGenerator.frontend.cfe.ats.get(channel = repcap.
↳Channel.Default)
```

Sets the angle between frontend and radar sensor. Reference point for the definition of the angle is the center of the frontend. The angle describes the deviation of the position of the frontend from the 0DEG center position of the field of view of the radar.

INTRO_CMD_HELP: We recommend that you zero in regular intervals (at least once a day) , if:

- Positive angle frontend to sensor: counter clockwise deviation of frontend position to center position.
- Negative angle frontend to sensor: clockwise deviation of frontend position to center position.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

return

areg_fe_ats: float Range: -90 to 90

set(areg_fe_ats: float, channel=Channel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ATS
driver.source.areGenerator.frontend.cfe.ats.set(areg_fe_ats = 1.0, channel =
↳repcap.Channel.Default)
```

Sets the angle between frontend and radar sensor. Reference point for the definition of the angle is the center of the frontend. The angle describes the deviation of the position of the frontend from the 0DEG center position of the field of view of the radar.

INTRO_CMD_HELP: We recommend that you zero in regular intervals (at least once a day) , if:

- Positive angle frontend to sensor: counter clockwise deviation of frontend position to center position.
- Negative angle frontend to sensor: clockwise deviation of frontend position to center position.

param areg_fe_ats

float Range: -90 to 90

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

6.16.1.3.2.17 CableCorr**class CableCorrCls**

CableCorr commands group definition. 8 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.cfe.cableCorr.clone()
```

Subgroups**6.16.1.3.2.18 Connector<Connector>****RepCap Settings**

```
# Range: Nr1 .. Nr8
rc = driver.source.areGenerator.frontend.cfe.cableCorr.connector.repcap_connector_get()
driver.source.areGenerator.frontend.cfe.cableCorr.connector.repcap_connector_set(repcap.
↳Connector.Nr1)
```

class ConnectorCls

Connector commands group definition. 8 total commands, 2 Subgroups, 0 group commands Repeated Capability: Connector, default value after init: Connector.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.cfe.cableCorr.connector.clone()
```

Subgroups**6.16.1.3.2.19 Rx<RxIndex>****RepCap Settings**

```
# Range: Nr1 .. Nr16
rc = driver.source.areGenerator.frontend.cfe.cableCorr.connector.rx.repcap_rxIndex_get()
driver.source.areGenerator.frontend.cfe.cableCorr.connector.rx.repcap_rxIndex_set(repcap.
↳ RxIndex.Nr1)
```

class RxCls

Rx commands group definition. 4 total commands, 2 Subgroups, 0 group commands Repeated Capability: RxIndex, default value after init: RxIndex.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.cfe.cableCorr.connector.rx.clone()
```

Subgroups**6.16.1.3.2.20 Mode****SCPI Command :**

```
[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:RX<ST>:MODE
```

class ModeCls

Mode commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, connector=Connector.Default, rxIndex=RxIndex.Default) → AregCableCorrSour

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:RX
↳ <ST>:MODE
value: enums.AregCableCorrSour = driver.source.areGenerator.frontend.cfe.
↳ cableCorr.connector.rx.mode.get(channel = repcap.Channel.Default, connector =
↳ repcap.Connector.Default, rxIndex = repcap.RxIndex.Default)
```

Selects the source for cable correction data.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

areg_cabel_cor_mod: USER| S2P| FACTory USER Selects user-defined cable correction data, i.e. fixed values for delay and attenuation. S2P Selects cable correction data from a file with file extension *.s2p. FACTory For TRX-type frontends only. Selects cable correction data for the TRX frontend from factory specification.

set(areg_cabel_cor_mod: AregCableCorrSour, channel=Channel.Default, connector=Connector.Default, rxIndex=RxIndex.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:Cfe<CH>:CABLEcorr:CONNector<DI>:RX
↪<ST>:MODE
driver.source.areGenerator.frontend.cfe.cableCorr.connector.rx.mode.set(areg_
↪cabel_cor_mod = enums.AregCableCorrSour.FACTory, channel = repcap.Channel.
↪Default, connector = repcap.Connector.Default, rxIndex = repcap.RxIndex.
↪Default)
```

Selects the source for cable correction data.

param areg_cabel_cor_mod

USER| S2P| FACTory USER Selects user-defined cable correction data, i.e. fixed values for delay and attenuation. S2P Selects cable correction data from a file with file extension *.s2p. FACTory For TRX-type frontends only. Selects cable correction data for the TRX frontend from factory specification.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

6.16.1.3.2.21 User

class UserCls

User commands group definition. 3 total commands, 3 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.cfe.cableCorr.connector.rx.user.clone()
```

Subgroups

6.16.1.3.2.22 Attenuation

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:RX<ST>
↪:USER:ATTenuation
```

class AttenuationCls

Attenuation commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, connector=Connector.Default, rxIndex=RxIndex.Default) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:RX
↪<ST>:USER:ATTenuation
value: float = driver.source.areGenerator.frontend.cfe.cableCorr.connector.rx.
↪user.attenuation.get(channel = repcap.Channel.Default, connector = repcap.
↪Connector.Default, rxIndex = repcap.RxIndex.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> USER or [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> S2P. Sets a user-defined attenuation value.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

areg_cable_corr_at: float Range: -50 to 50

set(areg_cable_corr_at: float, channel=Channel.Default, connector=Connector.Default, rxIndex=RxIndex.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:RX
↳<ST>:USER:ATTenuation
driver.source.areGenerator.frontend.cfe.cableCorr.connector.rx.user.attenuation.
↳set(areg_cable_corr_at = 1.0, channel = repcap.Channel.Default, connector =
↳repcap.Connector.Default, rxIndex = repcap.RxIndex.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> USER or [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> S2P. Sets a user-defined attenuation value.

param areg_cable_corr_at
float Range: -50 to 50

param channel
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param connector
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

6.16.1.3.2.23 Delay

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:RX<ST>:USER:DElay
```

class DelayCls

Delay commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, connector=Connector.Default, rxIndex=RxIndex.Default) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:RX
↳<ST>:USER:DElay
value: float = driver.source.areGenerator.frontend.cfe.cableCorr.connector.rx.
↳user.delay.get(channel = repcap.Channel.Default, connector = repcap.Connector.
↳Default, rxIndex = repcap.RxIndex.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> USER. Sets a user-defined delay value.

param channel
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param connector
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

```

    return
    areg_cable_cor_del: float Range: 0 to 50
set(areg_cable_cor_del: float, channel=Channel.Default, connector=Connector.Default,
    rxIndex=RxIndex.Default) → None

```

```

# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:RX
↳<ST>:USER:DELAY
driver.source.areGenerator.frontend.cfe.cableCorr.connector.rx.user.delay.
↳set(areg_cable_cor_del = 1.0, channel = repcap.Channel.Default, connector =
↳repcap.Connector.Default, rxIndex = repcap.RxIndex.Default)

```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> USER. Sets a user-defined delay value.

```

param areg_cable_cor_del
    float Range: 0 to 50

param channel
    optional repeated capability selector. Default value: Nr1 (settable in the interface
    'Cfe')

param connector
    optional repeated capability selector. Default value: Nr1 (settable in the interface
    'Connector')

param rxIndex
    optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

```

6.16.1.3.2.24 File

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:RX<ST>:USER:FILE
```

class FileCls

File commands group definition. 1 total commands, 0 Subgroups, 1 group commands

```
get(channel=Channel.Default, connector=Connector.Default, rxIndex=RxIndex.Default) → str
```

```

# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:RX
↳<ST>:USER:FILE
value: str = driver.source.areGenerator.frontend.cfe.cableCorr.connector.rx.
↳user.file.get(channel = repcap.Channel.Default, connector = repcap.Connector.
↳Default, rxIndex = repcap.RxIndex.Default)

```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> S2P. Loads a cable correction data file with file extension *.s2p from the default or the specified directory.

```

param channel
    optional repeated capability selector. Default value: Nr1 (settable in the interface
    'Cfe')

param connector
    optional repeated capability selector. Default value: Nr1 (settable in the interface
    'Connector')

```


param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

areg_cable_cor_fil: string

set(areg_cable_cor_fil: str, channel=Channel.Default, connector=Connector.Default, rxIndex=RxIndex.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:RX
↳<ST>:USER:FILE
driver.source.areGenerator.frontend.cfe.cableCorr.connector.rx.user.file.
↳set(areg_cable_cor_fil = 'abc', channel = repcap.Channel.Default, connector =
↳repcap.Connector.Default, rxIndex = repcap.RxIndex.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> S2P. Loads a cable correction data file with file extension *.s2p from the default or the specified directory.

param areg_cable_cor_fil

string

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

6.16.1.3.2.25 Tx<TxIndexNull>**RepCap Settings**

```
# Range: Nr0 .. Nr15
rc = driver.source.areGenerator.frontend.cfe.cableCorr.connector.tx.repcap_txIndexNull_
↳get()
driver.source.areGenerator.frontend.cfe.cableCorr.connector.tx.repcap_txIndexNull_
↳set(repcap.TxIndexNull.Nr0)
```

class TxCls

Tx commands group definition. 4 total commands, 2 Subgroups, 0 group commands Repeated Capability: TxIndexNull, default value after init: TxIndexNull.Nr0

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.cfe.cableCorr.connector.tx.clone()
```

Subgroups

6.16.1.3.2.26 Mode

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:TX<ST0>:MODE
```

class ModeCls

Mode commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, connector=Connector.Default, txIndexNull=TxIndexNull.Default) → AregCableCorrSour

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:TX
↳<ST0>:MODE
value: enums.AregCableCorrSour = driver.source.areGenerator.frontend.cfe.
↳cableCorr.connector.tx.mode.get(channel = repcap.Channel.Default, connector =
↳repcap.Connector.Default, txIndexNull = repcap.TxIndexNull.Default)
```

Selects the source for cable correction data.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

areg_cabel_cor_mod: USER| S2P| FACTory USER Selects user-defined cable correction data, i.e. fixed values for delay and attenuation. S2P Selects cable correction data from a file with file extension *.s2p. FACTory For TRX-type frontends only. Selects cable correction data for the TRX frontend from factory specification.

set(areg_cabel_cor_mod: AregCableCorrSour, channel=Channel.Default, connector=Connector.Default, txIndexNull=TxIndexNull.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:TX
↳<ST0>:MODE
driver.source.areGenerator.frontend.cfe.cableCorr.connector.tx.mode.set(areg_
↳cabel_cor_mod = enums.AregCableCorrSour.FACTory, channel = repcap.Channel.
↳Default, connector = repcap.Connector.Default, txIndexNull = repcap.
↳TxIndexNull.Default)
```

Selects the source for cable correction data.

param areg_cabel_cor_mod

USER| S2P| FACTory USER Selects user-defined cable correction data, i.e. fixed values for delay and attenuation. S2P Selects cable correction data from a file with file extension *.s2p. FACTory For TRX-type frontends only. Selects cable correction data for the TRX frontend from factory specification.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

6.16.1.3.2.27 User

class UserCls

User commands group definition. 3 total commands, 3 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.cfe.cableCorr.connector.tx.user.clone()
```

Subgroups

6.16.1.3.2.28 Attenuation

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:TX<ST0>
↳:USER:ATTenuation
```

class AttenuationCls

Attenuation commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, connector=Connector.Default, txIndexNull=TxIndexNull.Default) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:TX
↳<ST0>:USER:ATTenuation
value: float = driver.source.areGenerator.frontend.cfe.cableCorr.connector.tx.
↳user.attenuation.get(channel = repcap.Channel.Default, connector = repcap.
↳Connector.Default, txIndexNull = repcap.TxIndexNull.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> USER or [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> S2P. Sets a user-defined attenuation value.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

areg_cable_corr_at: float Range: -50 to 50

set(areg_cable_corr_at: float, channel=Channel.Default, connector=Connector.Default, txIndexNull=TxIndexNull.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:TX
↳<ST0>:USER:ATTenuation
driver.source.areGenerator.frontend.cfe.cableCorr.connector.tx.user.attenuation.
↳set(areg_cable_corr_at = 1.0, channel = repcap.Channel.Default, connector =
↳repcap.Connector.Default, txIndexNull = repcap.TxIndexNull.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> USER or [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> S2P. Sets a user-defined attenuation value.

param areg_cable_corr_at

float Range: -50 to 50

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

6.16.1.3.2.29 Delay

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:TX<ST0>:USER:DElay
```

class DelayCls

Delay commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, connector=Connector.Default, txIndexNull=TxIndexNull.Default) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:TX
↳<ST0>:USER:DElay
value: float = driver.source.areGenerator.frontend.cfe.cableCorr.connector.tx.
↳user.delay.get(channel = repcap.Channel.Default, connector = repcap.Connector.
↳Default, txIndexNull = repcap.TxIndexNull.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> USER. Sets a user-defined delay value.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

areg_cable_cor_del: float Range: 0 to 50

set(areg_cable_cor_del: float, channel=Channel.Default, connector=Connector.Default, txIndexNull=TxIndexNull.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:TX
↳<ST0>:USER:DELAY
driver.source.areGenerator.frontend.cfe.cableCorr.connector.tx.user.delay.
↳set(areg_cable_cor_del = 1.0, channel = repcap.Channel.Default, connector =
↳repcap.Connector.Default, txIndexNull = repcap.TxIndexNull.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> USER. Sets a user-defined delay value.

param areg_cable_cor_del

float Range: 0 to 50

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

6.16.1.3.2.30 File

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:TX<ST0>:USER:FILE
```

class FileCls

File commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, connector=Connector.Default, txIndexNull=TxIndexNull.Default) → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNECTor<DI>:TX
↳<ST0>:USER:FILE
```

(continues on next page)

(continued from previous page)

```

value: str = driver.source.areGenerator.frontend.cfe.cableCorr.connector.tx.
↳ user.file.get(channel = repcap.Channel.Default, connector = repcap.Connector.
↳ Default, txIndexNull = repcap.TxIndexNull.Default)

```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNector<di>
S2P. Loads a cable correction data file with file extension *.s2p from the default or the specified directory.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

areg_cable_cor_fil: string

set(areg_cable_cor_fil: str, channel=Channel.Default, connector=Connector.Default, txIndexNull=TxIndexNull.Default) → None

```

# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNector<DI>:TX
↳ <ST0>:USER:FILE
driver.source.areGenerator.frontend.cfe.cableCorr.connector.tx.user.file.
↳ set(areg_cable_cor_fil = 'abc', channel = repcap.Channel.Default, connector =
↳ repcap.Connector.Default, txIndexNull = repcap.TxIndexNull.Default)

```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNector<di>
S2P. Loads a cable correction data file with file extension *.s2p from the default or the specified directory.

param areg_cable_cor_fil

string

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

6.16.1.3.2.31 Center

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONTend:CFE<CH>:CENTer
```

class CenterCls

Center commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → float

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONTend:CFE<CH>:CENTer
value: float = driver.source.areGenerator.frontend.cfe.center.get(channel = ↵
↵repcap.Channel.Default)
```

Sets the RF center frequency of the output signal of the connected frontend. The frontend center frequency and frequency range depend on the configuration of the R&S AREG800A and the configuration of the frontend included in the test setup. For more information, see the data sheet. When using custom frontends, the IF center frequency instead of the RF center frequency is configurable in the frontend configuration. The IF center frequency with the sensor bandwidth is used for the cable correction, whereas the sensor frequency and bandwidth is used for the antenna correction.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

return

areg_fe_center_fre: float Range: 0 to 100E9

set(areg_fe_center_fre: float, channel=Channel.Default) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONTend:CFE<CH>:CENTer
driver.source.areGenerator.frontend.cfe.center.set(areg_fe_center_fre = 1.0, ↵
↵channel = repcap.Channel.Default)
```

Sets the RF center frequency of the output signal of the connected frontend. The frontend center frequency and frequency range depend on the configuration of the R&S AREG800A and the configuration of the frontend included in the test setup. For more information, see the data sheet. When using custom frontends, the IF center frequency instead of the RF center frequency is configurable in the frontend configuration. The IF center frequency with the sensor bandwidth is used for the cable correction, whereas the sensor frequency and bandwidth is used for the antenna correction.

param areg_fe_center_fre

float Range: 0 to 100E9

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

6.16.1.3.2.32 Id

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ID
```

class IdCls

Id commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ID
value: int = driver.source.areGenerator.frontend.cfe.id.get(channel = repcap.
↳Channel.Default)
```

No command help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

return

areg_fe_id: No help available

6.16.1.3.2.33 Rmv

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:RMV
```

class RmvCls

Rmv commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(channel=Channel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:RMV
driver.source.areGenerator.frontend.cfe.rmv.set(channel = repcap.Channel.
↳Default)
```

Removes the configuration of the connected QAT-type, FE-type or custom frontend.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

set_with_opc(channel=Channel.Default, opc_timeout_ms: int = -1) → None

6.16.1.3.2.34 Rts

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:RTS
```

class RtsCls

Rts commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:RTS
value: float = driver.source.areGenerator.frontend.cfe.rts.get(channel = repcap.
↳Channel.Default)
```

Sets the rotation angle between frontend and sensor. Reference point for the definition of the angle is the center of the frontend. The rotation describes the deviation of the position of the frontend from a 90DEG angle to the direct line of sight of the sensor. For TRX-type or custom frontends this parameter has currently no impact, since it is a single sensor and no sensor array.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

return

areg_fe_rts: float Range: -60 to 60

set(areg_fe_rts: float, channel=Channel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:RTS
driver.source.areGenerator.frontend.cfe.rts.set(areg_fe_rts = 1.0, channel =
↳repcap.Channel.Default)
```

Sets the rotation angle between frontend and sensor. Reference point for the definition of the angle is the center of the frontend. The rotation describes the deviation of the position of the frontend from a 90DEG angle to the direct line of sight of the sensor. For TRX-type or custom frontends this parameter has currently no impact, since it is a single sensor and no sensor array.

param areg_fe_rts

float Range: -60 to 60

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

6.16.1.3.2.35 Rx<RxIndex>

RepCap Settings

```
# Range: Nr1 .. Nr16
rc = driver.source.areGenerator.frontend.cfe.rx.repcap_rxIndex_get()
driver.source.areGenerator.frontend.cfe.rx.repcap_rxIndex_set(repcap.RxIndex.Nr1)
```

class RxCls

Rx commands group definition. 2 total commands, 2 Subgroups, 0 group commands Repeated Capability: RxIndex, default value after init: RxIndex.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.cfe.rx.clone()
```

Subgroups**6.16.1.3.2.36 Efrontend****SCPI Command :**

```
[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:RX<ST>:EFRontend
```

class EfrontendCls

Efrontend commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, rxIndex=RxIndex.Default) → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:RX<ST>:EFRontend
value: str = driver.source.areGenerator.frontend.cfe.rx.efrontend.get(channel =
↳repcap.Channel.Default, rxIndex = repcap.RxIndex.Default)
```

No command help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

instr_name: No help available

set(instr_name: str, channel=Channel.Default, rxIndex=RxIndex.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:RX<ST>:EFRontend
driver.source.areGenerator.frontend.cfe.rx.efrontend.set(instr_name = 'abc',
↳channel = repcap.Channel.Default, rxIndex = repcap.RxIndex.Default)
```

No command help available

param instr_name

No help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

6.16.1.3.2.37 Ota

class OtaCls

Ota commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.cfe.rx.ota.clone()
```

Subgroups

6.16.1.3.2.38 Offset

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:RX<ST>:OTA:OFFSet
```

class OffsetCls

Offset commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, rxIndex=RxIndex.Default) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:RX<ST>:OTA:OFFSet
value: int = driver.source.areGenerator.frontend.cfe.rx.ota.offset.get(channel,
↳= repcap.Channel.Default, rxIndex = repcap.RxIndex.Default)
```

Specifies the length of the gap between frontend and target.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

areg_fe_ota_offset: integer Range: 0.01 to 30

set(areg_fe_ota_offset: int, channel=Channel.Default, rxIndex=RxIndex.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:RX<ST>:OTA:OFFSet
driver.source.areGenerator.frontend.cfe.rx.ota.offset.set(areg_fe_ota_offset =
↳1, channel = repcap.Channel.Default, rxIndex = repcap.RxIndex.Default)
```

Specifies the length of the gap between frontend and target.

param areg_fe_ota_offset

integer Range: 0.01 to 30

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

6.16.1.3.2.39 Tx<TxIndexNull>**RepCap Settings**

Range: Nr0 .. Nr15

rc = driver.source.areGenerator.frontend.cfe.tx.repcap_txIndexNull_get()

driver.source.areGenerator.frontend.cfe.tx.repcap_txIndexNull_set(repcap.TxIndexNull.Nr0)

class TxCls

Tx commands group definition. 2 total commands, 2 Subgroups, 0 group commands Repeated Capability: TxIndexNull, default value after init: TxIndexNull.Nr0

Cloning the Group

Create a clone of the original group, that exists independently

group2 = driver.source.areGenerator.frontend.cfe.tx.clone()

Subgroups**6.16.1.3.2.40 Efrontend****SCPI Command :**

[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:TX<ST0>:EFRontend

class EfrontendCls

Efrontend commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, txIndexNull=TxIndexNull.Default) → str

SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:TX<ST0>:EFRontend

value: str = driver.source.areGenerator.frontend.cfe.tx.efrontend.get(channel = ↵
↵repcap.Channel.Default, txIndexNull = repcap.TxIndexNull.Default)

No command help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

instr_name: No help available

set(instr_name: str, channel=Channel.Default, txIndexNull=TxIndexNull.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:TX<ST0>:EFRontend
driver.source.areGenerator.frontend.cfe.tx.efrontend.set(instr_name = 'abc',
↳ channel = repcap.Channel.Default, txIndexNull = repcap.TxIndexNull.Default)
```

No command help available

param instr_name

No help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

6.16.1.3.2.41 Ota

class OtaCls

Ota commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.cfe.tx.ota.clone()
```

Subgroups

6.16.1.3.2.42 Offset

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:TX<ST0>:OTA:OFFSet
```

class OffsetCls

Offset commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, txIndexNull=TxIndexNull.Default) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:TX<ST0>:OTA:OFFSet
value: int = driver.source.areGenerator.frontend.cfe.tx.ota.offset.get(channel,
↳ = repcap.Channel.Default, txIndexNull = repcap.TxIndexNull.Default)
```

Specifies the length of the gap between frontend and target.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Cfe')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

```

    return
    areg_fe_ota_offset: integer Range: 0.01 to 30

set(areg_fe_ota_offset: int, channel=Channel.Default, txIndexNull=TxIndexNull.Default) → None

```

```

# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:TX<ST0>:OTA:OFFSet
driver.source.areGenerator.frontend.cfe.tx.ota.offset.set(areg_fe_ota_offset =
↪1, channel = repcap.Channel.Default, txIndexNull = repcap.TxIndexNull.Default)

```

Specifies the length of the gap between frontend and target.

```

param areg_fe_ota_offset
    integer Range: 0.01 to 30

param channel
    optional repeated capability selector. Default value: Nr1 (settable in the interface
    'Cfe')

param txIndexNull
    optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

```

6.16.1.3.2.43 TypePy

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:TYPE
```

class TypePyCls

TypePy commands group definition. 1 total commands, 0 Subgroups, 1 group commands

```
get(channel=Channel.Default) → AregFeType
```

```

# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:TYPE
value: enums.AregFeType = driver.source.areGenerator.frontend.cfe.typePy.
↪get(channel = repcap.Channel.Default)

```

Queries the type of the connected frontend.

```

param channel
    optional repeated capability selector. Default value: Nr1 (settable in the interface
    'Cfe')

return
    frontend_type: TRX| QAT| NONE| FE| CFE TRX A TRX-type frontend is connected.
    QAT A QAT-type frontend is connected. NONE No frontend is connected. FE An
    FE-type frontend is connected. CFE A custom frontend is connected.

```

6.16.1.3.3 Fe<Channel>

RepCap Settings

```
# Range: Nr1 .. Nr64
rc = driver.source.areGenerator.frontend.fe.repcap_channel_get()
driver.source.areGenerator.frontend.fe.repcap_channel_set(repcap.Channel.Nr1)
```

class FeCls

Fe commands group definition. 34 total commands, 16 Subgroups, 0 group commands Repeated Capability: Channel, default value after init: Channel.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.fe.clone()
```

Subgroups

6.16.1.3.3.1 Add

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONtend:FE<CH>:ADD
```

class AddCls

Add commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(channel=Channel.Default) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONtend:FE<CH>:ADD
driver.source.areGenerator.frontend.fe.add.set(channel = repcap.Channel.Default)
```

Adds a configuration for an FE-type external frontend. A line with contiguous numeration is added.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

set_with_opc(channel=Channel.Default, opc_timeout_ms: int = -1) → None

6.16.1.3.3.2 Alias

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONtend:FE<CH>:ALIAS
```

class AliasCls

Alias commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*channel=Channel.Default*) → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ALIAS
value: str = driver.source.areGenerator.frontend.fe.alias.get(channel = repcap.
↳ Channel.Default)
```

Sets the alias of the frontend.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

return

areg_fe_alias: string

set(*areg_fe_alias: str, channel=Channel.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ALIAS
driver.source.areGenerator.frontend.fe.alias.set(areg_fe_alias = 'abc', channel_
↳ = repcap.Channel.Default)
```

Sets the alias of the frontend.

param areg_fe_alias

string

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

6.16.1.3.3.3 Antenna

class AntennaCls

Antenna commands group definition. 10 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.fe.antenna.clone()
```

Subgroups

6.16.1.3.3.4 Custom

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:EXPort
```

class CustomCls

Custom commands group definition. 10 total commands, 5 Subgroups, 1 group commands

export_file(*export_filename: str, channel=Channel.Default*) → None


```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:EXPort
driver.source.areGenerator.frontend.fe.antenna.custom.export_file(export_
↪ filename = 'abc', channel = repcap.Channel.Default)
```

Exports the defined frequency table to an external list file with file extension *.txt in a directory.

param export_filename
string

param channel
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.fe.antenna.custom.clone()
```

Subgroups

6.16.1.3.3.5 Flist

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:FLISt
```

class FlistCls

Flist commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get(channel=Channel.Default) → List[float]

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:FLISt
value: List[float] = driver.source.areGenerator.frontend.fe.antenna.custom.
↪ flist.get(channel = repcap.Channel.Default)
```

For TRX-type frontend: Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] LIST. Sets the values for frequency in the list. Enter all values of the list separated by comma.

param channel
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

return
areg_fconf_use_cust_ant_freq_list: No help available

set(areg_fconf_use_cust_ant_freq_list: List[float], channel=Channel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:FLISt
driver.source.areGenerator.frontend.fe.antenna.custom.flist.set(areg_fconf_use_
↪ cust_ant_freq_list = [1.1, 2.2, 3.3], channel = repcap.Channel.Default)
```

For TRX-type frontend: Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] LIST. Sets the values for frequency in the list. Enter all values of the list separated by comma.

param areg_fconf_use_cust_ant_freq_list
No help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.fe.antenna.custom.flist.clone()
```

Subgroups**6.16.1.3.3.6 Row<Index>****RepCap Settings**

```
# Range: Nr1 .. Nr64
rc = driver.source.areGenerator.frontend.fe.antenna.custom.flist.row.repcap_index_get()
driver.source.areGenerator.frontend.fe.antenna.custom.flist.row.repcap_index_set(repcap.
↪ Index.Nr1)
```

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONtend:FE<CH>:ANTenna:CUSTom:FLISt:ROW<DI>
```

class RowCls

Row commands group definition. 1 total commands, 0 Subgroups, 1 group commands Repeated Capability: Index, default value after init: Index.Nr1

get(channel=Channel.Default, index=Index.Default) → int

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONtend:FE<CH>:ANTenna:CUSTom:FLISt:ROW<DI>
value: int = driver.source.areGenerator.frontend.fe.antenna.custom.flist.row.
↪ get(channel = repcap.Channel.Default, index = repcap.Index.Default)
```

Sets the frequency value in the selected row of the list.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param index

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Row')

return

frequency: integer Range: 500E6 to 1E12

set(frequency: int, channel=Channel.Default, index=Index.Default) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONtend:FE<CH>:ANTenna:CUSTom:FLISt:ROW<DI>
driver.source.areGenerator.frontend.fe.antenna.custom.flist.row.set(frequency = ↪
↪ 1, channel = repcap.Channel.Default, index = repcap.Index.Default)
```

Sets the frequency value in the selected row of the list.

param frequency

integer Range: 500E6 to 1E12

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param index

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Row')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.fe.antenna.custom.flist.row.clone()
```

6.16.1.3.3.7 Fpoints**SCPI Command :**

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:FPOints
```

class FpointsCls

Fpoints commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:FPOints
value: int = driver.source.areGenerator.frontend.fe.antenna.custom.fpoints.
    ↪ get(channel = repcap.Channel.Default)
```

Sets the number of frequencies that you want to define in the list.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

return

areg_fe_cust_ant_fp: integer Range: 1 to 512

set(areg_fe_cust_ant_fp: int, channel=Channel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:FPOints
driver.source.areGenerator.frontend.fe.antenna.custom.fpoints.set(areg_fe_cust_
    ↪ ant_fp = 1, channel = repcap.Channel.Default)
```

Sets the number of frequencies that you want to define in the list.

param areg_fe_cust_ant_fp

integer Range: 1 to 512

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

6.16.1.3.3.8 ImportPy

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:IMPort
```

class ImportPyCls

ImportPy commands group definition. 2 total commands, 1 Subgroups, 1 group commands

set(import_filename: str, channel=Channel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:IMPort
driver.source.areGenerator.frontend.fe.antenna.custom.importPy.set(import_
↪ filename = 'abc', channel = repcap.Channel.Default)
```

Imports an external list with file extension *.txt from a directory. The file format is a text file as comma-separated list with the list elements frequency, RX gain and TX gain.

param import_filename
string

param channel
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.fe.antenna.custom.importPy.clone()
```

Subgroups

6.16.1.3.3.9 Predefined

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:IMPort:PREDefined
```

class PredefinedCls

Predefined commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(import_filename: str, channel=Channel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>
↪ :ANTenna:CUSTom:IMPort:PREDefined
driver.source.areGenerator.frontend.fe.antenna.custom.importPy.predefined.
↪ set(import_filename = 'abc', channel = repcap.Channel.Default)
```

Imports a predefined file for standard antennas, stored on the R&S AREG800A.

param import_filename
string

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

6.16.1.3.3.10 Rx<RxIndex>**RepCap Settings**

```
# Range: Nr1 .. Nr16
rc = driver.source.areGenerator.frontend.fe.antenna.custom.rx.repcap_rxIndex_get()
driver.source.areGenerator.frontend.fe.antenna.custom.rx.repcap_rxIndex_set(repcap.
↳ RxIndex.Nr1)
```

class RxCls

Rx commands group definition. 2 total commands, 1 Subgroups, 0 group commands Repeated Capability: RxIndex, default value after init: RxIndex.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.fe.antenna.custom.rx.clone()
```

Subgroups**6.16.1.3.3.11 Glist****SCPI Command :**

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:RX<ST>:GLIST
```

class GlistCls

Glist commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get(channel=Channel.Default, rxIndex=RxIndex.Default) → List[float]

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:RX<ST>:GLIST
value: List[float] = driver.source.areGenerator.frontend.fe.antenna.custom.rx.
↳ glist.get(channel = repcap.Channel.Default, rxIndex = repcap.RxIndex.Default)
```

For TRX-type frontend: Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] LIST. Sets the values for antenna gain RX/TX in the list. Enter all values of the list separated by comma.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

areg_fconf_use_cust_ant_gain_list: No help available

```
set(areg_fconf_use_cust_ant_gain_list: List[float], channel=Channel.Default, rxIndex=RxIndex.Default) →
None
```

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:RX<ST>:GLIST
driver.source.areGenerator.frontend.fe.antenna.custom.rx.glist.set(areg_fconf_
↪use_cust_ant_gain_list = [1.1, 2.2, 3.3], channel = repcap.Channel.Default,
↪rxIndex = repcap.RxIndex.Default)
```

For TRX-type frontend: Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] LIST. Sets the values for antenna gain RX/TX in the list. Enter all values of the list separated by comma.

param areg_fconf_use_cust_ant_gain_list

No help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.fe.antenna.custom.rx.glist.clone()
```

Subgroups

6.16.1.3.3.12 Row<Index>

RepCap Settings

```
# Range: Nr1 .. Nr64
rc = driver.source.areGenerator.frontend.fe.antenna.custom.rx.glist.row.repcap_index_
↪get()
driver.source.areGenerator.frontend.fe.antenna.custom.rx.glist.row.repcap_index_
↪set(repcap.Index.Nr1)
```

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:RX<ST>:GLIST:ROW<DI>
```

class RowCls

Row commands group definition. 1 total commands, 0 Subgroups, 1 group commands Repeated Capability: Index, default value after init: Index.Nr1

```
get(channel=Channel.Default, rxIndex=RxIndex.Default, index=Index.Default) → int
```

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:RX<ST>
↪:GLIST:ROW<DI>
value: int = driver.source.areGenerator.frontend.fe.antenna.custom.rx.glist.row.
```

(continues on next page)

(continued from previous page)

```
↪ get(channel = repcap.Channel.Default, rxIndex = repcap.RxIndex.Default, index =  
↪ repcap.Index.Default)
```

Sets the value for antenna gain RX/TX in the selected row of the list.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

param index

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Row')

return

gain: integer Range: -50 to 50

set(gain: int, channel=Channel.Default, rxIndex=RxIndex.Default, index=Index.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:RX<ST>  
↪ :GLIST:ROW<DI>  
driver.source.areGenerator.frontend.fe.antenna.custom.rx.glist.row.set(gain = 1,  
↪ channel = repcap.Channel.Default, rxIndex = repcap.RxIndex.Default, index =  
↪ repcap.Index.Default)
```

Sets the value for antenna gain RX/TX in the selected row of the list.

param gain

integer Range: -50 to 50

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

param index

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Row')

Cloning the Group

```
# Create a clone of the original group, that exists independently  
group2 = driver.source.areGenerator.frontend.fe.antenna.custom.rx.glist.row.clone()
```

6.16.1.3.3.13 Tx<TxIndexNull>

RepCap Settings

```
# Range: Nr0 .. Nr15
rc = driver.source.areGenerator.frontend.fe.antenna.custom.tx.repcap_txIndexNull_get()
driver.source.areGenerator.frontend.fe.antenna.custom.tx.repcap_txIndexNull_set(repcap.
↳TxIndexNull.Nr0)
```

class TxCls

Tx commands group definition. 2 total commands, 1 Subgroups, 0 group commands Repeated Capability: TxIndexNull, default value after init: TxIndexNull.Nr0

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.fe.antenna.custom.tx.clone()
```

Subgroups

6.16.1.3.3.14 Glist

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:TX<ST0>:GLIST
```

class GlistCls

Glist commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get(channel=Channel.Default, txIndexNull=TxIndexNull.Default) → List[float]

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:TX<ST0>:GLIST
value: List[float] = driver.source.areGenerator.frontend.fe.antenna.custom.tx.
↳glist.get(channel = repcap.Channel.Default, txIndexNull = repcap.TxIndexNull.
↳Default)
```

For TRX-type frontend: Requires [:SOURce<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] LIST. Sets the values for antenna gain RX/TX in the list. Enter all values of the list separated by comma.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

areg_fconf_use_cust_ant_gain_list: No help available

set(areg_fconf_use_cust_ant_gain_list: List[float], channel=Channel.Default, txIndexNull=TxIndexNull.Default) → None


```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:TX<ST0>:GLIST
driver.source.areGenerator.frontend.fe.antenna.custom.tx.glist.set(areg_fconf_
↪ use_cust_ant_gain_list = [1.1, 2.2, 3.3], channel = repcap.Channel.Default,
↪ txIndexNull = repcap.TxIndexNull.Default)
```

For TRX-type frontend: Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] LIST. Sets the values for antenna gain RX/TX in the list. Enter all values of the list separated by comma.

param areg_fconf_use_cust_ant_gain_list

No help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.fe.antenna.custom.tx.glist.clone()
```

Subgroups

6.16.1.3.3.15 Row<Index>

RepCap Settings

```
# Range: Nr1 .. Nr64
rc = driver.source.areGenerator.frontend.fe.antenna.custom.tx.glist.row.repcap_index_
↪ get()
driver.source.areGenerator.frontend.fe.antenna.custom.tx.glist.row.repcap_index_
↪ set(repcap.Index.Nr1)
```

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:TX<ST0>:GLIST:ROW<DI>
```

class RowCls

Row commands group definition. 1 total commands, 0 Subgroups, 1 group commands Repeated Capability: Index, default value after init: Index.Nr1

get(channel=Channel.Default, txIndexNull=TxIndexNull.Default, index=Index.Default) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:TX<ST0>
↪ :GLIST:ROW<DI>
value: int = driver.source.areGenerator.frontend.fe.antenna.custom.tx.glist.row.
↪ get(channel = repcap.Channel.Default, txIndexNull = repcap.TxIndexNull.
↪ Default, index = repcap.Index.Default)
```

Sets the value for antenna gain RX/TX in the selected row of the list.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

param index

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Row')

return

gain: integer Range: -50 to 50

set(gain: int, channel=Channel.Default, txIndexNull=TxIndexNull.Default, index=Index.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna:CUSTom:TX<ST0>
↪:GLIST:ROW<DI>
driver.source.areGenerator.frontend.fe.antenna.custom.tx.glist.row.set(gain = 1,
↪ channel = repcap.Channel.Default, txIndexNull = repcap.TxIndexNull.Default,
↪ index = repcap.Index.Default)
```

Sets the value for antenna gain RX/TX in the selected row of the list.

param gain

integer Range: -50 to 50

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

param index

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Row')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.fe.antenna.custom.tx.glist.row.clone()
```

6.16.1.3.3.16 Ats**SCPI Command :**

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ATS
```

class AtsCls

Ats commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ATS
value: float = driver.source.areGenerator.frontend.fe.ats.get(channel = repcap.
↪ Channel.Default)
```

Sets the angle between frontend and radar sensor. Reference point for the definition of the angle is the center of the frontend. The angle describes the deviation of the position of the frontend from the 0DEG center position of the field of view of the radar.

INTRO_CMD_HELP: We recommend that you zero in regular intervals (at least once a day) , if:

- Positive angle frontend to sensor: counter clockwise deviation of frontend position to center position.
- Negative angle frontend to sensor: clockwise deviation of frontend position to center position.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

return

areg_fe_ats: float Range: -90 to 90

set(areg_fe_ats: float, channel=Channel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ATS
driver.source.areGenerator.frontend.fe.ats.set(areg_fe_ats = 1.0, channel =
↳repcap.Channel.Default)
```

Sets the angle between frontend and radar sensor. Reference point for the definition of the angle is the center of the frontend. The angle describes the deviation of the position of the frontend from the 0DEG center position of the field of view of the radar.

INTRO_CMD_HELP: We recommend that you zero in regular intervals (at least once a day) , if:

- Positive angle frontend to sensor: counter clockwise deviation of frontend position to center position.
- Negative angle frontend to sensor: clockwise deviation of frontend position to center position.

param areg_fe_ats

float Range: -90 to 90

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

6.16.1.3.3.17 Bw

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:BW
```

class BwCls

Bw commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:BW
value: float = driver.source.areGenerator.frontend.fe.bw.get(channel = repcap.
↳Channel.Default)
```

Displays the frequency bandwidth of the output signal of the connected frontend.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

return

areg_fe_bw: float Range: 0 to 10E9

set(areg_fe_bw: float, channel=Channel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:BW
driver.source.areGenerator.frontend.fe.bw.set(areg_fe_bw = 1.0, channel =
↳repcap.Channel.Default)
```

Displays the frequency bandwidth of the output signal of the connected frontend.

param areg_fe_bw

float Range: 0 to 10E9

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

6.16.1.3.3.18 CableCorr

class CableCorrCls

CableCorr commands group definition. 8 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.fe.cableCorr.clone()
```

Subgroups

6.16.1.3.3.19 Connector<Connector>

RepCap Settings

```
# Range: Nr1 .. Nr8
rc = driver.source.areGenerator.frontend.fe.cableCorr.connector.repcap_connector_get()
driver.source.areGenerator.frontend.fe.cableCorr.connector.repcap_connector_set(repcap.
↳Connector.Nr1)
```

class ConnectorCls

Connector commands group definition. 8 total commands, 2 Subgroups, 0 group commands Repeated Capability: Connector, default value after init: Connector.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.fe.cableCorr.connector.clone()
```

Subgroups

6.16.1.3.3.20 Rx<RxIndex>

RepCap Settings

```
# Range: Nr1 .. Nr16
rc = driver.source.areGenerator.frontend.fe.cableCorr.connector.rx.repcap_rxIndex_get()
driver.source.areGenerator.frontend.fe.cableCorr.connector.rx.repcap_rxIndex_set(repcap.
↳ RxIndex.Nr1)
```

class RxCls

Rx commands group definition. 4 total commands, 2 Subgroups, 0 group commands Repeated Capability: RxIndex, default value after init: RxIndex.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.fe.cableCorr.connector.rx.clone()
```

Subgroups

6.16.1.3.3.21 Mode

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONTend:FE<CH>:CABLecorr:CONNector<DI>:RX<ST>:MODE
```

class ModeCls

Mode commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, connector=Connector.Default, rxIndex=RxIndex.Default) → AregCableCorrSour

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONTend:FE<CH>:CABLecorr:CONNector<DI>:RX<ST>
↳ :MODE
value: enums.AregCableCorrSour = driver.source.areGenerator.frontend.fe.
↳ cableCorr.connector.rx.mode.get(channel = repcap.Channel.Default, connector =
↳ repcap.Connector.Default, rxIndex = repcap.RxIndex.Default)
```

Selects the source for cable correction data.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

areg_cabel_cor_mod: USER| S2P| FACTory USER Selects user-defined cable correction data, i.e. fixed values for delay and attenuation. S2P Selects cable correction data from a file with file extension *.s2p. FACTory For TRX-type frontends only. Selects cable correction data for the TRX frontend from factory specification.

set(areg_cabel_cor_mod: AregCableCorrSour, channel=Channel.Default, connector=Connector.Default, rxIndex=RxIndex.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLEcorr:CONNeCtor<DI>:RX<ST>
↪:MODE
driver.source.areGenerator.frontend.fe.cableCorr.connector.rx.mode.set(areg_
↪cabel_cor_mod = enums.AregCableCorrSour.FACTory, channel = repcap.Channel.
↪Default, connector = repcap.Connector.Default, rxIndex = repcap.RxIndex.
↪Default)
```

Selects the source for cable correction data.

param areg_cabel_cor_mod

USER| S2P| FACTory USER Selects user-defined cable correction data, i.e. fixed values for delay and attenuation. S2P Selects cable correction data from a file with file extension *.s2p. FACTory For TRX-type frontends only. Selects cable correction data for the TRX frontend from factory specification.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

6.16.1.3.3.22 User

class UserCls

User commands group definition. 3 total commands, 3 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.fe.cableCorr.connector.rx.user.clone()
```

Subgroups

6.16.1.3.3.23 Attenuation

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLEcorr:CONNector<DI>:RX<ST>:USER:ATTenuation
```

class AttenuationCls

Attenuation commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, connector=Connector.Default, rxIndex=RxIndex.Default) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLEcorr:CONNector<DI>:RX<ST>
↳:USER:ATTenuation
value: float = driver.source.areGenerator.frontend.fe.cableCorr.connector.rx.
↳user.attenuation.get(channel = repcap.Channel.Default, connector = repcap.
↳Connector.Default, rxIndex = repcap.RxIndex.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNector<di> USER or [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNector<di> S2P. Sets a user-defined attenuation value.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

areg_cable_corr_at: float Range: -50 to 50

set(areg_cable_corr_at: float, channel=Channel.Default, connector=Connector.Default, rxIndex=RxIndex.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLEcorr:CONNector<DI>:RX<ST>
↳:USER:ATTenuation
driver.source.areGenerator.frontend.fe.cableCorr.connector.rx.user.attenuation.
```

(continues on next page)

(continued from previous page)

```
↪ set(areg_cable_corr_at = 1.0, channel = repcap.Channel.Default, connector = ↪
↪ repcap.Connector.Default, rxIndex = repcap.RxIndex.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNector<di> USER or [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNector<di> S2P. Sets a user-defined attenuation value.

param areg_cable_corr_at

float Range: -50 to 50

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

6.16.1.3.3.24 Delay

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLEcorr:CONNector<DI>:RX<ST>:USER:DElay
```

class DelayCls

Delay commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, connector=Connector.Default, rxIndex=RxIndex.Default) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLEcorr:CONNector<DI>:RX<ST>
↪ :USER:DElay
value: float = driver.source.areGenerator.frontend.fe.cableCorr.connector.rx.
↪ user.delay.get(channel = repcap.Channel.Default, connector = repcap.Connector.
↪ Default, rxIndex = repcap.RxIndex.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNector<di> USER. Sets a user-defined delay value.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

areg_cable_cor_del: float Range: 0 to 50

set(areg_cable_cor_del: float, channel=Channel.Default, connector=Connector.Default, rxIndex=RxIndex.Default) → None


```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLEcorr:CONNector<DI>:RX<ST>
↳:USER:DElay
driver.source.areGenerator.frontend.fe.cableCorr.connector.rx.user.delay.
↳set(areg_cable_cor_del = 1.0, channel = repcap.Channel.Default, connector =
↳repcap.Connector.Default, rxIndex = repcap.RxIndex.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNector<di>:USER. Sets a user-defined delay value.

param areg_cable_cor_del

float Range: 0 to 50

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

6.16.1.3.3.25 File

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLEcorr:CONNector<DI>:RX<ST>:USER:FILE
```

class FileCls

File commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, connector=Connector.Default, rxIndex=RxIndex.Default) → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLEcorr:CONNector<DI>:RX<ST>
↳:USER:FILE
value: str = driver.source.areGenerator.frontend.fe.cableCorr.connector.rx.user.
↳file.get(channel = repcap.Channel.Default, connector = repcap.Connector.
↳Default, rxIndex = repcap.RxIndex.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNector<di>:S2P. Loads a cable correction data file with file extension *.s2p from the default or the specified directory.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

areg_cable_cor_fil: string

```
set(areg_cable_cor_fil: str, channel=Channel.Default, connector=Connector.Default,
    rxIndex=RxIndex.Default) → None
```

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLeCorr:CONNeCtor<DI>:RX<ST>
↪:USER:FILE
driver.source.areGenerator.frontend.fe.cableCorr.connector.rx.user.file.
↪set(areg_cable_cor_fil = 'abc', channel = repcap.Channel.Default, connector =
↪repcap.Connector.Default, rxIndex = repcap.RxIndex.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLeCorr:CONNeCtor<di> S2P. Loads a cable correction data file with file extension *.s2p from the default or the specified directory.

param areg_cable_cor_fil

string

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

6.16.1.3.3.26 Tx<TxIndexNull>

RepCap Settings

```
# Range: Nr0 .. Nr15
rc = driver.source.areGenerator.frontend.fe.cableCorr.connector.tx.repcap_txIndexNull_
↪get()
driver.source.areGenerator.frontend.fe.cableCorr.connector.tx.repcap_txIndexNull_
↪set(repcap.TxIndexNull.Nr0)
```

class TxCls

Tx commands group definition. 4 total commands, 2 Subgroups, 0 group commands Repeated Capability: TxIndexNull, default value after init: TxIndexNull.Nr0

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.fe.cableCorr.connector.tx.clone()
```

Subgroups

6.16.1.3.3.27 Mode

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLecorr:CONNeCtor<DI>:TX<ST0>:MODE
```

class ModeCls

Mode commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, connector=Connector.Default, txIndexNull=TxIndexNull.Default) → AregCableCorrSour

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLecorr:CONNeCtor<DI>:TX
↳<ST0>:MODE
value: enums.AregCableCorrSour = driver.source.areGenerator.frontend.fe.
↳cableCorr.connector.tx.mode.get(channel = repcap.Channel.Default, connector =
↳repcap.Connector.Default, txIndexNull = repcap.TxIndexNull.Default)
```

Selects the source for cable correction data.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

areg_cabel_cor_mod: USER| S2P| FACTory USER Selects user-defined cable correction data, i.e. fixed values for delay and attenuation. S2P Selects cable correction data from a file with file extension *.s2p. FACTory For TRX-type frontends only. Selects cable correction data for the TRX frontend from factory specification.

set(areg_cabel_cor_mod: AregCableCorrSour, channel=Channel.Default, connector=Connector.Default, txIndexNull=TxIndexNull.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLecorr:CONNeCtor<DI>:TX
↳<ST0>:MODE
driver.source.areGenerator.frontend.fe.cableCorr.connector.tx.mode.set(areg_
↳cabel_cor_mod = enums.AregCableCorrSour.FACTory, channel = repcap.Channel.
↳Default, connector = repcap.Connector.Default, txIndexNull = repcap.
↳TxIndexNull.Default)
```

Selects the source for cable correction data.

param areg_cabel_cor_mod

USER| S2P| FACTory USER Selects user-defined cable correction data, i.e. fixed values for delay and attenuation. S2P Selects cable correction data from a file with file extension *.s2p. FACTory For TRX-type frontends only. Selects cable correction data for the TRX frontend from factory specification.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

6.16.1.3.3.28 User**class UserCls**

User commands group definition. 3 total commands, 3 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.fe.cableCorr.connector.tx.user.clone()
```

Subgroups**6.16.1.3.3.29 Attenuation****SCPI Command :**

```
[SOURce<HW>]:AREGenerator:FRONtend:FE<CH>:CABLEcorr:CONNector<DI>:TX<ST0>
↳:USER:ATTenuation
```

class AttenuationCls

Attenuation commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, connector=Connector.Default, txIndexNull=TxIndexNull.Default) → float

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONtend:FE<CH>:CABLEcorr:CONNector<DI>:TX
↳<ST0>:USER:ATTenuation
value: float = driver.source.areGenerator.frontend.fe.cableCorr.connector.tx.
↳user.attenuation.get(channel = repcap.Channel.Default, connector = repcap.
↳Connector.Default, txIndexNull = repcap.TxIndexNull.Default)
```

Requires [:SOURce<hw>]:AREGenerator:FRONtend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNector<di> USER or [:SOURce<hw>]:AREGenerator:FRONtend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNector<di> S2P. Sets a user-defined attenuation value.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

```

    return
    areg_cable_corr_at: float Range: -50 to 50
set(areg_cable_corr_at: float, channel=Channel.Default, connector=Connector.Default,
    txIndexNull=TxIndexNull.Default) → None

```

```

# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLEcorr:CONNECTor<DI>:TX
↳<ST0>:USER:ATTenuation
driver.source.areGenerator.frontend.fe.cableCorr.connector.tx.user.attenuation.
↳set(areg_cable_corr_at = 1.0, channel = repcap.Channel.Default, connector =
↳repcap.Connector.Default, txIndexNull = repcap.TxIndexNull.Default)

```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> USER or [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> S2P. Sets a user-defined attenuation value.

param areg_cable_corr_at
float Range: -50 to 50

param channel
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param connector
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull
optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

6.16.1.3.3.30 Delay

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLEcorr:CONNECTor<DI>:TX<ST0>:USER:DElay
```

class DelayCls

Delay commands group definition. 1 total commands, 0 Subgroups, 1 group commands

```
get(channel=Channel.Default, connector=Connector.Default, txIndexNull=TxIndexNull.Default) → float
```

```

# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLEcorr:CONNECTor<DI>:TX
↳<ST0>:USER:DElay
value: float = driver.source.areGenerator.frontend.fe.cableCorr.connector.tx.
↳user.delay.get(channel = repcap.Channel.Default, connector = repcap.Connector.
↳Default, txIndexNull = repcap.TxIndexNull.Default)

```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> USER. Sets a user-defined delay value.

param channel
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param connector
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

areg_cable_cor_del: float Range: 0 to 50

set(areg_cable_cor_del: float, channel=Channel.Default, connector=Connector.Default, txIndexNull=TxIndexNull.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLeCorr:CONNector<DI>:TX
↳<ST0>:USER:DElay
driver.source.areGenerator.frontend.fe.cableCorr.connector.tx.user.delay.
↳set(areg_cable_cor_del = 1.0, channel = repcap.Channel.Default, connector =
↳repcap.Connector.Default, txIndexNull = repcap.TxIndexNull.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLeCorr:CONNector<di>:USER. Sets a user-defined delay value.

param areg_cable_cor_del

float Range: 0 to 50

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

6.16.1.3.3.31 File**SCPI Command :**

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLeCorr:CONNector<DI>:TX<ST0>:USER:FILE
```

class FileCls

File commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, connector=Connector.Default, txIndexNull=TxIndexNull.Default) → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLeCorr:CONNector<DI>:TX
↳<ST0>:USER:FILE
value: str = driver.source.areGenerator.frontend.fe.cableCorr.connector.tx.user.
↳file.get(channel = repcap.Channel.Default, connector = repcap.Connector.
↳Default, txIndexNull = repcap.TxIndexNull.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLeCorr:CONNector<di>:S2P. Loads a cable correction data file with file extension *.s2p from the default or the specified directory.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

areg_cable_cor_fil: string

set(areg_cable_cor_fil: str, channel=Channel.Default, connector=Connector.Default, txIndexNull=TxIndexNull.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLeCorr:CONNector<DI>:TX
↳<ST0>:USER:FILE
driver.source.areGenerator.frontend.fe.cableCorr.connector.tx.user.file.
↳set(areg_cable_cor_fil = 'abc', channel = repcap.Channel.Default, connector =
↳repcap.Connector.Default, txIndexNull = repcap.TxIndexNull.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLeCorr:CONNector<di>S2P. Loads a cable correction data file with file extension *.s2p from the default or the specified directory.

param areg_cable_cor_fil

string

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

6.16.1.3.3.32 Center**SCPI Command :**

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CENTer
```

class CenterCls

Center commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CENTer
value: float = driver.source.areGenerator.frontend.fe.center.get(channel =
↳repcap.Channel.Default)
```

Sets the RF center frequency of the output signal of the connected frontend. The frontend center frequency and frequency range depend on the configuration of the R&S AREG800A and the configuration of the frontend included in the test setup. For more information, see the data sheet. When using custom frontends, the IF center frequency instead of the RF center frequency is configurable in the frontend configuration. The IF center frequency with the sensor bandwidth is used for the cable correction, whereas the sensor frequency and bandwidth is used for the antenna correction.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

```

    return
    areg_fe_center_fre: float Range: 0 to 100E9
set(areg_fe_center_fre: float, channel=Channel.Default) → None

```

```

# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CENTer
driver.source.areGenerator.frontend.fe.center.set(areg_fe_center_fre = 1.0,
↪channel = repcap.Channel.Default)

```

Sets the RF center frequency of the output signal of the connected frontend. The frontend center frequency and frequency range depend on the configuration of the R&S AREG800A and the configuration of the frontend included in the test setup. For more information, see the data sheet. When using custom frontends, the IF center frequency instead of the RF center frequency is configurable in the frontend configuration. The IF center frequency with the sensor bandwidth is used for the cable correction, whereas the sensor frequency and bandwidth is used for the antenna correction.

param areg_fe_center_fre
float Range: 0 to 100E9

param channel
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

6.16.1.3.3.33 Connect

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CONNECT
```

class ConnectCls

Connect commands group definition. 1 total commands, 0 Subgroups, 1 group commands

```
set(channel=Channel.Default) → None
```

```

# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CONNECT
driver.source.areGenerator.frontend.fe.connect.set(channel = repcap.Channel.
↪Default)

```

Triggers a connection procedure to connect the R&S AREG800A with the external frontend in the network.

param channel
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

```
set_with_opc(channel=Channel.Default, opc_timeout_ms: int = -1) → None
```

6.16.1.3.3.34 Disconnect

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:DISConnect
```

class DisconnectCls

Disconnect commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(channel=Channel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:DISConnect
driver.source.areGenerator.frontend.fe.disconnect.set(channel = repcap.Channel.
↳Default)
```

Triggers a connection procedure to connect the R&S AREG800A with the external frontend in the network.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

set_with_opc(channel=Channel.Default, opc_timeout_ms: int = -1) → None

6.16.1.3.3.35 Id

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ID
```

class IdCls

Id commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ID
value: int = driver.source.areGenerator.frontend.fe.id.get(channel = repcap.
↳Channel.Default)
```

No command help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

return

areg_fe_id: No help available

6.16.1.3.3.36 Rmv

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:RMV
```

class RmvCls

Rmv commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(channel=Channel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:RMV
driver.source.areGenerator.frontend.fe.rmv.set(channel = repcap.Channel.Default)
```

Removes the configuration of the connected QAT-type, FE-type or custom frontend.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

```
set_with_opc(channel=Channel.Default, opc_timeout_ms: int = -1) → None
```

6.16.1.3.3.37 Rts

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:RTS
```

class RtsCls

Rts commands group definition. 1 total commands, 0 Subgroups, 1 group commands

```
get(channel=Channel.Default) → float
```

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:RTS
value: float = driver.source.areGenerator.frontend.fe.rts.get(channel = repcap.
↳ Channel.Default)
```

Sets the rotation angle between frontend and sensor. Reference point for the definition of the angle is the center of the frontend. The rotation describes the deviation of the position of the frontend from a 90DEG angle to the direct line of sight of the sensor. For TRX-type or custom frontends this parameter has currently no impact, since it is a single sensor and no sensor array.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

return

areg_fe_rts: float Range: -60 to 60

```
set(areg_fe_rts: float, channel=Channel.Default) → None
```

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:RTS
driver.source.areGenerator.frontend.fe.rts.set(areg_fe_rts = 1.0, channel =
↳ repcap.Channel.Default)
```

Sets the rotation angle between frontend and sensor. Reference point for the definition of the angle is the center of the frontend. The rotation describes the deviation of the position of the frontend from a 90DEG angle to the direct line of sight of the sensor. For TRX-type or custom frontends this parameter has currently no impact, since it is a single sensor and no sensor array.

param areg_fe_rts

float Range: -60 to 60

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

6.16.1.3.3.38 Rx<RxIndex>

RepCap Settings

```
# Range: Nr1 .. Nr16
rc = driver.source.areGenerator.frontend.fe.rx.repcap_rxIndex_get()
driver.source.areGenerator.frontend.fe.rx.repcap_rxIndex_set(repcap.RxIndex.Nr1)
```

class RxCls

Rx commands group definition. 2 total commands, 2 Subgroups, 0 group commands Repeated Capability: RxIndex, default value after init: RxIndex.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.fe.rx.clone()
```

Subgroups

6.16.1.3.3.39 Efrontend

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:RX<ST>:EFRontend
```

class EfrontendCls

Efrontend commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, rxIndex=RxIndex.Default) → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:RX<ST>:EFRontend
value: str = driver.source.areGenerator.frontend.fe.rx.efrontend.get(channel = ↵
↵repcap.Channel.Default, rxIndex = repcap.RxIndex.Default)
```

Selects the external frontend to connect to the R&S AREG800A.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

instr_name: string

set(instr_name: str, channel=Channel.Default, rxIndex=RxIndex.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:RX<ST>:EFRontend
driver.source.areGenerator.frontend.fe.rx.efrontend.set(instr_name = 'abc', ↵
↵channel = repcap.Channel.Default, rxIndex = repcap.RxIndex.Default)
```

Selects the external frontend to connect to the R&S AREG800A.

param instr_name

string

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

6.16.1.3.3.40 Ota

class OtaCls

Ota commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.fe.rx.ota.clone()
```

Subgroups

6.16.1.3.3.41 Offset

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:RX<ST>:OTA:OFFSet
```

class OffsetCls

Offset commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, rxIndex=RxIndex.Default) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:RX<ST>:OTA:OFFSet
value: int = driver.source.areGenerator.frontend.fe.rx.ota.offset.get(channel =
↳ repcap.Channel.Default, rxIndex = repcap.RxIndex.Default)
```

Specifies the length of the gap between frontend and target.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

areg_fe_ota_offset: integer Range: 0.01 to 30

set(areg_fe_ota_offset: int, channel=Channel.Default, rxIndex=RxIndex.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:RX<ST>:OTA:OFFSet
driver.source.areGenerator.frontend.fe.rx.ota.offset.set(areg_fe_ota_offset = 1,
↳ channel = repcap.Channel.Default, rxIndex = repcap.RxIndex.Default)
```

Specifies the length of the gap between frontend and target.

param areg_fe_ota_offset
integer Range: 0.01 to 30

param channel
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param rxIndex
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

6.16.1.3.3.42 Status

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:STATUS
```

class StatusCls

Status commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → AregFeQatConnMode

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:STATUS
value: enums.AregFeQatConnMode = driver.source.areGenerator.frontend.fe.status.
    ↪get(channel = repcap.Channel.Default)
```

Queries the connection status of the connected QAT-type or FE-type frontend.

param channel
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

return
areg_fe_qat_status: DISConnected| DIALing| CONNected| CERRor| UPDate| UER-
Ror DISConnected Frontend is disconnected. DIALing Tries to establish a frontend
connection. CONNected Valid frontend connection is established. CERRor Network
connection error. UPDate Update of the network connection is in progress. UERRor
Update of the network connection failed.

6.16.1.3.3.43 Tx<TxIndexNull>

RepCap Settings

```
# Range: Nr0 .. Nr15
rc = driver.source.areGenerator.frontend.fe.tx.repcap_txIndexNull_get()
driver.source.areGenerator.frontend.fe.tx.repcap_txIndexNull_set(repcap.TxIndexNull.Nr0)
```

class TxCls

Tx commands group definition. 2 total commands, 2 Subgroups, 0 group commands Repeated Capability: TxIn-
dexNull, default value after init: TxIndexNull.Nr0

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.fe.tx.clone()
```

Subgroups

6.16.1.3.3.4 Efrontend

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONTend:FE<CH>:TX<ST0>:EFRontend
```

class EfrontendCls

Efrontend commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, txIndexNull=TxIndexNull.Default) → str

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONTend:FE<CH>:TX<ST0>:EFRontend
value: str = driver.source.areGenerator.frontend.fe.tx.efrontend.get(channel =
↳repcap.Channel.Default, txIndexNull = repcap.TxIndexNull.Default)
```

Selects the external frontend to connect to the R&S AREG800A.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

instr_name: string

set(instr_name: str, channel=Channel.Default, txIndexNull=TxIndexNull.Default) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONTend:FE<CH>:TX<ST0>:EFRontend
driver.source.areGenerator.frontend.fe.tx.efrontend.set(instr_name = 'abc',
↳channel = repcap.Channel.Default, txIndexNull = repcap.TxIndexNull.Default)
```

Selects the external frontend to connect to the R&S AREG800A.

param instr_name

string

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

6.16.1.3.3.45 Ota

class OtaCls

Ota commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.fe.tx.ota.clone()
```

Subgroups

6.16.1.3.3.46 Offset

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:TX<ST0>:OTA:OFFSet
```

class OffsetCls

Offset commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default, txIndexNull=TxIndexNull.Default) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:TX<ST0>:OTA:OFFSet
value: int = driver.source.areGenerator.frontend.fe.tx.ota.offset.get(channel =
↳ repcap.Channel.Default, txIndexNull = repcap.TxIndexNull.Default)
```

Specifies the length of the gap between frontend and target.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

areg_fe_ota_offset: integer Range: 0.01 to 30

set(areg_fe_ota_offset: int, channel=Channel.Default, txIndexNull=TxIndexNull.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:TX<ST0>:OTA:OFFSet
driver.source.areGenerator.frontend.fe.tx.ota.offset.set(areg_fe_ota_offset = 1,
↳ channel = repcap.Channel.Default, txIndexNull = repcap.TxIndexNull.Default)
```

Specifies the length of the gap between frontend and target.

param areg_fe_ota_offset

integer Range: 0.01 to 30

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

6.16.1.3.3.47 TypePy

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:TYPE
```

class TypePyCls

TypePy commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → AregFeType

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:TYPE
value: enums.AregFeType = driver.source.areGenerator.frontend.fe.typePy.
    ↪get(channel = repcap.Channel.Default)
```

Queries the type of the connected frontend.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Fe')

return

frontend_type: TRX| QAT| NONE| FE| CFE TRX A TRX-type frontend is connected.
QAT A QAT-type frontend is connected. NONE No frontend is connected. FE An
FE-type frontend is connected. CFE A custom frontend is connected.

6.16.1.3.4 Last

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:LAST:CFE
```

class LastCls

Last commands group definition. 3 total commands, 2 Subgroups, 1 group commands

get_cfe() → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:LAST:CFE
value: int = driver.source.areGenerator.frontend.last.get_cfe()
```

Queries the last added QAT-type, FE-type or custom frontend. Displays the number included in the frontend ID, e.g. '3' for QAT-type frontend ID 'Q3'.

return

areg_fe_last_add_qa: integer Range: 0 to 8

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.last.clone()
```

Subgroups

6.16.1.3.4.1 Fe<ChannelNull>

RepCap Settings

```
# Range: Nr0 .. Nr63
rc = driver.source.areGenerator.frontend.last.fe.repcap_channelNull_get()
driver.source.areGenerator.frontend.last.fe.repcap_channelNull_set(repcap.ChannelNull.
↳Nr0)
```

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONtend:LAST:FE<CH0>
```

class FeCls

Fe commands group definition. 1 total commands, 0 Subgroups, 1 group commands Repeated Capability: ChannelNull, default value after init: ChannelNull.Nr0

get(channelNull=ChannelNull.Default) → int

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONtend:LAST:FE<CH0>
value: int = driver.source.areGenerator.frontend.last.fe.get(channelNull =
↳repcap.ChannelNull.Default)
```

Queries the last added QAT-type, FE-type or custom frontend. Displays the number included in the frontend ID, e.g. '3' for QAT-type frontend ID 'Q3'.

param channelNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Fe')

return

areg_fe_last_add_qa: integer Range: 0 to 8

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.last.fe.clone()
```

6.16.1.3.4.2 Qat<QatFrontent>

RepCap Settings

```
# Range: Nr1 .. Nr8
rc = driver.source.areGenerator.frontend.last.qat.repcap_qatFrontent_get()
driver.source.areGenerator.frontend.last.qat.repcap_qatFrontent_set(repcap.QatFrontent.
↳Nr1)
```

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:LAST:QAT<CH>
```

class QatCls

Qat commands group definition. 1 total commands, 0 Subgroups, 1 group commands Repeated Capability: QatFrontent, default value after init: QatFrontent.Nr1

get(qatFrontent=QatFrontent.Default) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:LAST:QAT<CH>
value: int = driver.source.areGenerator.frontend.last.qat.get(qatFrontent =
↳repcap.QatFrontent.Default)
```

Queries the last added QAT-type, FE-type or custom frontend. Displays the number included in the frontend ID, e.g. '3' for QAT-type frontend ID 'Q3'.

param qatFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Qat')

return

areg_fe_last_add_qa: integer Range: 0 to 8

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.last.qat.clone()
```

6.16.1.3.5 Qat<QatFrontent>

RepCap Settings

```
# Range: Nr1 .. Nr8
rc = driver.source.areGenerator.frontend.qat.repcap_qatFrontent_get()
driver.source.areGenerator.frontend.qat.repcap_qatFrontent_set(repcap.QatFrontent.Nr1)
```

Cloning the Group

```
# Create a clone of the original group, that exists independently  
group2 = driver.source.areGenerator.frontend.qat.clone()
```

Subgroups

6.16.1.3.5.1 Add

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONtend:QAT<CH>:ADD
```

6.16.1.3.5.2 Alias

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONtend:QAT<CH>:ALIAS
```

6.16.1.3.5.3 Ats

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONtend:QAT<CH>:ATS
```

6.16.1.3.5.4 Bw

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONtend:QAT<CH>:BW
```

6.16.1.3.5.5 CableCorr

Cloning the Group

```
# Create a clone of the original group, that exists independently  
group2 = driver.source.areGenerator.frontend.qat.cableCorr.clone()
```

Subgroups

6.16.1.3.5.6 Connector<Connector>

RepCap Settings

```
# Range: Nr1 .. Nr8
rc = driver.source.areGenerator.frontend.qat.cableCorr.connector.repcap_connector_get()
driver.source.areGenerator.frontend.qat.cableCorr.connector.repcap_connector_set(repcap.
↳Connector.Nr1)
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.qat.cableCorr.connector.clone()
```

Subgroups

6.16.1.3.5.7 Rx<RxIndex>

RepCap Settings

```
# Range: Nr1 .. Nr16
rc = driver.source.areGenerator.frontend.qat.cableCorr.connector.rx.repcap_rxIndex_get()
driver.source.areGenerator.frontend.qat.cableCorr.connector.rx.repcap_rxIndex_set(repcap.
↳RxIndex.Nr1)
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.qat.cableCorr.connector.rx.clone()
```

Subgroups

6.16.1.3.5.8 Mode

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONTend:QAT<CH>:CABLEcorr:CONNector<DI>:RX<ST>:MODE
```

6.16.1.3.5.9 User

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.qat.cableCorr.connector.rx.user.clone()
```

Subgroups

6.16.1.3.5.10 Attenuation

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:CABLEcorr:CONNector<DI>:RX<ST>
↳:USER:ATTenuation
```

6.16.1.3.5.11 Delay

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:CABLEcorr:CONNector<DI>:RX<ST>:USER:DELay
```

6.16.1.3.5.12 File

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:CABLEcorr:CONNector<DI>:RX<ST>:USER:FILE
```

6.16.1.3.5.13 Tx<TxIndexNull>

RepCap Settings

```
# Range: Nr0 .. Nr15
rc = driver.source.areGenerator.frontend.qat.cableCorr.connector.tx.repcap_txIndexNull_
↳get()
driver.source.areGenerator.frontend.qat.cableCorr.connector.tx.repcap_txIndexNull_
↳set(repcap.TxIndexNull.Nr0)
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.qat.cableCorr.connector.tx.clone()
```

Subgroups

6.16.1.3.5.14 Mode

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONtend:QAT<CH>:CABLEcorr:CONNector<DI>:TX<ST0>:MODE
```

6.16.1.3.5.15 User

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.qat.cableCorr.connector.tx.user.clone()
```

Subgroups

6.16.1.3.5.16 Attenuation

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONtend:QAT<CH>:CABLEcorr:CONNector<DI>:TX<ST0>
↪:USER:ATTenuation
```

6.16.1.3.5.17 Delay

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONtend:QAT<CH>:CABLEcorr:CONNector<DI>:TX<ST0>:USER:DELay
```

6.16.1.3.5.18 File

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONtend:QAT<CH>:CABLEcorr:CONNector<DI>:TX<ST0>:USER:FILE
```

6.16.1.3.5.19 Center

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:CENTer
```

6.16.1.3.5.20 Channels

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:CHANnels
```

6.16.1.3.5.21 Connect

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:CONNEct
```

6.16.1.3.5.22 Disconnect

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:DISConnect
```

6.16.1.3.5.23 Hostname

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:HOSTname
```

6.16.1.3.5.24 Id

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:ID
```

6.16.1.3.5.25 IPAddress

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:IPADdress
```

6.16.1.3.5.26 Mode

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:MODE
```

6.16.1.3.5.27 Name

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:NAME
```

6.16.1.3.5.28 Or

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:OR
```

6.16.1.3.5.29 Ota

Cloning the Group

```
# Create a clone of the original group, that exists independently  
group2 = driver.source.areGenerator.frontend.qat.ota.clone()
```

Subgroups

6.16.1.3.5.30 Offset

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:OTA:OFFSet
```


6.16.1.3.5.31 Rmv**SCPI Command :**

```
[SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:RMV
```

6.16.1.3.5.32 Rts**SCPI Command :**

```
[SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:RTS
```

6.16.1.3.5.33 Snumber**SCPI Command :**

```
[SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:SNUMBER
```

6.16.1.3.5.34 Status**SCPI Command :**

```
[SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:STATUS
```

6.16.1.3.5.35 TypePy**SCPI Command :**

```
[SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:TYPE
```

6.16.1.3.6 Trx<TrxFrontend>**RepCap Settings**

```
# Range: Nr1 .. Nr4
rc = driver.source.areGenerator.frontend.trx.repcap_trxFrontend_get()
driver.source.areGenerator.frontend.trx.repcap_trxFrontend_set(repcap.TrxFrontend.Nr1)
```

class TrxCls

Trx commands group definition. 38 total commands, 14 Subgroups, 0 group commands Repeated Capability: TrxFrontend, default value after init: TrxFrontend.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.trx.clone()
```

Subgroups

6.16.1.3.6.1 Alias

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ALIAS
```

class AliasCls

Alias commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*trxFrontent*=*TrxFrontent.Default*) → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ALIAS
value: str = driver.source.areGenerator.frontend.trx.alias.get(trxFrontent =
↳repcap.TrxFrontent.Default)
```

Sets the alias of the frontend.

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

return

areg_fe_alias: string

set(*areg_fe_alias*: str, *trxFrontent*=*TrxFrontent.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ALIAS
driver.source.areGenerator.frontend.trx.alias.set(areg_fe_alias = 'abc',
↳trxFrontent = repcap.TrxFrontent.Default)
```

Sets the alias of the frontend.

param *areg_fe_alias*

string

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

6.16.1.3.6.2 Antenna

class AntennaCls

Antenna commands group definition. 16 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.trx.antenna.clone()
```

Subgroups

6.16.1.3.6.3 Custom

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:EXPort
```

class CustomCls

Custom commands group definition. 14 total commands, 7 Subgroups, 1 group commands

export_file(export_filename: str, trxFrontent=TrxFrontent.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:EXPort
driver.source.areGenerator.frontend.trx.antenna.custom.export_file(export_
filename = 'abc', trxFrontent = repcap.TrxFrontent.Default)
```

Exports the defined frequency table to an external list file with file extension *.txt in a directory.

param export_filename

string

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.trx.antenna.custom.clone()
```

Subgroups

6.16.1.3.6.4 Flist

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:FLISt
```

class FlistCls

Flist commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get(*trxFrontent*=*TrxFrontent.Default*) → List[float]

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:FLISt
value: List[float] = driver.source.areGenerator.frontend.trx.antenna.custom.
    ↪flist.get(trxFrontent = repcap.TrxFrontent.Default)
```

For TRX-type frontend: Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] LIST. Sets the values for frequency in the list. Enter all values of the list separated by comma.

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

return

areg_fconf_use_cust_ant_freq_list: No help available

set(*areg_fconf_use_cust_ant_freq_list*: List[float], *trxFrontent*=*TrxFrontent.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:FLISt
driver.source.areGenerator.frontend.trx.antenna.custom.flist.set(areg_fconf_use_
    ↪cust_ant_freq_list = [1.1, 2.2, 3.3], trxFrontent = repcap.TrxFrontent.
    ↪Default)
```

For TRX-type frontend: Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] LIST. Sets the values for frequency in the list. Enter all values of the list separated by comma.

param *areg_fconf_use_cust_ant_freq_list*

No help available

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.trx.antenna.custom.flist.clone()
```

Subgroups

6.16.1.3.6.5 Row<Index>

RepCap Settings

```
# Range: Nr1 .. Nr64
rc = driver.source.areGenerator.frontend.trx.antenna.custom.flist.row.repcap_index_get()
driver.source.areGenerator.frontend.trx.antenna.custom.flist.row.repcap_index_set(repcap.
↳ Index.Nr1)
```

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONtend:TRX<CH>:ANTenna:CUSTom:FLISt:ROW<DI>
```

class RowCls

Row commands group definition. 1 total commands, 0 Subgroups, 1 group commands Repeated Capability: Index, default value after init: Index.Nr1

set(*trxFrontent*=*TrxFrontent.Default*, *index*=*Index.Default*) → int

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONtend:TRX<CH>:ANTenna:CUSTom:FLISt:ROW<DI>
value: int = driver.source.areGenerator.frontend.trx.antenna.custom.flist.row.
↳ get(trxFrontent = repcap.TrxFrontent.Default, index = repcap.Index.Default)
```

Sets the frequency value in the selected row of the list.

param **trxFrontent**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param **index**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Row')

return

frequency: integer Range: 500E6 to 1E12

set(*frequency*: int, *trxFrontent*=*TrxFrontent.Default*, *index*=*Index.Default*) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONtend:TRX<CH>:ANTenna:CUSTom:FLISt:ROW<DI>
driver.source.areGenerator.frontend.trx.antenna.custom.flist.row.set(frequency,
↳ 1, trxFrontent = repcap.TrxFrontent.Default, index = repcap.Index.Default)
```

Sets the frequency value in the selected row of the list.

param **frequency**

integer Range: 500E6 to 1E12

param **trxFrontent**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param **index**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Row')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.trx.antenna.custom.flist.row.clone()
```

6.16.1.3.6.6 FormatPy

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:FORMat
```

class FormatPyCls

FormatPy commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*trxFrontent=TrxFrontent.Default*) → CustAntFormat

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:FORMat
value: enums.CustAntFormat = driver.source.areGenerator.frontend.trx.antenna.
↳ custom.formatPy.get(trxFrontent = repcap.TrxFrontent.Default)
```

No command help available

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

return

areg_fe_trx_an_form: No help available

set(*areg_fe_trx_an_form: CustAntFormat, trxFrontent=TrxFrontent.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:FORMat
driver.source.areGenerator.frontend.trx.antenna.custom.formatPy.set(areg_fe_trx_
↳ an_form = enums.CustAntFormat.CSV, trxFrontent = repcap.TrxFrontent.Default)
```

No command help available

param *areg_fe_trx_an_form*

No help available

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

6.16.1.3.6.7 Fpoints

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:FPOints
```

class FpointsCls

Fpoints commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*trxFrontent*=*TrxFrontent.Default*) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:FPOints
value: int = driver.source.areGenerator.frontend.trx.antenna.custom.fpoints.
↪ get(trxFrontent = repcap.TrxFrontent.Default)
```

Sets the number of frequencies that you want to define in the list.

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

return

areg_fe_cust_ant_fp: integer Range: 1 to 512

set(*areg_fe_cust_ant_fp*: int, *trxFrontent*=*TrxFrontent.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:FPOints
driver.source.areGenerator.frontend.trx.antenna.custom.fpoints.set(areg_fe_cust_
↪ ant_fp = 1, trxFrontent = repcap.TrxFrontent.Default)
```

Sets the number of frequencies that you want to define in the list.

param *areg_fe_cust_ant_fp*

integer Range: 1 to 512

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

6.16.1.3.6.8 ImportPy

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:IMPort
```

class ImportPyCls

ImportPy commands group definition. 2 total commands, 1 Subgroups, 1 group commands

set(*import_filename*: str, *trxFrontent*=*TrxFrontent.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:IMPort
driver.source.areGenerator.frontend.trx.antenna.custom.importPy.set(import_
↪ filename = 'abc', trxFrontent = repcap.TrxFrontent.Default)
```

Imports an external list with file extension *.txt from a directory. The file format is a text file as comma-separated list with the list elements frequency, RX gain and TX gain.

param *import_filename*

string

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.trx.antenna.custom.importPy.clone()
```

Subgroups

6.16.1.3.6.9 Predefined

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:IMPort:PREDefined
```

class PredefinedCls

Predefined commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(import_filename: str, trxFrontent=TrxFrontent.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>
↳:ANTenna:CUSTom:IMPort:PREDefined
driver.source.areGenerator.frontend.trx.antenna.custom.importPy.predefined.
↳set(import_filename = 'abc', trxFrontent = repcap.TrxFrontent.Default)
```

Imports a predefined file for standard antennas, stored on the R&S AREG800A.

param import_filename

string

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

6.16.1.3.6.10 Mode

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:[MODE]
```

class ModeCls

Mode commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(trxFrontent=TrxFrontent.Default) → AregFconfUseCustAntAreg800

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:[MODE]
value: enums.AregFconfUseCustAntAreg800 = driver.source.areGenerator.frontend.
↳trx.antenna.custom.mode.get(trxFrontent = repcap.TrxFrontent.Default)
```

Sets the source for defining the antenna gain.

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

return

areg_fe_trx_an_cust: NONE| LIST NONE The antenna gain for TX and RX is defined by the antenna mounted on the R&S AREG800A. LIST The antenna gain is defined in a list. Define frequency points manually in a table or import an external file with file extension *.csv or *.txt from a directory.

set(areg_fe_trx_an_cust: AregFconfUseCustAntAreg800, trxFrontent=TrxFrontent.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:[MODE]
driver.source.areGenerator.frontend.trx.antenna.custom.mode.set(areg_fe_trx_an_
↪cust = enums.AregFconfUseCustAntAreg800.LIST, trxFrontent = repcap.
↪TrxFrontent.Default)
```

Sets the source for defining the antenna gain.

param areg_fe_trx_an_cust

NONE| LIST NONE The antenna gain for TX and RX is defined by the antenna mounted on the R&S AREG800A. LIST The antenna gain is defined in a list. Define frequency points manually in a table or import an external file with file extension *.csv or *.txt from a directory.

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

6.16.1.3.6.11 Rx<RxIndex>**RepCap Settings**

```
# Range: Nr1 .. Nr16
rc = driver.source.areGenerator.frontend.trx.antenna.custom.rx.repcap_rxIndex_get()
driver.source.areGenerator.frontend.trx.antenna.custom.rx.repcap_rxIndex_set(repcap.
↪RxIndex.Nr1)
```

class RxCls

Rx commands group definition. 3 total commands, 2 Subgroups, 0 group commands Repeated Capability: RxIndex, default value after init: RxIndex.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.trx.antenna.custom.rx.clone()
```

Subgroups

6.16.1.3.6.12 File

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:RX<ST>:FILE
```

class FileCls

File commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*trxFrontent*=*TrxFrontent.Default*, *rxIndex*=*RxIndex.Default*) → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:RX<ST>:FILE
value: str = driver.source.areGenerator.frontend.trx.antenna.custom.rx.file.
↳get(trxFrontent = repcap.TrxFrontent.Default, rxIndex = repcap.RxIndex.
↳Default)
```

No command help available

param **trxFrontent**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param **rxIndex**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

areg_fe_trx_an_file: No help available

set(*areg_fe_trx_an_file*: str, *trxFrontent*=*TrxFrontent.Default*, *rxIndex*=*RxIndex.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:RX<ST>:FILE
driver.source.areGenerator.frontend.trx.antenna.custom.rx.file.set(areg_fe_trx_
↳an_file = 'abc', trxFrontent = repcap.TrxFrontent.Default, rxIndex = repcap.
↳RxIndex.Default)
```

No command help available

param **areg_fe_trx_an_file**

No help available

param **trxFrontent**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param **rxIndex**

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

6.16.1.3.6.13 Glist

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:RX<ST>:GLISt
```

class GlistCls

Glist commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get(*trxFrontent*=*TrxFrontent.Default*, *rxIndex*=*RxIndex.Default*) → List[float]

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:RX<ST>:GLISt
value: List[float] = driver.source.areGenerator.frontend.trx.antenna.custom.rx.
↳glist.get(trxFrontent = repcap.TrxFrontent.Default, rxIndex = repcap.RxIndex.
↳Default)
```

For TRX-type frontend: Requires [:SOURce<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] LIST. Sets the values for antenna gain RX/TX in the list. Enter all values of the list separated by comma.

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param *rxIndex*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

areg_fconf_use_cust_ant_gain_list: No help available

set(*areg_fconf_use_cust_ant_gain_list*: List[float], *trxFrontent*=*TrxFrontent.Default*, *rxIndex*=*RxIndex.Default*) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:RX<ST>:GLISt
driver.source.areGenerator.frontend.trx.antenna.custom.rx.glist.set(areg_fconf_
↳use_cust_ant_gain_list = [1.1, 2.2, 3.3], trxFrontent = repcap.TrxFrontent.
↳Default, rxIndex = repcap.RxIndex.Default)
```

For TRX-type frontend: Requires [:SOURce<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] LIST. Sets the values for antenna gain RX/TX in the list. Enter all values of the list separated by comma.

param *areg_fconf_use_cust_ant_gain_list*

No help available

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param *rxIndex*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.trx.antenna.custom.rx.glist.clone()
```

Subgroups

6.16.1.3.6.14 Row<Index>

RepCap Settings

```
# Range: Nr1 .. Nr64
rc = driver.source.areGenerator.frontend.trx.antenna.custom.rx.glist.row.repcap_index_
    ↪ get()
driver.source.areGenerator.frontend.trx.antenna.custom.rx.glist.row.repcap_index_
    ↪ set(repcap.Index.Nr1)
```

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONtend:TRX<CH>:ANTenna:CUSTom:RX<ST>:GLISt:ROW<DI>
```

class RowCls

Row commands group definition. 1 total commands, 0 Subgroups, 1 group commands Repeated Capability: Index, default value after init: Index.Nr1

get(*trxFrontent*=*TrxFrontent.Default*, *rxIndex*=*RxIndex.Default*, *index*=*Index.Default*) → int

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONtend:TRX<CH>:ANTenna:CUSTom:RX<ST>
    ↪ :GLISt:ROW<DI>
value: int = driver.source.areGenerator.frontend.trx.antenna.custom.rx.glist.
    ↪ row.get(trxFrontent = repcap.TrxFrontent.Default, rxIndex = repcap.RxIndex.
    ↪ Default, index = repcap.Index.Default)
```

Sets the value for antenna gain RX/TX in the selected row of the list.

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param *rxIndex*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

param *index*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Row')

return

gain: integer Range: -50 to 50

set(*gain*: int, *trxFrontent*=*TrxFrontent.Default*, *rxIndex*=*RxIndex.Default*, *index*=*Index.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTOM:RX<ST>
↪:GLIST:ROW<DI>
driver.source.areGenerator.frontend.trx.antenna.custom.rx.glist.row.set(gain =
↪1, trxFrontend = repcap.TrxFrontend.Default, rxIndex = repcap.RxIndex.Default,
↪index = repcap.Index.Default)
```

Sets the value for antenna gain RX/TX in the selected row of the list.

param gain

integer Range: -50 to 50

param trxFrontend

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

param index

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Row')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.trx.antenna.custom.rx.glist.row.clone()
```

6.16.1.3.6.15 Tx<TxIndexNull>

RepCap Settings

```
# Range: Nr0 .. Nr15
rc = driver.source.areGenerator.frontend.trx.antenna.custom.tx.repcap_txIndexNull_get()
driver.source.areGenerator.frontend.trx.antenna.custom.tx.repcap_txIndexNull_set(repcap.
↪TxIndexNull.Nr0)
```

class TxCls

Tx commands group definition. 3 total commands, 2 Subgroups, 0 group commands Repeated Capability: TxIndexNull, default value after init: TxIndexNull.Nr0

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.trx.antenna.custom.tx.clone()
```

Subgroups

6.16.1.3.6.16 File

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:TX<ST0>:FILE
```

class FileCls

File commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*trxFrontent*=*TrxFrontent.Default*, *txIndexNull*=*TxIndexNull.Default*) → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:TX<ST0>:FILE
value: str = driver.source.areGenerator.frontend.trx.antenna.custom.tx.file.
↳get(trxFrontent = repcap.TrxFrontent.Default, txIndexNull = repcap.
↳TxIndexNull.Default)
```

No command help available

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Tx')

param *txIndexNull*

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

areg_fe_trx_an_file: No help available

set(*areg_fe_trx_an_file*: str, *trxFrontent*=*TrxFrontent.Default*, *txIndexNull*=*TxIndexNull.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:TX<ST0>:FILE
driver.source.areGenerator.frontend.trx.antenna.custom.tx.file.set(areg_fe_trx_
↳an_file = 'abc', trxFrontent = repcap.TrxFrontent.Default, txIndexNull =
↳repcap.TxIndexNull.Default)
```

No command help available

param *areg_fe_trx_an_file*

No help available

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Tx')

param *txIndexNull*

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

6.16.1.3.6.17 Glist

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:TX<ST0>:GLIST
```

class GlistCls

Glist commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get(*trxFrontent*=*TrxFrontent.Default*, *txIndexNull*=*TxIndexNull.Default*) → List[float]

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:TX<ST0>:GLIST
value: List[float] = driver.source.areGenerator.frontend.trx.antenna.custom.tx.
↳glist.get(trxFrontent = repcap.TrxFrontent.Default, txIndexNull = repcap.
↳TxIndexNull.Default)
```

For TRX-type frontend: Requires [:SOURce<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] LIST. Sets the values for antenna gain RX/TX in the list. Enter all values of the list separated by comma.

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Tx')

param *txIndexNull*

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

areg_fconf_use_cust_ant_gain_list: No help available

set(*areg_fconf_use_cust_ant_gain_list*: List[float], *trxFrontent*=*TrxFrontent.Default*, *txIndexNull*=*TxIndexNull.Default*) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:TX<ST0>:GLIST
driver.source.areGenerator.frontend.trx.antenna.custom.tx.glist.set(areg_fconf_
↳use_cust_ant_gain_list = [1.1, 2.2, 3.3], trxFrontent = repcap.TrxFrontent.
↳Default, txIndexNull = repcap.TxIndexNull.Default)
```

For TRX-type frontend: Requires [:SOURce<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] LIST. Sets the values for antenna gain RX/TX in the list. Enter all values of the list separated by comma.

param *areg_fconf_use_cust_ant_gain_list*

No help available

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Tx')

param *txIndexNull*

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.trx.antenna.custom.tx.glist.clone()
```

Subgroups

6.16.1.3.6.18 Row<Index>

RepCap Settings

```
# Range: Nr1 .. Nr64
rc = driver.source.areGenerator.frontend.trx.antenna.custom.tx.glist.row.repcap_index_
    ↪ get()
driver.source.areGenerator.frontend.trx.antenna.custom.tx.glist.row.repcap_index_
    ↪ set(repcap.Index.Nr1)
```

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONtend:TRX<CH>:ANTenna:CUSTom:TX<ST0>:GLISt:ROW<DI>
```

class RowCls

Row commands group definition. 1 total commands, 0 Subgroups, 1 group commands Repeated Capability: Index, default value after init: Index.Nr1

get(trxFrontent=TrxFrontent.Default, txIndexNull=TxIndexNull.Default, index=Index.Default) → int

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONtend:TRX<CH>:ANTenna:CUSTom:TX<ST0>
    ↪ :GLISt:ROW<DI>
value: int = driver.source.areGenerator.frontend.trx.antenna.custom.tx.glist.
    ↪ row.get(trxFrontent = repcap.TrxFrontent.Default, txIndexNull = repcap.
    ↪ TxIndexNull.Default, index = repcap.Index.Default)
```

Sets the value for antenna gain RX/TX in the selected row of the list.

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

param index

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Row')

return

gain: integer Range: -50 to 50

set(gain: int, trxFrontent=TrxFrontent.Default, txIndexNull=TxIndexNull.Default, index=Index.Default) → None


```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:CUSTom:TX<ST0>
↪:GLIST:ROW<DI>
driver.source.areGenerator.frontend.trx.antenna.custom.tx.glist.row.set(gain = ↪
↪1, trxFrontent = repcap.TrxFrontent.Default, txIndexNull = repcap.TxIndexNull.
↪Default, index = repcap.Index.Default)
```

Sets the value for antenna gain RX/TX in the selected row of the list.

param gain

integer Range: -50 to 50

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

param index

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Row')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.trx.antenna.custom.tx.glist.row.clone()
```

6.16.1.3.6.19 Gain

class GainCls

Gain commands group definition. 2 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.trx.antenna.gain.clone()
```

Subgroups

6.16.1.3.6.20 Rx

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:GAIN:RX
```

class RxCls

Rx commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*trxFrontent*=*TrxFrontent.Default*) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:GAIN:RX
value: float = driver.source.areGenerator.frontend.trx.antenna.gain.rx.
↪get(trxFrontent = repcap.TrxFrontent.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] NONE.
Displays the antenna gain of the receiving antenna (RX) that is mounted on the R&S AREG800A.

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

return

areg_fe_trx_an_rx: float Range: 0 to 30

set(*areg_fe_trx_an_rx*: float, *trxFrontent*=*TrxFrontent.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:GAIN:RX
driver.source.areGenerator.frontend.trx.antenna.gain.rx.set(areg_fe_trx_an_rx = ↪
↪1.0, trxFrontent = repcap.TrxFrontent.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] NONE.
Displays the antenna gain of the receiving antenna (RX) that is mounted on the R&S AREG800A.

param *areg_fe_trx_an_rx*

float Range: 0 to 30

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

6.16.1.3.6.21 Tx

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:GAIN:TX
```

class TxCls

Tx commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*trxFrontent*=*TrxFrontent.Default*) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:GAIN:TX
value: float = driver.source.areGenerator.frontend.trx.antenna.gain.tx.
↪get(trxFrontent = repcap.TrxFrontent.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] NONE.
Displays the antenna gain of the transmitting antenna (TX) that is mounted on the R&S AREG800A.

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

return

areg_fe_trx_gain_tx: float Range: 0 to 30

set(*areg_fe_trx_gain_tx*: float, *trxFrontent*=*TrxFrontent.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ANTenna:GAIN:TX
driver.source.areGenerator.frontend.trx.antenna.gain.tx.set(areg_fe_trx_gain_tx,
↳= 1.0, trxFrontent = repcap.TrxFrontent.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>:ANTenna:CUSTom[:MODE] NONE.
Displays the antenna gain of the transmitting antenna (TX) that is mounted on the R&S AREG800A.

param areg_fe_trx_gain_tx
float Range: 0 to 30

param trxFrontent
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

6.16.1.3.6.22 Ats

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ATS
```

class AtsCls

Ats commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*trxFrontent*=*TrxFrontent.Default*) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ATS
value: float = driver.source.areGenerator.frontend.trx.ats.get(trxFrontent =
↳ repcap.TrxFrontent.Default)
```

Sets the angle between frontend and radar sensor. Reference point for the definition of the angle is the center of the frontend. The angle describes the deviation of the position of the frontend from the 0DEG center position of the field of view of the radar.

INTRO_CMD_HELP: We recommend that you zero in regular intervals (at least once a day) , if:

- Positive angle frontend to sensor: counter clockwise deviation of frontend position to center position.
- Negative angle frontend to sensor: clockwise deviation of frontend position to center position.

param trxFrontent
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

return
areg_fe_ats: float Range: -90 to 90

set(*areg_fe_ats*: float, *trxFrontent*=*TrxFrontent.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ATS
driver.source.areGenerator.frontend.trx.ats.set(areg_fe_ats = 1.0, trxFrontent,
↳ repcap.TrxFrontent.Default)
```

Sets the angle between frontend and radar sensor. Reference point for the definition of the angle is the center of the frontend. The angle describes the deviation of the position of the frontend from the 0DEG center position of the field of view of the radar.

INTRO_CMD_HELP: We recommend that you zero in regular intervals (at least once a day) , if:

- Positive angle frontend to sensor: counter clockwise deviation of frontend position to center position.
- Negative angle frontend to sensor: clockwise deviation of frontend position to center position.

param areg_fe_at

float Range: -90 to 90

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

6.16.1.3.6.23 Bw

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONtend:TRX<CH>:BW
```

class BwCls

Bw commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*trxFrontent*=*TrxFrontent.Default*) → float

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONtend:TRX<CH>:BW
value: float = driver.source.areGenerator.frontend.trx.bw.get(trxFrontent =
↳repcap.TrxFrontent.Default)
```

Displays the frequency bandwidth of the output signal of the connected frontend.

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

return

areg_fe_bw: float Range: 0 to 10E9

set(*areg_fe_bw*: float, *trxFrontent*=*TrxFrontent.Default*) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONtend:TRX<CH>:BW
driver.source.areGenerator.frontend.trx.bw.set(areg_fe_bw = 1.0, trxFrontent =
↳repcap.TrxFrontent.Default)
```

Displays the frequency bandwidth of the output signal of the connected frontend.

param areg_fe_bw

float Range: 0 to 10E9

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

6.16.1.3.6.24 CableCorr

class CableCorrCls

CableCorr commands group definition. 8 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.trx.cableCorr.clone()
```

Subgroups

6.16.1.3.6.25 Connector<Connector>

RepCap Settings

```
# Range: Nr1 .. Nr8
rc = driver.source.areGenerator.frontend.trx.cableCorr.connector.repcap_connector_get()
driver.source.areGenerator.frontend.trx.cableCorr.connector.repcap_connector_set(repcap.
↳Connector.Nr1)
```

class ConnectorCls

Connector commands group definition. 8 total commands, 2 Subgroups, 0 group commands Repeated Capability: Connector, default value after init: Connector.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.trx.cableCorr.connector.clone()
```

Subgroups

6.16.1.3.6.26 Rx<RxIndex>

RepCap Settings

```
# Range: Nr1 .. Nr16
rc = driver.source.areGenerator.frontend.trx.cableCorr.connector.rx.repcap_rxIndex_get()
driver.source.areGenerator.frontend.trx.cableCorr.connector.rx.repcap_rxIndex_set(repcap.
↳RxIndex.Nr1)
```

class RxCls

Rx commands group definition. 4 total commands, 2 Subgroups, 0 group commands Repeated Capability: RxIndex, default value after init: RxIndex.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.trx.cableCorr.connector.rx.clone()
```

Subgroups

6.16.1.3.6.27 Mode

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:CABLEcorr:CONNECTor<DI>:RX<ST>:MODE
```

class ModeCls

Mode commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*trxFrontent*=*TrxFrontent.Default*, *connector*=*Connector.Default*, *rxIndex*=*RxIndex.Default*) → *AregCableCorrSour*

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:CABLEcorr:CONNECTor<DI>:RX
↳<ST>:MODE
value: enums.AregCableCorrSour = driver.source.areGenerator.frontend.trx.
↳cableCorr.connector.rx.mode.get(trxFrontent = repcap.TrxFrontent.Default,
↳connector = repcap.Connector.Default, rxIndex = repcap.RxIndex.Default)
```

Selects the source for cable correction data.

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param *connector*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param *rxIndex*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

areg_cabel_cor_mod: USER| S2P| FACTory USER Selects user-defined cable correction data, i.e. fixed values for delay and attenuation. S2P Selects cable correction data from a file with file extension *.s2p. FACTory For TRX-type frontends only. Selects cable correction data for the TRX frontend from factory specification.

set(*areg_cabel_cor_mod*: *AregCableCorrSour*, *trxFrontent*=*TrxFrontent.Default*, *connector*=*Connector.Default*, *rxIndex*=*RxIndex.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:CABLEcorr:CONNECTor<DI>:RX
↳<ST>:MODE
driver.source.areGenerator.frontend.trx.cableCorr.connector.rx.mode.set(areg_
↳cabel_cor_mod = enums.AregCableCorrSour.FACTory, trxFrontent = repcap.
↳TrxFrontent.Default, connector = repcap.Connector.Default, rxIndex = repcap.
↳RxIndex.Default)
```

Selects the source for cable correction data.

param areg_cabel_cor_mod

USER| S2P| FACTory USER Selects user-defined cable correction data, i.e. fixed values for delay and attenuation. S2P Selects cable correction data from a file with file extension *.s2p. FACTory For TRX-type frontends only. Selects cable correction data for the TRX frontend from factory specification.

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

6.16.1.3.6.28 User

class UserCls

User commands group definition. 3 total commands, 3 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.trx.cableCorr.connector.rx.user.clone()
```

Subgroups

6.16.1.3.6.29 Attenuation

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONTend:TRX<CH>:CABLEcorr:CONNector<DI>:RX<ST>
↳:USER:ATTenuation
```

class AttenuationCls

Attenuation commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(trxFrontent=TrxFrontent.Default, connector=Connector.Default, rxIndex=RxIndex.Default) → float

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONTend:TRX<CH>:CABLEcorr:CONNector<DI>:RX
↳<ST>:USER:ATTenuation
value: float = driver.source.areGenerator.frontend.trx.cableCorr.connector.rx.
↳user.attenuation.get(trxFrontent = repcap.TrxFrontent.Default, connector =
↳repcap.Connector.Default, rxIndex = repcap.RxIndex.Default)
```

Requires [:SOURce<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNector<di> USER or [:SOURce<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNector<di> S2P. Sets a user-defined attenuation value.

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

areg_cable_corr_at: float Range: -50 to 50

set(areg_cable_corr_at: float, trxFrontent=TrxFrontent.Default, connector=Connector.Default, rxIndex=RxIndex.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:CABLEcorr:CONNECTor<DI>:RX
↳<ST>:USER:ATTenuation
driver.source.areGenerator.frontend.trx.cableCorr.connector.rx.user.attenuation.
↳set(areg_cable_corr_at = 1.0, trxFrontent = repcap.TrxFrontent.Default,
↳connector = repcap.Connector.Default, rxIndex = repcap.RxIndex.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> USER or [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> S2P. Sets a user-defined attenuation value.

param areg_cable_corr_at

float Range: -50 to 50

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

6.16.1.3.6.30 Delay

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:CABLEcorr:CONNECTor<DI>:RX<ST>:USER:DElay
```

class DelayCls

Delay commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(trxFrontent=TrxFrontent.Default, connector=Connector.Default, rxIndex=RxIndex.Default) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:CABLEcorr:CONNECTor<DI>:RX
↳<ST>:USER:DElay
value: float = driver.source.areGenerator.frontend.trx.cableCorr.connector.rx.
↳user.delay.get(trxFrontent = repcap.TrxFrontent.Default, connector = repcap.
↳Connector.Default, rxIndex = repcap.RxIndex.Default)
```


Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> USER. Sets a user-defined delay value.

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

areg_cable_cor_del: float Range: 0 to 50

set(areg_cable_cor_del: float, trxFrontent=TrxFrontent.Default, connector=Connector.Default, rxIndex=RxIndex.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:CABLEcorr:CONNECTor<DI>:RX
↳<ST>:USER:DELAY
driver.source.areGenerator.frontend.trx.cableCorr.connector.rx.user.delay.
↳set(areg_cable_cor_del = 1.0, trxFrontent = repcap.TrxFrontent.Default,
↳connector = repcap.Connector.Default, rxIndex = repcap.RxIndex.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> USER. Sets a user-defined delay value.

param areg_cable_cor_del

float Range: 0 to 50

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

6.16.1.3.6.31 File

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:CABLEcorr:CONNECTor<DI>:RX<ST>:USER:FILE
```

class FileCls

File commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(trxFrontent=TrxFrontent.Default, connector=Connector.Default, rxIndex=RxIndex.Default) → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:CABLEcorr:CONNECTor<DI>:RX
↳<ST>:USER:FILE
```

(continues on next page)

(continued from previous page)

```
value: str = driver.source.areGenerator.frontend.trx.cableCorr.connector.rx.  
↪user.file.get(trxFrontent = repcap.TrxFrontent.Default, connector = repcap.  
↪Connector.Default, rxIndex = repcap.RxIndex.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNector<di>
S2P. Loads a cable correction data file with file extension *.s2p from the default or the specified directory.

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

areg_cable_cor_fil: string

set(areg_cable_cor_fil: str, trxFrontent=TrxFrontent.Default, connector=Connector.Default, rxIndex=RxIndex.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:CABLEcorr:CONNector<DI>:RX  
↪<ST>:USER:FILE  
driver.source.areGenerator.frontend.trx.cableCorr.connector.rx.user.file.  
↪set(areg_cable_cor_fil = 'abc', trxFrontent = repcap.TrxFrontent.Default, ↪  
↪connector = repcap.Connector.Default, rxIndex = repcap.RxIndex.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNector<di>
S2P. Loads a cable correction data file with file extension *.s2p from the default or the specified directory.

param areg_cable_cor_fil

string

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

6.16.1.3.6.32 Tx<TxIndexNull>

RepCap Settings

```
# Range: Nr0 .. Nr15
rc = driver.source.areGenerator.frontend.trx.cableCorr.connector.tx.repcap_txIndexNull_
↪get()
driver.source.areGenerator.frontend.trx.cableCorr.connector.tx.repcap_txIndexNull_
↪set(repcap.TxIndexNull.Nr0)
```

class TxCls

Tx commands group definition. 4 total commands, 2 Subgroups, 0 group commands Repeated Capability: TxIndexNull, default value after init: TxIndexNull.Nr0

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.trx.cableCorr.connector.tx.clone()
```

Subgroups

6.16.1.3.6.33 Mode

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:CABLEcorr:CONNECTor<DI>:TX<ST0>:MODE
```

class ModeCls

Mode commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*trxFrontent*=*TrxFrontent.Default*, *connector*=*Connector.Default*, *txIndexNull*=*TxIndexNull.Default*) → AregCableCorrSour

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:CABLEcorr:CONNECTor<DI>:TX
↪<ST0>:MODE
value: enums.AregCableCorrSour = driver.source.areGenerator.frontend.trx.
↪cableCorr.connector.tx.mode.get(trxFrontent = repcap.TrxFrontent.Default,
↪connector = repcap.Connector.Default, txIndexNull = repcap.TxIndexNull.
↪Default)
```

Selects the source for cable correction data.

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Tx')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

areg_cabel_cor_mod: USER| S2P| FACTory USER Selects user-defined cable correction data, i.e. fixed values for delay and attenuation. S2P Selects cable correction data from a file with file extension *.s2p. FACTory For TRX-type frontends only. Selects cable correction data for the TRX frontend from factory specification.

set(areg_cabel_cor_mod: AregCableCorrSour, trxFrontent=TrxFrontent.Default, connector=Connector.Default, txIndexNull=TxIndexNull.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:CABLEcorr:CONNECTor<DI>:TX
↪<ST0>:MODE
driver.source.areGenerator.frontend.trx.cableCorr.connector.tx.mode.set(areg_
↪cabel_cor_mod = enums.AregCableCorrSour.FACTory, trxFrontent = repcap.
↪TrxFrontent.Default, connector = repcap.Connector.Default, txIndexNull =
↪repcap.TxIndexNull.Default)
```

Selects the source for cable correction data.

param areg_cabel_cor_mod

USER| S2P| FACTory USER Selects user-defined cable correction data, i.e. fixed values for delay and attenuation. S2P Selects cable correction data from a file with file extension *.s2p. FACTory For TRX-type frontends only. Selects cable correction data for the TRX frontend from factory specification.

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Tx')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

6.16.1.3.6.34 User**class UserCls**

User commands group definition. 3 total commands, 3 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.trx.cableCorr.connector.tx.user.clone()
```

Subgroups

6.16.1.3.6.35 Attenuation

SCPI Command :

```
[SOURce<HW>]:AREGenerator:FRONtend:TRX<CH>:CABLe CORR:CONNeCtor<DI>:TX<ST0>
↳:USER:ATTenuation
```

class AttenuationCls

Attenuation commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*trxFrontent*=*TrxFrontent.Default*, *connector*=*Connector.Default*, *txIndexNull*=*TxIndexNull.Default*) → float

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONtend:TRX<CH>:CABLe CORR:CONNeCtor<DI>:TX
↳<ST0>:USER:ATTenuation
value: float = driver.source.areGenerator.frontend.trx.cableCorr.connector.tx.
↳user.attenuation.get(trxFrontent = repcap.TrxFrontent.Default, connector =
↳repcap.Connector.Default, txIndexNull = repcap.TxIndexNull.Default)
```

Requires [:SOURce<hw>]:AREGenerator:FRONtend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLe CORR:CONNeCtor<di> USER or [:SOURce<hw>]:AREGenerator:FRONtend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLe CORR:CONNeCtor<di> S2P. Sets a user-defined attenuation value.

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param *connector*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param *txIndexNull*

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

areg_cable_corr_at: float Range: -50 to 50

set(*areg_cable_corr_at*: float, *trxFrontent*=*TrxFrontent.Default*, *connector*=*Connector.Default*, *txIndexNull*=*TxIndexNull.Default*) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONtend:TRX<CH>:CABLe CORR:CONNeCtor<DI>:TX
↳<ST0>:USER:ATTenuation
driver.source.areGenerator.frontend.trx.cableCorr.connector.tx.user.attenuation.
↳set(areg_cable_corr_at = 1.0, trxFrontent = repcap.TrxFrontent.Default,
↳connector = repcap.Connector.Default, txIndexNull = repcap.TxIndexNull.
↳Default)
```

Requires [:SOURce<hw>]:AREGenerator:FRONtend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLe CORR:CONNeCtor<di> USER or [:SOURce<hw>]:AREGenerator:FRONtend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLe CORR:CONNeCtor<di> S2P. Sets a user-defined attenuation value.

param *areg_cable_corr_at*

float Range: -50 to 50

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

6.16.1.3.6.36 Delay**SCPI Command :**

```
[SOURce<HW>]:AREGenerator:FRONtend:TRX<CH>:CABLEcorr:CONNector<DI>:TX<ST0>:USER:DElay
```

class DelayCls

Delay commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*trxFrontent*=*TrxFrontent.Default*, *connector*=*Connector.Default*, *txIndexNull*=*TxIndexNull.Default*) → float

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONtend:TRX<CH>:CABLEcorr:CONNector<DI>:TX
↳<ST0>:USER:DElay
value: float = driver.source.areGenerator.frontend.trx.cableCorr.connector.tx.
↳user.delay.get(trxFrontent = repcap.TrxFrontent.Default, connector = repcap.
↳Connector.Default, txIndexNull = repcap.TxIndexNull.Default)
```

Requires [:SOURce<hw>]:AREGenerator:FRONtend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNector<di>:USER. Sets a user-defined delay value.

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

areg_cable_cor_del: float Range: 0 to 50

set(*areg_cable_cor_del*: float, *trxFrontent*=*TrxFrontent.Default*, *connector*=*Connector.Default*, *txIndexNull*=*TxIndexNull.Default*) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:FRONtend:TRX<CH>:CABLEcorr:CONNector<DI>:TX
↳<ST0>:USER:DElay
driver.source.areGenerator.frontend.trx.cableCorr.connector.tx.user.delay.
↳set(areg_cable_cor_del = 1.0, trxFrontent = repcap.TrxFrontent.Default,
↳connector = repcap.Connector.Default, txIndexNull = repcap.TxIndexNull.
↳Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> USER. Sets a user-defined delay value.

param areg_cable_cor_del

float Range: 0 to 50

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Tx')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

6.16.1.3.6.37 File

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:CABLEcorr:CONNECTor<DI>:TX<ST0>:USER:FILE
```

class FileCls

File commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*trxFrontent=TrxFrontent.Default, connector=Connector.Default, txIndexNull=TxIndexNull.Default*) → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:CABLEcorr:CONNECTor<DI>:TX
↳<ST0>:USER:FILE
value: str = driver.source.areGenerator.frontend.trx.cableCorr.connector.tx.
↳user.file.get(trxFrontent = repcap.TrxFrontent.Default, connector = repcap.
↳Connector.Default, txIndexNull = repcap.TxIndexNull.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNECTor<di> S2P. Loads a cable correction data file with file extension *.s2p from the default or the specified directory.

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Tx')

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

areg_cable_cor_fil: string

set(*areg_cable_cor_fil: str, trxFrontent=TrxFrontent.Default, connector=Connector.Default, txIndexNull=TxIndexNull.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:CABLEcorr:CONNector<DI>:TX
↳<ST0>:USER:FILE
driver.source.areGenerator.frontend.trx.cableCorr.connector.tx.user.file.
↳set(areg_cable_cor_fil = 'abc', trxFrontent = repcap.TrxFrontent.Default,
↳connector = repcap.Connector.Default, txIndexNull = repcap.TxIndexNull.
↳Default)
```

Requires [:SOURCE<hw>]:AREGenerator:FRONTend:TRX<ch>|QAT<ch>|FE<ch>|CFE<ch>:CABLEcorr:CONNector<di> S2P. Loads a cable correction data file with file extension *.s2p from the default or the specified directory.

param areg_cable_cor_fil
string

param trxFrontent
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

param connector
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull
optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

6.16.1.3.6.38 Center

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:CENTER
```

class CenterCls

Center commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*trxFrontent=TrxFrontent.Default*) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:CENTER
value: float = driver.source.areGenerator.frontend.trx.center.get(trxFrontent =
↳repcap.TrxFrontent.Default)
```

Sets the RF center frequency of the output signal of the connected frontend. The frontend center frequency and frequency range depend on the configuration of the R&S AREG800A and the configuration of the frontend included in the test setup. For more information, see the data sheet. When using custom frontends, the IF center frequency instead of the RF center frequency is configurable in the frontend configuration. The IF center frequency with the sensor bandwidth is used for the cable correction, whereas the sensor frequency and bandwidth is used for the antenna correction.

param trxFrontent
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

return
areg_fe_center_fre: float Range: 0 to 100E9

set(*areg_fe_center_fre: float, trxFrontent=TrxFrontent.Default*) → None


```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:CENTer
driver.source.areGenerator.frontend.trx.center.set(areg_fe_center_fre = 1.0,
↳trxFrontent = repcap.TrxFrontent.Default)
```

Sets the RF center frequency of the output signal of the connected frontend. The frontend center frequency and frequency range depend on the configuration of the R&S AREG800A and the configuration of the frontend included in the test setup. For more information, see the data sheet. When using custom frontends, the IF center frequency instead of the RF center frequency is configurable in the frontend configuration. The IF center frequency with the sensor bandwidth is used for the cable correction, whereas the sensor frequency and bandwidth is used for the antenna correction.

param areg_fe_center_fre

float Range: 0 to 100E9

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

6.16.1.3.6.39 Eirp

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:EIRP
```

class EirpCls

Eirp commands group definition. 3 total commands, 2 Subgroups, 1 group commands

get(trxFrontent=TrxFrontent.Default) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:EIRP
value: float = driver.source.areGenerator.frontend.trx.eirp.get(trxFrontent =
↳repcap.TrxFrontent.Default)
```

Queries the calculated Effective Isotropic Radiated Power of the power sensor connected to the TRX-type frontend.

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

return

areg_radar_eirp: float Range: -150 to 150

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.trx.eirp.clone()
```

Subgroups

6.16.1.3.6.40 Port

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:EIRP:PORT
```

class PortCls

Port commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*trxFrontent*=*TrxFrontent.Default*) → AregMeasPort

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:EIRP:PORT
value: enums.AregMeasPort = driver.source.areGenerator.frontend.trx.eirp.port.
↪get(trxFrontent = repcap.TrxFrontent.Default)
```

Selects the port of the connected R&S NRP power sensor for calculating the EIRP.

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

return

port: POW| AUX POW The R&S NRP power sensor is connected to the 'RX power' port of the frontend. AUX The R&S NRP power sensor is connected to the 'Aux IF Out' port of the R&S AREG800A.

set(*port*: *AregMeasPort*, *trxFrontent*=*TrxFrontent.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:EIRP:PORT
driver.source.areGenerator.frontend.trx.eirp.port.set(port = enums.AregMeasPort.
↪AUX, trxFrontent = repcap.TrxFrontent.Default)
```

Selects the port of the connected R&S NRP power sensor for calculating the EIRP.

param *port*

POW| AUX POW The R&S NRP power sensor is connected to the 'RX power' port of the frontend. AUX The R&S NRP power sensor is connected to the 'Aux IF Out' port of the R&S AREG800A.

param *trxFrontent*

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

6.16.1.3.6.41 Sensor

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:EIRP:SENSOR
```

class SensorCls

Sensor commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*trxFrontent*=*TrxFrontent.Default*) → *AregPowSens*

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:EIRP:SENsOr
value: enums.AregPowSens = driver.source.areGenerator.frontend.trx.eirp.sensor.
↳get(trxFrontent = repcap.TrxFrontent.Default)
```

Selects the R&S NRP power sensor connected to the TRX-type frontend for calculating the EIRP value.

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

return

areg_pow_sen_selec: SEN4| SEN3| SEN2| SEN1| UDEfined
SEN4|SEN3|SEN2|SEN1 Selects the respective R&S NRP power sensor for the TRX-type frontend. UDEfined No R&S NRP power sensor is connected to the TRX-type frontend.

set(*areg_pow_sen_selec*: *AregPowSens*, *trxFrontent*=*TrxFrontent.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:EIRP:SENsOr
driver.source.areGenerator.frontend.trx.eirp.sensor.set(areg_pow_sen_selec =
↳enums.AregPowSens.SEN1, trxFrontent = repcap.TrxFrontent.Default)
```

Selects the R&S NRP power sensor connected to the TRX-type frontend for calculating the EIRP value.

param areg_pow_sen_selec

SEN4| SEN3| SEN2| SEN1| UDEfined SEN4|SEN3|SEN2|SEN1 Selects the respective R&S NRP power sensor for the TRX-type frontend. UDEfined No R&S NRP power sensor is connected to the TRX-type frontend.

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

6.16.1.3.6.42 Gain

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:GAIN
```

class GainCls

Gain commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*trxFrontent*=*TrxFrontent.Default*) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:GAIN
value: int = driver.source.areGenerator.frontend.trx.gain.get(trxFrontent =
↳repcap.TrxFrontent.Default)
```

No command help available

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

return
 areg_fe_gain: No help available

set(areg_fe_gain: int, trxFrontent=TrxFrontent.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:GAIN
driver.source.areGenerator.frontend.trx.gain.set(areg_fe_gain = 1, trxFrontent_
↳= repcap.TrxFrontent.Default)
```

No command help available

param areg_fe_gain
 No help available

param trxFrontent
 optional repeated capability selector. Default value: Nr1 (settable in the interface
 'Trx')

6.16.1.3.6.43 Id

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ID
```

class IdCls

Id commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(trxFrontent=TrxFrontent.Default) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:ID
value: int = driver.source.areGenerator.frontend.trx.id.get(trxFrontent =
↳ repcap.TrxFrontent.Default)
```

No command help available

param trxFrontent
 optional repeated capability selector. Default value: Nr1 (settable in the interface
 'Trx')

return
 areg_fe_id: No help available

6.16.1.3.6.44 Name

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:NAME
```

class NameCls

Name commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(trxFrontent=TrxFrontent.Default) → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:NAME
value: str = driver.source.areGenerator.frontend.trx.name.get(trxFrontend =
↳repcap.TrxFrontend.Default)
```

Queries the name of the connected frontend.

```
param trxFrontend
    optional repeated capability selector. Default value: Nr1 (settable in the interface
    'Trx')

return
    areg_fe_name: string
```

6.16.1.3.6.45 Ota

class OtaCls

Ota commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.frontend.trx.ota.clone()
```

Subgroups

6.16.1.3.6.46 Offset

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:OTA:OFFSet
```

class OffsetCls

Offset commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(trxFrontend=TrxFrontend.Default) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:OTA:OFFSet
value: int = driver.source.areGenerator.frontend.trx.ota.offset.get(trxFrontend,
↳repcap.TrxFrontend.Default)
```

Specifies the length of the gap between frontend and target.

```
param trxFrontend
    optional repeated capability selector. Default value: Nr1 (settable in the interface
    'Trx')

return
    areg_fe_ota_offset: integer Range: 0.01 to 30
```

set(*areg_fe_ota_offset*: int, *trxFrontent*=*TrxFrontent.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:OTA:OFFSet
driver.source.areGenerator.frontend.trx.ota.offset.set(areg_fe_ota_offset = 1,
↳trxFrontent = repcap.TrxFrontent.Default)
```

Specifies the length of the gap between frontend and target.

param areg_fe_ota_offset

integer Range: 0.01 to 30

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

6.16.1.3.6.47 Rts

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:RTS
```

class RtsCls

Rts commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*trxFrontent*=*TrxFrontent.Default*) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:RTS
value: float = driver.source.areGenerator.frontend.trx.rts.get(trxFrontent =
↳repcap.TrxFrontent.Default)
```

Sets the rotation angle between frontend and sensor. Reference point for the definition of the angle is the center of the frontend. The rotation describes the deviation of the position of the frontend from a 90DEG angle to the direct line of sight of the sensor. For TRX-type or custom frontends this parameter has currently no impact, since it is a single sensor and no sensor array.

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

return

areg_fe_rts: float Range: -60 to 60

set(*areg_fe_rts*: float, *trxFrontent*=*TrxFrontent.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:RTS
driver.source.areGenerator.frontend.trx.rts.set(areg_fe_rts = 1.0, trxFrontent_
↳= repcap.TrxFrontent.Default)
```

Sets the rotation angle between frontend and sensor. Reference point for the definition of the angle is the center of the frontend. The rotation describes the deviation of the position of the frontend from a 90DEG angle to the direct line of sight of the sensor. For TRX-type or custom frontends this parameter has currently no impact, since it is a single sensor and no sensor array.

param areg_fe_rts

float Range: -60 to 60

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

6.16.1.3.6.48 Snumber**SCPI Command :**

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:SNUMBER
```

class SnumberCls

Snumber commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*trxFrontent*=*TrxFrontent.Default*) → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:SNUMBER
value: str = driver.source.areGenerator.frontend.trx.snumber.get(trxFrontent =
↳ repcap.TrxFrontent.Default)
```

Queries the 6-digit serial number of the connected frontend.

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

return

areg_fe_ser_number: string

set(*areg_fe_ser_number*: str, *trxFrontent*=*TrxFrontent.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:SNUMBER
driver.source.areGenerator.frontend.trx.snumber.set(areg_fe_ser_number = 'abc',
↳ trxFrontent = repcap.TrxFrontent.Default)
```

Queries the 6-digit serial number of the connected frontend.

param areg_fe_ser_number

string

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Trx')

6.16.1.3.6.49 TypePy**SCPI Command :**

```
[SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:TYPE
```

class TypePyCls

TypePy commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*trxFrontent*=*TrxFrontent.Default*) → AregFeType

```
# SCPI: [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:TYPE
value: enums.AregFeType = driver.source.areGenerator.frontend.trx.typePy.
↪get(trxFrontent = repcap.TrxFrontent.Default)
```

Queries the type of the connected frontend.

param trxFrontent

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Trx’)

return

frontend_type: TRX| QAT| NONE| FE| CFE TRX A TRX-type frontend is connected. QAT A QAT-type frontend is connected. NONE No frontend is connected. FE An FE-type frontend is connected. CFE A custom frontend is connected.

6.16.1.4 Hil

SCPI Commands :

```
[SOURCE<HW>]:AREGenerator:HIL:RATE
[SOURCE<HW>]:AREGenerator:HIL:RECeived
```

class HilCls

Hil commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_rate() → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:HIL:RATE
value: float = driver.source.areGenerator.hil.get_rate()
```

Queries the update rate of HiL/ViL commands that are transmitted via the open simulation interface (OSI)

return

hil: float Range: 0 to 1E9

get_received() → HilDataReceive

```
# SCPI: [SOURCE<HW>]:AREGenerator:HIL:RECeived
value: enums.HilDataReceive = driver.source.areGenerator.hil.get_received()
```

Queries the receive state of HiL/ViL data via the open simulation interface (OSI) .

return

hil_data_received: NOData| RECeived| NOTHil NOData No data received via OSI. RECeived Receives data via OSI. NOTHil Non HiL/ViL-compliant data received via OSI.

set_received(*hil_data_received: HilDataReceive*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:HIL:RECeived
driver.source.areGenerator.hil.set_received(hil_data_received = enums.
↪HilDataReceive.NOData)
```


Queries the receive state of HiL/ViL data via the open simulation interface (OSI) .

param hil_data_received

NOData| RECeived| NOTHiL NOData No data received via OSI. RECeived Receives data via OSI. NOTHiL Non HiL/ViL-compliant data received via OSI.

6.16.1.5 Last

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:LAST:SENSOR
```

class LastCls

Last commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_sensor() → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:LAST:SENSOR
value: int = driver.source.areGenerator.last.get_sensor()
```

Queries the last added sensor. Displays the number included in the sensor ID, e.g. '3' for sensor ID 'S3'.

return

areg_last_sensor: integer Range: 0 to 8

6.16.1.6 Mapping<MappingChannel>

RepCap Settings

```
# Range: Nr1 .. Nr8
rc = driver.source.areGenerator.mapping.repcap_mappingChannel_get()
driver.source.areGenerator.mapping.repcap_mappingChannel_set(repcap.MappingChannel.Nr1)
```

class MappingCls

Mapping commands group definition. 7 total commands, 4 Subgroups, 0 group commands Repeated Capability: MappingChannel, default value after init: MappingChannel.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.mapping.clone()
```

Subgroups

6.16.1.6.1 Adjust

class AdjustCls

Adjust commands group definition. 3 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.mapping.adjust.clone()
```

Subgroups

6.16.1.6.1.1 All

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:MAPPING<CH>:ADJUST:ALL
```

class AllCls

All commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(mappingChannel=MappingChannel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:MAPPING<CH>:ADJUST:ALL
driver.source.areGenerator.mapping.adjust.all.set(mappingChannel = repcap.
↳ MappingChannel.Default)
```

Adjusts the input attenuation of the R&S AREG800A for the applied signal automatically for all output channels.

param mappingChannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Mapping')

set_with_opc(mappingChannel=MappingChannel.Default, opc_timeout_ms: int = -1) → None

6.16.1.6.1.2 Level

class LevelCls

Level commands group definition. 2 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.mapping.adjust.level.clone()
```

Subgroups

6.16.1.6.1.3 DigHeadroom

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:MAPPING<CH>:ADJust:LEVel:DIGHeadroom
```

class DigHeadroomCls

DigHeadroom commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(mappingChannel=MappingChannel.Default) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:MAPPING<CH>:ADJust:LEVel:DIGHeadroom
value: int = driver.source.areGenerator.mapping.adjust.level.digHeadroom.
↪get(mappingChannel = repcap.MappingChannel.Default)
```

Sets the digital headroom of the channel output power.

param mappingChannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Mapping')

return

areg_adjust_dhead: integer Range: 0 to 30

set(areg_adjust_dhead: int, mappingChannel=MappingChannel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:MAPPING<CH>:ADJust:LEVel:DIGHeadroom
driver.source.areGenerator.mapping.adjust.level.digHeadroom.set(areg_adjust_
↪dhead = 1, mappingChannel = repcap.MappingChannel.Default)
```

Sets the digital headroom of the channel output power.

param areg_adjust_dhead

integer Range: 0 to 30

param mappingChannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Mapping')

6.16.1.6.1.4 Otime

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:MAPPING<CH>:ADJUST:LEVEL:OTIME
```

class OtimeCls

Otime commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(mappingChannel=MappingChannel.Default) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:MAPPING<CH>:ADJUST:LEVEL:OTIME
value: int = driver.source.areGenerator.mapping.adjust.level.otime.
↪ get(mappingChannel = repcap.MappingChannel.Default)
```

Sets the observation time to determine peaks of the channel output power level.

param mappingChannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Mapping')

return

areg_adjust_otime: integer Range: 10 to 10000

set(areg_adjust_otime: int, mappingChannel=MappingChannel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:MAPPING<CH>:ADJUST:LEVEL:OTIME
driver.source.areGenerator.mapping.adjust.level.otime.set(areg_adjust_otime = 1,
↪ mappingChannel = repcap.MappingChannel.Default)
```

Sets the observation time to determine peaks of the channel output power level.

param areg_adjust_otime

integer Range: 10 to 10000

param mappingChannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Mapping')

6.16.1.6.2 Psensor

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:MAPPING<CH>:PSENSOR
```

class PsensorCls

Psensor commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(mappingChannel=MappingChannel.Default) → AregChanMappingSensor

```
# SCPI: [SOURCE<HW>]:AREGenerator:MAPPING<CH>:PSENSOR
value: enums.AregChanMappingSensor = driver.source.areGenerator.mapping.psensor.
↪ get(mappingChannel = repcap.MappingChannel.Default)
```

No command help available

param mappingChannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Mapping')

return

areg_mapping_ps_enable: No help available

set(areg_mapping_ps_enable: AregChanMappingSensor, mappingChannel=MappingChannel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:MAPPING<CH>:PSEnSor
driver.source.areGenerator.mapping.psensor.set(areg_mapping_ps_enable = enums.
↪AregChanMappingSensor.NONE, mappingChannel = repcap.MappingChannel.Default)
```

No command help available

param areg_mapping_ps_enable

No help available

param mappingChannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Mapping')

6.16.1.6.3 Sensor**SCPI Command :**

```
[SOURCE<HW>]:AREGenerator:MAPPING<CH>:SENsOr
```

class SensorCls

Sensor commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(mappingChannel=MappingChannel.Default) → AregChanMappingSensor

```
# SCPI: [SOURCE<HW>]:AREGenerator:MAPPING<CH>:SENsOr
value: enums.AregChanMappingSensor = driver.source.areGenerator.mapping.sensor.
↪get(mappingChannel = repcap.MappingChannel.Default)
```

Selects the sensor that is mapped to the radar channel.

param mappingChannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Mapping')

return

areg_mapping_mts: NONE| SEN1| SEN2| SEN4| SEN3| SEN5| SEN6| SEN7| SEN8
NONE No sensor is mapped. SEN1|SEN2|SEN4|SEN3|SEN5|SEN6|SEN7|SEN8 Se-
lects the respective sensor and maps it to the radar channel.

set(areg_mapping_mts: AregChanMappingSensor, mappingChannel=MappingChannel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:MAPPING<CH>:SENsOr
driver.source.areGenerator.mapping.sensor.set(areg_mapping_mts = enums.
↪AregChanMappingSensor.NONE, mappingChannel = repcap.MappingChannel.Default)
```

Selects the sensor that is mapped to the radar channel.

param areg_mapping_mts

NONE| SEN1| SEN2| SEN4| SEN3| SEN5| SEN6| SEN7| SEN8 NONE No sensor is mapped. SEN1|SEN2|SEN4|SEN3|SEN5|SEN6|SEN7|SEN8 Selects the respective sensor and maps it to the radar channel.

param mappingChannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Mapping')

6.16.1.6.4 SubChannel<Subchannel>

RepCap Settings

```
# Range: Nr1 .. Nr16
rc = driver.source.areGenerator.mapping.subChannel.repcap_subchannel_get()
driver.source.areGenerator.mapping.subChannel.repcap_subchannel_set(repcap.Subchannel.
↪Nr1)
```

class SubChannelCls

SubChannel commands group definition. 2 total commands, 2 Subgroups, 0 group commands Repeated Capability: Subchannel, default value after init: Subchannel.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.mapping.subChannel.clone()
```

Subgroups

6.16.1.6.4.1 Adjust

class AdjustCls

Adjust commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.mapping.subChannel.adjust.clone()
```

Subgroups

6.16.1.6.4.2 Level

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:MAPPING<CH>:[SUBChannel<ST>]:ADJust:LEVel
```

class LevelCls

Level commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(mappingChannel=MappingChannel.Default, subchannel=Subchannel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:MAPPING<CH>:[SUBChannel<ST>]:ADJust:LEVel
driver.source.areGenerator.mapping.subChannel.adjust.level.set(mappingChannel =
↳repcap.MappingChannel.Default, subchannel = repcap.Subchannel.Default)
```

Adjusts the input attenuation of the R&S AREG800A for the applied signal automatically for the selected output channel.

param mappingChannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Mapping')

param subchannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sub-Channel')

set_with_opc(mappingChannel=MappingChannel.Default, subchannel=Subchannel.Default, opc_timeout_ms: int = -1) → None

6.16.1.6.4.3 Fe

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:MAPPING<CH>:[SUBChannel<ST>]:FE
```

class FeCls

Fe commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(mappingChannel=MappingChannel.Default, subchannel=Subchannel.Default) → AregChanMappingGui

```
# SCPI: [SOURCE<HW>]:AREGenerator:MAPPING<CH>:[SUBChannel<ST>]:FE
value: enums.AregChanMappingGui = driver.source.areGenerator.mapping.subChannel.
↳fe.get(mappingChannel = repcap.MappingChannel.Default, subchannel = repcap.
↳Subchannel.Default)
```

Maps the external frontend to the IF channel.

param mappingChannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Mapping')

param subchannel

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Sub-Channel’)

return

areg_mapping_ctf: NONE| IFONly| TRX1| TRX2| TRX3| TRX4| QAT1CH1| QAT1CH2| QAT1CH3| QAT1CH4| QAT1CH5| QAT1CH6| QAT1CH7| QAT1CH8| QAT2CH1| QAT2CH2| QAT2CH3| QAT2CH4| QAT2CH5| QAT2CH6| QAT2CH7| QAT2CH8| QAT3CH1| QAT3CH2| QAT3CH3| QAT3CH4| QAT3CH5| QAT3CH6| QAT3CH7| QAT3CH8| QAT4CH1| QAT4CH2| QAT4CH3| QAT4CH4| QAT4CH5| QAT4CH6| QAT4CH7| QAT4CH8| QAT5CH1| QAT5CH2| QAT5CH3| QAT5CH4| QAT5CH5| QAT5CH6| QAT5CH7| QAT5CH8| QAT6CH1| QAT6CH2| QAT6CH3| QAT6CH4| QAT6CH5| QAT6CH6| QAT6CH7| QAT6CH8| QAT7CH1| QAT7CH2| QAT7CH3| QAT7CH4| QAT7CH5| QAT7CH6| QAT7CH7| QAT7CH8| QAT8CH1| QAT8CH2| QAT8CH3| QAT8CH4| QAT8CH5| QAT8CH6| QAT8CH7| QAT8CH8| FE1| FE2| FE3| FE4| CFE1| CFE2| CFE3| CFE4 NONE No frontend is mapped. IFONly Selects the IF interface without known frontend. TRX1|TRX2|TRX3|TRX4 Selects the TRX-type frontend and maps it to the respective radar channel. QAT1CH1|QAT1CH2|QAT1CH3|QAT1CH4|QAT1CH5|QAT1CH6|QAT1CH7|QAT1CH8|QAT2CH1|QAT2CH2|QAT2CH3|QAT2CH4|QAT2CH5|QAT2CH6|QAT2CH7|QAT2CH8 Selects the QAT-type frontend and maps it to the respective radar channel. FE1|FE2|FE3|FE4 Selects the FE-type frontend and maps it to the respective radar channel. CFE1|CFE2|CFE3|CFE4 Selects the custom frontend and maps it to the respective radar channel.

set(areg_mapping_ctf: AregChanMappingGui, mappingChannel=MappingChannel.Default, subchannel=Subchannel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:MAPPING<CH>:[SUBChannel<ST>]:FE
driver.source.areGenerator.mapping.subChannel.fe.set(areg_mapping_ctf = enums.
↳AregChanMappingGui.CFE1, mappingChannel = repcap.MappingChannel.Default,
↳subchannel = repcap.Subchannel.Default)
```

Maps the external frontend to the IF channel.

param areg_mapping_ctf

NONE| IFONly| TRX1| TRX2| TRX3| TRX4| QAT1CH1| QAT1CH2| QAT1CH3| QAT1CH4| QAT1CH5| QAT1CH6| QAT1CH7| QAT1CH8| QAT2CH1| QAT2CH2| QAT2CH3| QAT2CH4| QAT2CH5| QAT2CH6| QAT2CH7| QAT2CH8| QAT3CH1| QAT3CH2| QAT3CH3| QAT3CH4| QAT3CH5| QAT3CH6| QAT3CH7| QAT3CH8| QAT4CH1| QAT4CH2| QAT4CH3| QAT4CH4| QAT4CH5| QAT4CH6| QAT4CH7| QAT4CH8| QAT5CH1| QAT5CH2| QAT5CH3| QAT5CH4| QAT5CH5| QAT5CH6| QAT5CH7| QAT5CH8| QAT6CH1| QAT6CH2| QAT6CH3| QAT6CH4| QAT6CH5| QAT6CH6| QAT6CH7| QAT6CH8| QAT7CH1| QAT7CH2| QAT7CH3| QAT7CH4| QAT7CH5| QAT7CH6| QAT7CH7| QAT7CH8| QAT8CH1| QAT8CH2| QAT8CH3| QAT8CH4| QAT8CH5| QAT8CH6| QAT8CH7| QAT8CH8| FE1| FE2| FE3| FE4| CFE1| CFE2| CFE3| CFE4 NONE No frontend is mapped. IFONly Selects the IF interface without known frontend. TRX1|TRX2|TRX3|TRX4 Selects the TRX-type frontend and maps it to the respective radar channel. QAT1CH1|QAT1CH2|QAT1CH3|QAT1CH4|QAT1CH5|QAT1CH6|QAT1CH7|QAT1CH8|QAT2CH1|QAT2CH2|QAT2CH3|QAT2CH4|QAT2CH5|QAT2CH6|QAT2CH7|QAT2CH8 Selects the QAT-type frontend and maps it to the respective radar channel. FE1|FE2|FE3|FE4 Selects the FE-type frontend and maps it to the respective radar channel. CFE1|CFE2|CFE3|CFE4 Selects the custom frontend and maps it to the respective radar channel.

param mappingChannel

optional repeated capability selector. Default value: Nr1 (settable in the interface

‘Mapping’)

param subchannel

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Sub-Channel’)

6.16.1.7 Marker

class MarkerCls

Marker commands group definition. 3 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.marker.clone()
```

Subgroups

6.16.1.7.1 Object

SCPI Commands :

```
[SOURCE<HW>]:AREGenerator:MARKer:OBJECT:DElay
[SOURCE<HW>]:AREGenerator:MARKer:OBJECT:ONTime
[SOURCE<HW>]:AREGenerator:MARKer:OBJECT:SOURce
```

class ObjectCls

Object commands group definition. 3 total commands, 0 Subgroups, 3 group commands

get_delay() → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:MARKer:OBJECT:DElay
value: int = driver.source.areGenerator.marker.object.get_delay()
```

Sets a delay time for the start of the object marker. The delay time delays the marker signal at the marker output relative to the signal generation start.

return

obj_marker_delay: integer Range: -150000 to 150000

get_ontime() → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:MARKer:OBJECT:ONTime
value: float = driver.source.areGenerator.marker.object.get_ontime()
```

Sets the on time (pulse width) of the object marker.

return

obj_marker_on_time: float Range: 10 to 150000

get_source() → AregObjMarkSource

```
# SCPI: [SOURCE<HW>]:AREGenerator:MARKer:OBJECT:SOURce
value: enums.AregObjMarkSource = driver.source.areGenerator.marker.object.get_
↪source()
```

Sets the marker source used in the test setup.

return

obj_marker_source: SETTING| SCENario| HIL SETTING Sets the object marker after a change in the radar object settings. SCE-
Nario Requires: [:SOURCEhw]:AREGenerator:OSETup:MODE DY-
Namic and [:SOURCEhw]:AREGenerator:OSETup:SOURce SCE-
Nario. Sets the object marker at the restart of the replayed sce-
nario. HIL Requires: [:SOURCEhw]:AREGenerator:OSETup:MODE DY-
Namic. For [:SOURCEhw]:AREGenerator:OSETup:SOURce HIL: requires
[:SOURCEhw]:AREGenerator:OSETup:PROTOCOL ZMQ|DCP|UDP. Sets the ob-
ject marker according to a timestamp defined in the open simulation interface (OSI)
protocol.

set_delay(obj_marker_delay: int) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:MARKer:OBJECT:DELay
driver.source.areGenerator.marker.object.set_delay(obj_marker_delay = 1)
```

Sets a delay time for the start of the object marker. The delay time delays the marker signal at the marker output relative to the signal generation start.

param obj_marker_delay

integer Range: -150000 to 150000

set_ontime(obj_marker_on_time: float) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:MARKer:OBJECT:ONTime
driver.source.areGenerator.marker.object.set_ontime(obj_marker_on_time = 1.0)
```

Sets the on time (pulse width) of the object marker.

param obj_marker_on_time

float Range: 10 to 150000

set_source(obj_marker_source: AregObjMarkSource) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:MARKer:OBJECT:SOURce
driver.source.areGenerator.marker.object.set_source(obj_marker_source = enums.
↪AregObjMarkSource.HIL)
```

Sets the marker source used in the test setup.

param obj_marker_source

SETTING| SCENario| HIL SETTING Sets the object marker after a change in the radar
object settings. SCENario Requires: [:SOURCEhw]:AREGenerator:OSETup:MODE
DYNamic and [:SOURCEhw]:AREGenerator:OSETup:SOURce SCE-
Nario. Sets the object marker at the restart of the replayed sce-
nario. HIL Requires: [:SOURCEhw]:AREGenerator:OSETup:MODE DY-
Namic. For [:SOURCEhw]:AREGenerator:OSETup:SOURce HIL: requires

[[:SOURCEhw]:AREGenerator:OSETup:PROTOCOL ZMQ|DCP|UDP. Sets the object marker according to a timestamp defined in the open simulation interface (OSI) protocol.

6.16.1.8 Measurement

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:MEASurement:KEEPsettings
```

class MeasurementCls

Measurement commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_keep_settings() → bool

```
# SCPI: [SOURCE<HW>]:AREGenerator:MEASurement:KEEPsettings
value: bool = driver.source.areGenerator.measurement.get_keep_settings()
```

Keeps the configurations and connection settings of connected external frontends if preset is activated.

```
return
    keep_settings: 1| ON| 0| OFF
```

set_keep_settings(keep_settings: bool) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:MEASurement:KEEPsettings
driver.source.areGenerator.measurement.set_keep_settings(keep_settings = False)
```

Keeps the configurations and connection settings of connected external frontends if preset is activated.

```
param keep_settings
    1| ON| 0| OFF
```

6.16.1.9 Object<ObjectIx>

RepCap Settings

```
# Range: Nr1 .. Nr12
rc = driver.source.areGenerator.object.repcap_objectIx_get()
driver.source.areGenerator.object.repcap_objectIx_set(repcap.ObjectIx.Nr1)
```

class ObjectCls

Object commands group definition. 8 total commands, 2 Subgroups, 0 group commands Repeated Capability: ObjectIx, default value after init: ObjectIx.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.object.clone()
```

Subgroups

6.16.1.9.1 All

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OBJECT:ALL:[STATE]
```

class AllCls

All commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT:ALL:[STATE]
value: bool = driver.source.areGenerator.object.all.get_state()
```

Activates all available radar objects for a specific channel.

```
return
    global_obj_stat: 1| ON| 0| OFF
```

set_state(global_obj_stat: bool) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT:ALL:[STATE]
driver.source.areGenerator.object.all.set_state(global_obj_stat = False)
```

Activates all available radar objects for a specific channel.

```
param global_obj_stat
    1| ON| 0| OFF
```

6.16.1.9.2 SubChannel<Subchannel>

RepCap Settings

```
# Range: Nr1 .. Nr16
rc = driver.source.areGenerator.object.subChannel.repcap_subchannel_get()
driver.source.areGenerator.object.subChannel.repcap_subchannel_set(repcap.Subchannel.Nr1)
```

class SubChannelCls

SubChannel commands group definition. 7 total commands, 6 Subgroups, 0 group commands Repeated Capability: Subchannel, default value after init: Subchannel.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.object.subChannel.clone()
```

Subgroups

6.16.1.9.2.1 Angle

class AngleCls

Angle commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.object.subChannel.angle.clone()
```

Subgroups

6.16.1.9.2.2 Horizontal

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:ANGLE:HORIZONTAL
```

class HorizontalCls

Horizontal commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(objectIx=ObjectIx.Default, subchannel=Subchannel.Default) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:ANGLE:HORIZONTAL
value: float = driver.source.areGenerator.object.subChannel.angle.horizontal.
↳ get(objectIx = repcap.ObjectIx.Default, subchannel = repcap.Subchannel.
↳ Default)
```

Sets the horizontal angle of the simulated radar object.

param objectIx

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Object')

param subchannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'SubChannel')

return

areg_obj_hor_angle: float Range: -90 to 90

set(areg_obj_hor_angle: float, objectIx=ObjectIx.Default, subchannel=Subchannel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:ANGLE:HORizontal
driver.source.areGenerator.object.subChannel.angle.horizontal.set(areg_obj_hor_
↪ angle = 1.0, objectIx = repcap.ObjectIx.Default, subchannel = repcap.
↪ Subchannel.Default)
```

Sets the horizontal angle of the simulated radar object.

param areg_obj_hor_angle

float Range: -90 to 90

param objectIx

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Object')

param subchannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sub-Channel')

6.16.1.9.2.3 Attenuation

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:ATTenuation
```

class AttenuationCls

Attenuation commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(objectIx=ObjectIx.Default, subchannel=Subchannel.Default) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:ATTenuation
value: float = driver.source.areGenerator.object.subChannel.attenuation.
↪ get(objectIx = repcap.ObjectIx.Default, subchannel = repcap.Subchannel.
↪ Default)
```

Requires [:SOURCE<hw>]:AREGenerator:UNITs:KCONstant ATT. Sets the attenuation of the simulated radar object. The attenuation depends on the input power, i.e. a lower input signal can be amplified more. If the gain control reaches the upper limit, a message is displayed.

param objectIx

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Object')

param subchannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sub-Channel')

return

areg_obj_att: float Range: -90 to 90

set(areg_obj_att: float, objectIx=ObjectIx.Default, subchannel=Subchannel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:ATTenuation
driver.source.areGenerator.object.subChannel.attenuation.set(areg_obj_att = 1.0,
↪ objectIx = repcap.ObjectIx.Default, subchannel = repcap.Subchannel.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:UNITs:KCONstant ATT. Sets the attenuation of the simulated radar object. The attenuation depends on the input power, i.e. a lower input signal can be amplified more. If the gain control reaches the upper limit, a message is displayed.

param areg_obj_att

float Range: -90 to 90

param objectIx

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Object')

param subchannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sub-Channel')

6.16.1.9.2.4 Doppler

class DopplerCls

Doppler commands group definition. 2 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.object.subChannel.doppler.clone()
```

Subgroups

6.16.1.9.2.5 Frequency

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:DOPPLer:FREQuency
```

class FrequencyCls

Frequency commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(objectIx=ObjectIx.Default, subchannel=Subchannel.Default) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:DOPPLer:FREQuency
value: float = driver.source.areGenerator.object.subChannel.doppler.frequency.
↪get(objectIx = repcap.ObjectIx.Default, subchannel = repcap.Subchannel.
↪Default)
```

Requires [:SOURCE<hw>]:AREGenerator:UNITs:DOPPLer FREQuency. Sets the doppler shift of the simulated radar object.

param objectIx

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Object')

param subchannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sub-Channel')

return
 areg_ob_dopp_freq: float Range: depends on settings to depends on settings
set(areg_ob_dopp_freq: float, objectIx=ObjectIx.Default, subchannel=Subchannel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:DOPPLer:FREQuency
driver.source.areGenerator.object.subChannel.doppler.frequency.set(areg_ob_dopp_
↪freq = 1.0, objectIx = repcap.ObjectIx.Default, subchannel = repcap.
↪Subchannel.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:UNITs:DOPPLer FREQuency. Sets the doppler shift of the simulated radar object.

param areg_ob_dopp_freq
 float Range: depends on settings to depends on settings
param objectIx
 optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Object’)
param subchannel
 optional repeated capability selector. Default value: Nr1 (settable in the interface ‘SubChannel’)

6.16.1.9.2.6 Speed

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:DOPPLer:[SPEed]
```

class SpeedCls

Speed commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(objectIx=ObjectIx.Default, subchannel=Subchannel.Default) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:DOPPLer:[SPEed]
value: float = driver.source.areGenerator.object.subChannel.doppler.speed.
↪get(objectIx = repcap.ObjectIx.Default, subchannel = repcap.Subchannel.
↪Default)
```

Requires [:SOURCE<hw>]:AREGenerator:UNITs:DOPPLer SPEed. Sets the Doppler speed of the simulated radar object.

param objectIx
 optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Object’)
param subchannel
 optional repeated capability selector. Default value: Nr1 (settable in the interface ‘SubChannel’)
return
 areg_object_dopp: float Range: -500 to 500

set(areg_object_dopp: float, objectIx=ObjectIx.Default, subchannel=Subchannel.Default) → None


```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:DOPPLer:[SPEEd]
driver.source.areGenerator.object.subChannel.doppler.speed.set(areg_object_dopp_
↪= 1.0, objectIx = repcap.ObjectIx.Default, subchannel = repcap.Subchannel.
↪Default)
```

Requires [:SOURCE<hw>]:AREGenerator:UNITs:DOPPLer SPEEd. Sets the Doppler speed of the simulated radar object.

param areg_object_dopp
float Range: -500 to 500

param objectIx
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Object')

param subchannel
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sub-Channel')

6.16.1.9.2.7 Range

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:RANGE
```

class RangeCls

Range commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(objectIx=ObjectIx.Default, subchannel=Subchannel.Default) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:RANGE
value: float = driver.source.areGenerator.object.subChannel.range.get(objectIx_
↪= repcap.ObjectIx.Default, subchannel = repcap.Subchannel.Default)
```

Sets the range of the simulated radar object. The range depends on the installed option and on the cable delay settings, the air gap and the bandwidth option.

param objectIx
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Object')

param subchannel
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sub-Channel')

return
areg_obj_range: float Range: depends on settings to depends on settings

6.16.1.9.2.8 Rcs

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:RCS
```

class RcsCls

Rcs commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*objectIx=ObjectIx.Default, subchannel=Subchannel.Default*) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:RCS
value: float = driver.source.areGenerator.object.subChannel.rcs.get(objectIx =
↳repcap.ObjectIx.Default, subchannel = repcap.Subchannel.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:UNITs:KCONstant RCS. Sets the radar cross section of the radar object. The radar cross section is calculated with the corresponding values for attenuation via the radar equation.

param objectIx

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Object')

param subchannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'SubChannel')

return

areg_obj_rcs: float Range: -100 to 100

set(*areg_obj_rcs: float, objectIx=ObjectIx.Default, subchannel=Subchannel.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:RCS
driver.source.areGenerator.object.subChannel.rcs.set(areg_obj_rcs = 1.0,
↳objectIx = repcap.ObjectIx.Default, subchannel = repcap.Subchannel.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:UNITs:KCONstant RCS. Sets the radar cross section of the radar object. The radar cross section is calculated with the corresponding values for attenuation via the radar equation.

param areg_obj_rcs

float Range: -100 to 100

param objectIx

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Object')

param subchannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'SubChannel')

6.16.1.9.2.9 State

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:[STATE]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(objectIx=ObjectIx.Default, subchannel=Subchannel.Default) → bool

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:[STATE]
value: bool = driver.source.areGenerator.object.subChannel.state.get(objectIx =
↳repcap.ObjectIx.Default, subchannel = repcap.Subchannel.Default)
```

Activates simulation of the radar object.

param objectIx

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Object')

param subchannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'SubChannel')

return

areg_obj_state: 1| ON| 0| OFF

set(areg_obj_state: bool, objectIx=ObjectIx.Default, subchannel=Subchannel.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:[STATE]
driver.source.areGenerator.object.subChannel.state.set(areg_obj_state = False,
↳objectIx = repcap.ObjectIx.Default, subchannel = repcap.Subchannel.Default)
```

Activates simulation of the radar object.

param areg_obj_state

1| ON| 0| OFF

param objectIx

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Object')

param subchannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'SubChannel')

6.16.1.10 Objects

class ObjectsCls

Objects commands group definition. 4 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.objects.clone()
```

Subgroups

6.16.1.10.1 Invalid

SCPI Commands :

```
[SOURCE<HW>]:AREGenerator:OBjects:INValid:CATalog
[SOURCE<HW>]:AREGenerator:OBjects:INValid
```

class InvalidCls

Invalid commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_catalog() → List[str]

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBjects:INValid:CATalog
value: List[str] = driver.source.areGenerator.objects.invalid.get_catalog()
```

Queries the content of the 'Invalid objects' table. Lists the header and all values for the respective object number.

```
return
    areg_obj_invalid_cat: No help available
```

get_value() → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBjects:INValid
value: int = driver.source.areGenerator.objects.invalid.get_value()
```

Specifies the number of invalid radar objects for a specific channel.

```
return
    numb_of_invalid_ob: integer Range: 0 to 8
```

6.16.1.10.2 Valid

SCPI Commands :

```
[SOURCE<HW>]:AREGenerator:OBJECTs:VALid:CATalog
[SOURCE<HW>]:AREGenerator:OBJECTs:VALid
```

class ValidCls

Valid commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_catalog() → List[str]

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECTs:VALid:CATalog
value: List[str] = driver.source.areGenerator.objects.valid.get_catalog()
```

Queries the content of the 'valid objects' table. Lists the header and all values for the respective object number.

return
areg_obj_valid_cat: No help available

get_value() → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECTs:VALid
value: int = driver.source.areGenerator.objects.valid.get_value()
```

Specifies the number of valid radar objects for a specific channel.

return
numb_of_valid_obj: integer Range: 0 to 64

set_value(numb_of_valid_obj: int) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECTs:VALid
driver.source.areGenerator.objects.valid.set_value(numb_of_valid_obj = 1)
```

Specifies the number of valid radar objects for a specific channel.

param numb_of_valid_obj
integer Range: 0 to 64

6.16.1.11 Omonitoring

SCPI Commands :

```
[SOURCE<HW>]:AREGenerator:OMONitoring:HOSTname
[SOURCE<HW>]:AREGenerator:OMONitoring:PORT
[SOURCE<HW>]:AREGenerator:OMONitoring:[STATe]
```

class OmonitoringCls

Omonitoring commands group definition. 3 total commands, 0 Subgroups, 3 group commands

get_hostname() → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:OMONitoring:HOSTname
value: str = driver.source.areGenerator.omonitoring.get_hostname()
```

Sets hostname or IP address of the host (external PC) where the objects get streamed to.

```
return
    mon_hostname: string
```

get_port() → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:OMONitoring:PORT
value: int = driver.source.areGenerator.omonitoring.get_port()
```

Sets the port of the host (external PC) where the objects get streamed to.

```
return
    mon_port: integer Range: 0 to 65535
```

get_state() → bool

```
# SCPI: [SOURCE<HW>]:AREGenerator:OMONitoring:[STATE]
value: bool = driver.source.areGenerator.omonitoring.get_state()
```

Sets the streaming state.

```
return
    mon_state: 1| ON| 0| OFF
```

set_hostname(mon_hostname: str) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OMONitoring:HOSTname
driver.source.areGenerator.omonitoring.set_hostname(mon_hostname = 'abc')
```

Sets hostname or IP address of the host (external PC) where the objects get streamed to.

```
param mon_hostname
    string
```

set_port(mon_port: int) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OMONitoring:PORT
driver.source.areGenerator.omonitoring.set_port(mon_port = 1)
```

Sets the port of the host (external PC) where the objects get streamed to.

```
param mon_port
    integer Range: 0 to 65535
```

set_state(mon_state: bool) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OMONitoring:[STATE]
driver.source.areGenerator.omonitoring.set_state(mon_state = False)
```

Sets the streaming state.

```
param mon_state
    1| ON| 0| OFF
```

6.16.1.12 Osetup

SCPI Commands :

```
SOURce<HW>:AREGenerator:OSETup:CONFig
[SOURce<HW>]:AREGenerator:OSETup:HOSTName
[SOURce<HW>]:AREGenerator:OSETup:IPAddress
[SOURce<HW>]:AREGenerator:OSETup:MODE
[SOURce<HW>]:AREGenerator:OSETup:PORT
[SOURce<HW>]:AREGenerator:OSETup:PROTocol
[SOURce<HW>]:AREGenerator:OSETup:REFeRence
[SOURce<HW>]:AREGenerator:OSETup:SOURce
[SOURce<HW>]:AREGenerator:OSETup:TBASE
```

class OsetupCls

Osetup commands group definition. 24 total commands, 5 Subgroups, 9 group commands

get_config() → OsetupConfiguration

```
# SCPI: SOURce<HW>:AREGenerator:OSETup:CONFig
value: enums.OsetupConfiguration = driver.source.areGenerator.osetup.get_
↪ config()
```

Sets the configuration mode of the IF output channel.

return

mode_llm: STD|NR STD The IF output channel works in standard mode. NR Requires R&S AREG8-K814. The IF output channel works in FMCW near range mode. This setting provides low latency at the IF output and allows you to simulate minimum distances between frontend and DUT of the length of the air gap.

get_hostname() → str

```
# SCPI: [SOURce<HW>]:AREGenerator:OSETup:HOSTName
value: str = driver.source.areGenerator.osetup.get_hostname()
```

Requires 'Data Source > HiL/ViL'. Sets the hostname of the R&S AREG800A for the hardware in the loop (HiL) or vehicle in the loop (ViL) scenario controller.

return

areg_osetup_ip_address: No help available

get_ip_address() → str

```
# SCPI: [SOURce<HW>]:AREGenerator:OSETup:IPAddress
value: str = driver.source.areGenerator.osetup.get_ip_address()
```

Requires 'Data Source > HiL/ViL'. Sets the IP address of the R&S AREG800A for the hardware in the loop (HiL) or vehicle in the loop (ViL) scenario controller.

return

areg_osetup_ip_address: No help available

get_mode() → OsetupMode

```
# SCPI: [SOURce<HW>]:AREGenerator:OSETup:MODE
value: enums.OsetupMode = driver.source.areGenerator.osetup.get_mode()
```

Define the operation setup mode.

return
 areg_aset_mode: STATic| DYNamic
 STATic Simulates static radar objects. DYNamic
 Simulates dynamic radar objects.

get_port() → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:PORT
value: int = driver.source.areGenerator.asetup.get_port()
```

Requires 'Data Source > HiL/ViL'. Sets the host port of the instrument for the hardware in the loop (HiL) or vehicle in the loop (ViL) scenario controller.

return
 areg_aset_port: integer Range: 0 to 64000

get_protocol() → OsetupHilProtocol

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:PROTocol
value: enums.OsetupHilProtocol = driver.source.areGenerator.asetup.get_
protocol()
```

Sets the protocol type for protocol data of hardware in the loop (HiL) or vehicle in the loop (ViL) scenarios.

return
 areg_aset_protocol: ZMQ| DCP| UDP| UDPR
 ZMQ Zero message queue (ZMQ) asyn-
 chronous messaging library. The expected payload is the SensorData defined in the
 open simulation interface (OSI) . DCP Distributed co-simulation protocol (DCP) . The
 expected payload is the SensorData defined in the open simulation interface (OSI) .
 UDP User datagram protocol (UDP) . The expected payload is the SensorData defined
 in the open simulation interface (OSI) . UDPR User datagram protocol (UDP) raw
 data. Raw is a Rohde & Schwarz proprietary format.

get_reference() → OsetupObjRef

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:REFerence
value: enums.OsetupObjRef = driver.source.areGenerator.asetup.get_reference()
```

Sets the object reference.

return
 areg_asetup_ref: ORIGin| MAPPed ORIGin
 Sets the object reference to the origin in
 the polar coordinates map. MAPPed Sets a mapped sensor as object reference.

get_source() → OsetupDataSource

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:SOURce
value: enums.OsetupDataSource = driver.source.areGenerator.asetup.get_source()
```

Requires [:SOURCE<hw>]:AREGenerator:OSETup:MODE DYNamic. Sets the data source for the dynamic operation.

return
 areg_aset_source: SCENario| HIL SCENario
 Sets for dynamic radar object simulation
 scenarios. HIL Sets the data source to hardware in the loop (HiL) or vehicle in the loop
 (ViL) scenarios.

get_tbase() → AregSetupTimeBase

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:TBASE
value: enums.AregSetupTimeBase = driver.source.areGenerator.oseup.get_tbase()
```

Sets the time base of the logged data.

return

setup_time_base: SYSTem| SIMulation SYSTem The system time from the setup menu serves as time base. SIMulation The time stamp from the used scenario, e.g. from an OSI message, serves as time base.

set_config(mode_llm: OsetupConfiguration) → None

```
# SCPI: SOURCE<HW>:AREGenerator:OSETup:CONFig
driver.source.areGenerator.oseup.set_config(mode_llm = enums.
↳ OsetupConfiguration.NR)
```

Sets the configuration mode of the IF output channel.

param mode_llm

STD| NR STD The IF output channel works in standard mode. NR Requires R&S AREG8-K814. The IF output channel works in FMCW near range mode. This setting provides low latency at the IF output and allows you to simulate minimum distances between frontend and DUT of the length of the air gap.

set_hostname(areg_oseup_ip_address: str) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:HOSTName
driver.source.areGenerator.oseup.set_hostname(areg_oseup_ip_address = 'abc')
```

Requires 'Data Source > HiL/ViL'. Sets the hostname of the R&S AREG800A for the hardware in the loop (HiL) or vehicle in the loop (ViL) scenario controller.

param areg_oseup_ip_address

No help available

set_ip_address(areg_oseup_ip_address: str) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:IPAddress
driver.source.areGenerator.oseup.set_ip_address(areg_oseup_ip_address = 'abc')
```

Requires 'Data Source > HiL/ViL'. Sets the IP address of the R&S AREG800A for the hardware in the loop (HiL) or vehicle in the loop (ViL) scenario controller.

param areg_oseup_ip_address

string Range: 0.0.0.0. to ff.ff.ff.ff

set_mode(areg_oseup_mode: OsetupMode) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:MODE
driver.source.areGenerator.oseup.set_mode(areg_oseup_mode = enums.OsetupMode.
↳ DYNamic)
```

Define the operation setup mode.

param areg_oseup_mode

STATic| DYNamic STATic Simulates static radar objects. DYNamic Simulates dynamic radar objects.

set_port(*areg_aset_port*: int) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:PORT
driver.source.areGenerator.asetup.set_port(areg_aset_port = 1)
```

Requires 'Data Source > HiL/ViL'. Sets the host port of the instrument for the hardware in the loop (HiL) or vehicle in the loop (ViL) scenario controller.

param areg_aset_port
integer Range: 0 to 64000

set_protocol(*areg_aset_protocol*: *OsetupHilProtocol*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:PROTOCOL
driver.source.areGenerator.asetup.set_protocol(areg_aset_protocol = enums.
↳OsetupHilProtocol.DCP)
```

Sets the protocol type for protocol data of hardware in the loop (HiL) or vehicle in the loop (ViL) scenarios.

param areg_aset_protocol
ZMQ| DCP| UDP| UDPR ZMQ Zero message queue (ZMQ) asynchronous messaging library. The expected payload is the SensorData defined in the open simulation interface (OSI) . DCP Distributed co-simulation protocol (DCP) . The expected payload is the SensorData defined in the open simulation interface (OSI) . UDP User datagram protocol (UDP) . The expected payload is the SensorData defined in the open simulation interface (OSI) . UDPR User datagram protocol (UDP) raw data. Raw is a Rohde & Schwarz proprietary format.

set_reference(*areg_aset_ref*: *OsetupObjRef*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:REFERENCE
driver.source.areGenerator.asetup.set_reference(areg_aset_ref = enums.
↳OsetupObjRef.MAPPED)
```

Sets the object reference.

param areg_aset_ref
ORIGIN| MAPPED ORIGIN Sets the object reference to the origin in the polar coordinates map. MAPPED Sets a mapped sensor as object reference.

set_source(*areg_aset_source*: *OsetupDataSource*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:SOURCE
driver.source.areGenerator.asetup.set_source(areg_aset_source = enums.
↳OsetupDataSource.HIL)
```

Requires [:SOURCE<hw>]:AREGenerator:OSETup:MODE DYNAMIC. Sets the data source for the dynamic operation.

param areg_aset_source
SCENARIO| HIL SCENARIO Sets for dynamic radar object simulation scenarios. HIL Sets the data source to hardware in the loop (HiL) or vehicle in the loop (ViL) scenarios.

set_tbase(*setup_time_base*: *AregSetupTimeBase*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:TBASE
driver.source.areGenerator.asetup.set_tbase(setup_time_base = enums.
↳AregSetupTimeBase.SIMulation)
```

Sets the time base of the logged data.

param setup_time_base

SYSTem| SIMulation SYSTem The system time from the setup menu serves as time base. SIMulation The time stamp from the used scenario, e.g. from an OSI message, serves as time base.

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.oseup.clone()
```

Subgroups

6.16.1.12.1 Apply

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OSETup:APPLY
```

class ApplyCls

Apply commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:APPLY
driver.source.areGenerator.oseup.apply.set()
```

Assigns and confirms the settings.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:APPLY
driver.source.areGenerator.oseup.apply.set_with_opc()
```

Assigns and confirms the settings.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.16.1.12.2 Bw

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OSETup:BW
```

class BwCls

Bw commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get_value() → OsetupBw

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:BW
value: enums.OsetupBw = driver.source.areGenerator.osetup.bw.get_value()
```

Sets the bandwidth of the IF output channel frequencies.

return

areg_osetup_bw: BW1G| BW2G| BW5G BW1G Sets the bandwidth to 1 MHz. BW2G
Sets the bandwidth to 2 MHz. BW5G Sets the bandwidth to 5 MHz.

set_value(areg_osetup_bw: OsetupBw) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:BW
driver.source.areGenerator.osetup.bw.set_value(areg_osetup_bw = enums.OsetupBw.
↳ BW1G)
```

Sets the bandwidth of the IF output channel frequencies.

param areg_osetup_bw

BW1G| BW2G| BW5G BW1G Sets the bandwidth to 1 MHz. BW2G Sets the band-
width to 2 MHz. BW5G Sets the bandwidth to 5 MHz.

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.osetup.bw.clone()
```

Subgroups

6.16.1.12.2.1 Apply

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OSETup:BW:APPLY
```

class ApplyCls

Apply commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:BW:APPLY
driver.source.areGenerator.osetup.bw.apply.set()
```

Assigns and confirms the settings.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:BW:APPLY
driver.source.areGenerator.osetup.bw.apply.set_with_opc()
```

Assigns and confirms the settings.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.16.1.12.3 Hil

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OSETup:HIL:UPD
```

class HilCls

Hil commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_upd() → AregHilUpdateMode

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:HIL:UPD
value: enums.AregHilUpdateMode = driver.source.areGenerator.osetup.hil.get_upd()
```

Sets the update mode for the HiL interface. The timestamp is an optional part of the OSI packets.

return

upd_mode: IMMEDIATE|TIMESTAMP IMMEDIATE Updates the simulated objects immediately on arrival of the OSI packet. If there is a timestamp in the OSI packet, the timestamp is not regarded. TIMESTAMP Updates the simulated objects when the system time reaches the timestamp of the OSI packet.

set_upd(upd_mode: AregHilUpdateMode) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:HIL:UPD
driver.source.areGenerator.osetup.hil.set_upd(upd_mode = enums.
↪AregHilUpdateMode.IMMEDIATE)
```

Sets the update mode for the HiL interface. The timestamp is an optional part of the OSI packets.

param upd_mode

IMMEDIATE|TIMESTAMP IMMEDIATE Updates the simulated objects immediately on arrival of the OSI packet. If there is a timestamp in the OSI packet, the timestamp is not regarded. TIMESTAMP Updates the simulated objects when the system time reaches the timestamp of the OSI packet.

6.16.1.12.4 MultiInstrument

SCPI Commands :

```
[SOURCE<HW>]:AREGenerator:OSETup:MULTIinstrument:MODE
[SOURCE<HW>]:AREGenerator:OSETup:MULTIinstrument:PRIMARY
```

class MultiInstrumentCls

MultiInstrument commands group definition. 10 total commands, 3 Subgroups, 2 group commands

get_mode() → AregMultiInstMode

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:MODE
value: enums.AregMultiInstMode = driver.source.areGenerator.oseSetup.
↳ multiInstrument.get_mode()
```

Defines the operation mode of the R&S AREG800A in a multi-instrument setup.

return

mode: PRIMary| OFF| SECondary PRIMary The R&S AREG800A operates as a primary instrument. In this mode, the R&S AREG800A controls several R&S AREG800A instruments. OFF The R&S AREG800A operates in a standalone mode. SECondary Requires a control connection between this R&S AREG800A instrument and a primary R&S AREG800A instrument. The R&S AREG800A operates as a secondary instrument. In this mode, the R&S AREG800A is controlled by a primary R&S AREG800A instrument.

get_primary() → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:PRIMary
value: str = driver.source.areGenerator.oseSetup.multiInstrument.get_primary()
```

No command help available

return

prim_syst_ctrl_add: No help available

set_mode(mode: AregMultiInstMode) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:MODE
driver.source.areGenerator.oseSetup.multiInstrument.set_mode(mode = enums.
↳ AregMultiInstMode.OFF)
```

Defines the operation mode of the R&S AREG800A in a multi-instrument setup.

param mode

PRIMary| OFF| SECondary PRIMary The R&S AREG800A operates as a primary instrument. In this mode, the R&S AREG800A controls several R&S AREG800A instruments. OFF The R&S AREG800A operates in a standalone mode. SECondary Requires a control connection between this R&S AREG800A instrument and a primary R&S AREG800A instrument. The R&S AREG800A operates as a secondary instrument. In this mode, the R&S AREG800A is controlled by a primary R&S AREG800A instrument.

set_primary(prim_syst_ctrl_add: str) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:PRIMary
driver.source.areGenerator.oseSetup.multiInstrument.set_primary(prim_syst_ctrl_
↳ add = 'abc')
```

No command help available

param prim_syst_ctrl_add

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.osetup.multiInstrument.clone()
```

Subgroups

6.16.1.12.4.1 Connect

SCPI Command :

```
[SOURce<HW>]:AREGenerator:OSETup:MULTiinstrument:CONNECT
```

class ConnectCls

Connect commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: [SOURce<HW>]:AREGenerator:OSETup:MULTiinstrument:CONNECT
driver.source.areGenerator.osetup.multiInstrument.connect.set()
```

Triggers connection to all secondary instruments by establishing a control connection via LAN. The R&S AREG800A connects all secondary instruments as configured by their IP address or hostname. See [:SOURce<hw>]:AREGenerator:OSETup:MULTiinstrument:SECondary<st>:HOSTName.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:OSETup:MULTiinstrument:CONNECT
driver.source.areGenerator.osetup.multiInstrument.connect.set_with_opc()
```

Triggers connection to all secondary instruments by establishing a control connection via LAN. The R&S AREG800A connects all secondary instruments as configured by their IP address or hostname. See [:SOURce<hw>]:AREGenerator:OSETup:MULTiinstrument:SECondary<st>:HOSTName.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.16.1.12.4.2 Remove

class RemoveCls

Remove commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.osetup.multiInstrument.remove.clone()
```

Subgroups

6.16.1.12.4.3 Execute

SCPI Command :

```
[SOURce<HW>]:AREGenerator:OSETup:MULTiinstrument:REMove:EXECute
```

class ExecuteCls

Execute commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: [SOURce<HW>]:AREGenerator:OSETup:MULTiinstrument:REMove:EXECute
driver.source.areGenerator.osetup.multiInstrument.remove.execute.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:OSETup:MULTiinstrument:REMove:EXECute
driver.source.areGenerator.osetup.multiInstrument.remove.execute.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.16.1.12.4.4 Secondary

SCPI Commands :

```
[SOURce<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary:HOSTname
[SOURce<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary
```

class SecondaryCls

Secondary commands group definition. 6 total commands, 4 Subgroups, 2 group commands

get_hostname() → str

```
# SCPI: [SOURce<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary:HOSTname
value: str = driver.source.areGenerator.osetup.multiInstrument.secondary.get_
↳hostname()
```


Sets the IP address or hostname of the secondary instrument. If you remove the secondary instrument, the firmware saves hostname of the secondary instrument for correct mapping. For example, if you want to add the secondary instrument again.

```
return
    hostname: string
```

get_value() → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary
value: str = driver.source.areGenerator.oseSetup.multiInstrument.secondary.get_
↳ value()
```

No command help available

```
return
    sec_addr: No help available
```

set_hostname(hostname: str) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary:HOSTname
driver.source.areGenerator.oseSetup.multiInstrument.secondary.set_
↳ hostname(hostname = 'abc')
```

Sets the IP address or hostname of the secondary instrument. If you remove the secondary instrument, the firmware saves hostname of the secondary instrument for correct mapping. For example, if you want to add the secondary instrument again.

```
param hostname
    string
```

set_value(sec_addr: str) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary
driver.source.areGenerator.oseSetup.multiInstrument.secondary.set_value(sec_addr_
↳ = 'abc')
```

No command help available

```
param sec_addr
    No help available
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.oseSetup.multiInstrument.secondary.clone()
```

Subgroups

6.16.1.12.4.5 Add

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary:ADD
```

class AddCls

Add commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary:ADD
driver.source.areGenerator.oseSetup.multiInstrument.secondary.add.set()
```

Adds the configuration of the secondary instrument. Also triggers connecting the primary instrument for control the secondary instrument. You can add previous secondary instruments configurations without specifying the hostname again. The firmware saves hostname of the secondary instrument for correct mapping.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary:ADD
driver.source.areGenerator.oseSetup.multiInstrument.secondary.add.set_with_opc()
```

Adds the configuration of the secondary instrument. Also triggers connecting the primary instrument for control the secondary instrument. You can add previous secondary instruments configurations without specifying the hostname again. The firmware saves hostname of the secondary instrument for correct mapping.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.16.1.12.4.6 Connection

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary:CONNection:[STATE]
```

class ConnectionCls

Connection commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → AregMultiInstCnctStatus

```
# SCPI: [SOURCE<HW>]
↪]:AREGenerator:OSETup:MULTiinstrument:SECondary:CONNection:[STATE]
value: enums.AregMultiInstCnctStatus = driver.source.areGenerator.oseSetup.
↪multiInstrument.secondary.connection.get_state()
```

Queries the connection state of the secondary instrument. If you remove a secondary instrument, the connection state of this secondary instrument is DISConnected.

return
 conn_state: DISConnected| CONNected| TCONnencting| TDISconnecting| CERRor
 DISConnected The secondary instrument is disconnected. DISConnected The secondary instrument is connected. TDISconnecting Triggers disconnecting the secondary instrument. CERRor Connection error.

6.16.1.12.4.7 Execute

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary:EXECute
```

class ExecuteCls

Execute commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary:EXECute
driver.source.areGenerator.osecup.multiInstrument.secondary.execute.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary:EXECute
driver.source.areGenerator.osecup.multiInstrument.secondary.execute.set_with_
    ↪opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms
 Maximum time to wait in milliseconds, valid only for this call.

6.16.1.12.4.8 Remove

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary:REMOve
```

class RemoveCls

Remove commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary:REMOve
driver.source.areGenerator.osecup.multiInstrument.secondary.remove.set()
```

Removes the secondary instrument from connected R&S AREG800A instruments that are listed in the primary instrument. Also, this command terminates the control connection between primary instrument and the secondary instrument. The firmware saves hostname of the secondary instrument for correct mapping. For example, if you want to add the secondary instrument again.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSetUp:MULTIinstrument:SECondary:REMove
driver.source.areGenerator.oseSetup.multiInstrument.secondary.remove.set_with_
    ↪opc()
```

Removes the secondary instrument from connected R&S AREG800A instruments that are listed in the primary instrument. Also, this command terminates the control connection between primary instrument and the secondary instrument. The firmware saves hostname of the secondary instrument for correct mapping. For example, if you want to add the secondary instrument again.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.16.1.12.5 Swunit

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OSetUp:SWUNit:[STaTe]
```

class SwunitCls

Swunit commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSetUp:SWUNit:[STaTe]
value: bool = driver.source.areGenerator.oseSetup.swunit.get_state()
```

Activates using a switching unit in the test setup, e.g. R&S OSP open switch and control platform. A switching unit in the test setup allows you to connect up to eight QAT channels to less than eight R&S AREG800A IF ports.

return

areg_oseSetup_sw_unit: 1| ON| 0| OFF

set_state(areg_oseSetup_sw_unit: bool) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSetUp:SWUNit:[STaTe]
driver.source.areGenerator.oseSetup.swunit.set_state(areg_oseSetup_sw_unit = False)
```

Activates using a switching unit in the test setup, e.g. R&S OSP open switch and control platform. A switching unit in the test setup allows you to connect up to eight QAT channels to less than eight R&S AREG800A IF ports.

param areg_oseSetup_sw_unit

1| ON| 0| OFF

6.16.1.13 Radar

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:RADar:LSensitivity
```

class RadarCls

Radar commands group definition. 3 total commands, 2 Subgroups, 1 group commands

get_lsensitivity() → bool

```
# SCPI: [SOURCE<HW>]:AREGenerator:RADar:LSensitivity
value: bool = driver.source.areGenerator.radar.get_lsensitivity()
```

Defines if low sensitivity is used or not.

```
return
    areg_radar_low_sen: 1| ON| 0| OFF
```

set_lsensitivity(areg_radar_low_sen: bool) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:RADar:LSensitivity
driver.source.areGenerator.radar.set_lsensitivity(areg_radar_low_sen = False)
```

Defines if low sensitivity is used or not.

```
param areg_radar_low_sen
    1| ON| 0| OFF
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.radar.clone()
```

Subgroups

6.16.1.13.1 Base

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:RADar:BASE:ATTenuation
```

class BaseCls

Base commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_attenuation() → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:RADar:BASE:ATTenuation
value: int = driver.source.areGenerator.radar.base.get_attenuation()
```

No command help available

```

    return
    areg_base_att: No help available
set_attenuation(areg_base_att: int) → None

```

```

# SCPI: [SOURCE<HW>]:AREGenerator:RADar:BASE:ATTenuation
driver.source.areGenerator.radar.base.set_attenuation(areg_base_att = 1)

```

No command help available

```

param areg_base_att
    No help available

```

6.16.1.13.2 Power

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:RADar:POWER:INDicator
```

class PowerCls

Power commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_indicator() → AregRadarPowIndicator

```

# SCPI: [SOURCE<HW>]:AREGenerator:RADar:POWER:INDicator
value: enums.AregRadarPowIndicator = driver.source.areGenerator.radar.power.get_
↪indicator()

```

The radar power indicator is a summary indicator for all radar object powers.

```

return
    pow_indicator: OFF| GOOD| WEAK| BAD OFF No or very weak RX power is de-
    tected. GOOD The RX power is in linear range. WEAK The RX power is strong,
    non-linear effects can occur. BAD The RX power is in a range, where the receiver is
    in saturation.

```

6.16.1.14 Scenario

SCPI Commands :

```

[SOURCE<HW>]:AREGenerator:SCENario:PROGress
[SOURCE<HW>]:AREGenerator:SCENario:RESet
[SOURCE<HW>]:AREGenerator:SCENario:STARt
[SOURCE<HW>]:AREGenerator:SCENario:STATus
[SOURCE<HW>]:AREGenerator:SCENario:STOP

```

class ScenarioCls

Scenario commands group definition. 12 total commands, 4 Subgroups, 5 group commands

get_progress() → float

```

# SCPI: [SOURCE<HW>]:AREGenerator:SCENario:PROGress
value: float = driver.source.areGenerator.scenario.get_progress()

```

Queries the current position in time while playing the file. Query the current position via
[:SOURCE<hw>]:AREGenerator:SCENario:PROGress?.

return
scenario_progres: float Range: 0 to 100

get_status() → ScenarioStatus

```
# SCPI: [SOURCE<HW>]:AREGenerator:SCENario:STATUS
value: enums.ScenarioStatus = driver.source.areGenerator.scenario.get_status()
```

Queries the status of the played scenario file.

return
scenario_status: RUNNing| STOPped RUNNing The replay of the scenario is ongoing.
STOPped The replay of the scenario is stopped.

reset() → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SCENario:RESet
driver.source.areGenerator.scenario.reset()
```

Resets the Start, Stop and Position parameters of the replayed scenario.

reset_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SCENario:RESet
driver.source.areGenerator.scenario.reset_with_opc()
```

Resets the Start, Stop and Position parameters of the replayed scenario.

Same as reset, but waits for the operation to complete before continuing further. Use the
RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms
Maximum time to wait in milliseconds, valid only for this call.

set_progress(scenario_progres: float) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SCENario:PROGress
driver.source.areGenerator.scenario.set_progress(scenario_progres = 1.0)
```

Queries the current position in time while playing the file. Query the current position via
[:SOURCE<hw>]:AREGenerator:SCENario:PROGress?.

param scenario_progres
float Range: 0 to 100

set_status(scenario_status: ScenarioStatus) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SCENario:STATUS
driver.source.areGenerator.scenario.set_status(scenario_status = enums.
↳ ScenarioStatus.RUNNing)
```

Queries the status of the played scenario file.

param scenario_status
RUNNing| STOPped RUNNing The replay of the scenario is ongoing. STOPped The
replay of the scenario is stopped.

start() → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SCENario:START
driver.source.areGenerator.scenario.start()
```

Starts the player. Plays the scenario file from the beginning.

start_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SCENario:START
driver.source.areGenerator.scenario.start_with_opc()
```

Starts the player. Plays the scenario file from the beginning.

Same as start, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

stop() → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SCENario:STOP
driver.source.areGenerator.scenario.stop()
```

Stops the player. After stopping, you can resume playing by [:SOURCE<hw>]:AREGenerator:SCENario:START. The file plays from the start position.

stop_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SCENario:STOP
driver.source.areGenerator.scenario.stop_with_opc()
```

Stops the player. After stopping, you can resume playing by [:SOURCE<hw>]:AREGenerator:SCENario:START. The file plays from the start position.

Same as stop, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.scenario.clone()
```


Subgroups

6.16.1.14.1 File

SCPI Commands :

```
[SOURCE<HW>]:AREGenerator:SCENario:FILE:CATalog
[SOURCE<HW>]:AREGenerator:SCENario:FILE
```

class FileCls

File commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_catalog() → List[str]

```
# SCPI: [SOURCE<HW>]:AREGenerator:SCENario:FILE:CATalog
value: List[str] = driver.source.areGenerator.scenario.file.get_catalog()
```

Queries the available scenario files. Lists all *.osi and *.sm files available in the default directory /var/user/.

```
return
    areg_scenario_file_cat: No help available
```

get_value() → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:SCENario:FILE
value: str = driver.source.areGenerator.scenario.file.get_value()
```

Selects an existing scenario file from the default directory or from a specific directory.

```
return
    scenario_file: string
```

set_value(scenario_file: str) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SCENario:FILE
driver.source.areGenerator.scenario.file.set_value(scenario_file = 'abc')
```

Selects an existing scenario file from the default directory or from a specific directory.

```
param scenario_file
    string
```

6.16.1.14.2 Pause

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:SCENario:PAUSE
```

class PauseCls

Pause commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SCENario:PAUSE
driver.source.areGenerator.scenario.pause.set()
```

Pauses the player. After pausing, you can resume playing by
[:SOURCE<hw>]:AREGenerator:SCENario:START.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SCENario:PAUSE
driver.source.areGenerator.scenario.pause.set_with_opc()
```

Pauses the player. After pausing, you can resume playing by
[:SOURCE<hw>]:AREGenerator:SCENario:START.

Same as set, but waits for the operation to complete before continuing further. Use the
RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.16.1.14.3 Position

SCPI Commands :

```
[SOURCE<HW>]:AREGenerator:SCENario:POSition:ACTual
[SOURCE<HW>]:AREGenerator:SCENario:POSition:START
[SOURCE<HW>]:AREGenerator:SCENario:POSition:STOP
```

class PositionCls

Position commands group definition. 3 total commands, 0 Subgroups, 3 group commands

get_actual() → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:SCENario:POSition:ACTual
value: int = driver.source.areGenerator.scenario.position.get_actual()
```

Queries the current play position in the file.

return

scen_act_pos: integer Range: 0 to 1E9

get_start() → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:SCENario:POSition:START
value: int = driver.source.areGenerator.scenario.position.get_start()
```

Sets the start position in the scenario file. Data which chronologically precedes the start position is not replayed by the player. The entered time stamp must chronologically always precede the defined
[:SOURCE<hw>]:AREGenerator:SCENario:POSition:STOP time stamp.

return

scen_start_pos: integer Range: 0 to 1E9

get_stop() → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:SCENario:POSition:STOP
value: int = driver.source.areGenerator.scenario.position.get_stop()
```

Sets the end position in the file. Data which chronologically follows the end position is not replayed by the player. When the player reaches the Stop position, it returns to the Start position ([:SOURCE<hw>]:AREGenerator:SCENario:REPLay:LOOP) . The time stamp must chronologically always follow the defined [:SOURCE<hw>]:AREGenerator:SCENario:STARt time stamp.

```
return
    scen_stop_pos: integer Range: 0 to 1E9
```

```
set_start(scen_start_pos: int) → None
```

```
# SCPI: [:SOURCE<HW>]:AREGenerator:SCENario:POSition:STARt
driver.source.areGenerator.scenario.position.set_start(scen_start_pos = 1)
```

Sets the start position in the scenario file. Data which chronologically precedes the start position is not replayed by the player. The entered time stamp must chronologically always precede the defined [:SOURCE<hw>]:AREGenerator:SCENario:POSition:STOP time stamp.

```
param scen_start_pos
    integer Range: 0 to 1E9
```

```
set_stop(scen_stop_pos: int) → None
```

```
# SCPI: [:SOURCE<HW>]:AREGenerator:SCENario:POSition:STOP
driver.source.areGenerator.scenario.position.set_stop(scen_stop_pos = 1)
```

Sets the end position in the file. Data which chronologically follows the end position is not replayed by the player. When the player reaches the Stop position, it returns to the Start position ([:SOURCE<hw>]:AREGenerator:SCENario:REPLay:LOOP) . The time stamp must chronologically always follow the defined [:SOURCE<hw>]:AREGenerator:SCENario:STARt time stamp.

```
param scen_stop_pos
    integer Range: 0 to 1E9
```

6.16.1.14.4 Replay

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:SCENario:REPLay:[MODE]
```

class ReplayCls

Replay commands group definition. 1 total commands, 0 Subgroups, 1 group commands

```
get_mode() → ScenarioReplyMode
```

```
# SCPI: [:SOURCE<HW>]:AREGenerator:SCENario:REPLay:[MODE]
value: enums.ScenarioReplyMode = driver.source.areGenerator.scenario.replay.get_
↪mode()
```

Defines, if the files are played once or continuously. Files are replayed within the defined start position and stop position.

```
return
    scen_reply_mode: SINGLE| LOOP SINGLE Files are played once within the defined
    positions in the file. LOOP Files are played continuously within the defined positions
    in the file.
```

set_mode(scen_reply_mode: ScenarioReplyMode) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SCENario:REPlay:[MODE]
driver.source.areGenerator.scenario.replay.set_mode(scen_reply_mode = enums.
↳ ScenarioReplyMode.LOOP)
```

Defines, if the files are played once or continuously. Files are replayed within the defined start position and stop position.

param scen_reply_mode

SINGLE| LOOP SINGLE Files are played once within the defined positions in the file.

LOOP Files are played continuously within the defined positions in the file.

6.16.1.15 Sensor<Sensor>

RepCap Settings

```
# Range: Nr1 .. Nr8
rc = driver.source.areGenerator.sensor.repcap_sensor_get()
driver.source.areGenerator.sensor.repcap_sensor_set(repcap.Sensor.Nr1)
```

class SensorCls

Sensor commands group definition. 11 total commands, 11 Subgroups, 0 group commands Repeated Capability: Sensor, default value after init: Sensor.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.sensor.clone()
```

Subgroups

6.16.1.15.1 Add

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:SENSor<CH>:ADD
```

class AddCls

Add commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(sensor=Sensor.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SENSor<CH>:ADD
driver.source.areGenerator.sensor.add.set(sensor = repcap.Sensor.Default)
```

Adds a configuration for a connected sensor. A line with contiguous numeration is added.

param sensor

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sensor')

set_with_opc(*sensor=Sensor.Default, opc_timeout_ms: int = -1*) → None

6.16.1.15.2 Alias

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:SENSOR<CH>:ALIAS
```

class AliasCls

Alias commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*sensor=Sensor.Default*) → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:SENSOR<CH>:ALIAS
value: str = driver.source.areGenerator.sensor.alias.get(sensor = repcap.Sensor.
↳Default)
```

Sets the alias of the radar sensor.

param sensor

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sensor')

return

areg_sens_alias: string

set(*areg_sens_alias: str, sensor=Sensor.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SENSOR<CH>:ALIAS
driver.source.areGenerator.sensor.alias.set(areg_sens_alias = 'abc', sensor =
↳repcap.Sensor.Default)
```

Sets the alias of the radar sensor.

param areg_sens_alias

string

param sensor

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sensor')

6.16.1.15.3 Angle

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:SENSOR<CH>:ANGLE
```

class AngleCls

Angle commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*sensor=Sensor.Default*) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:SENSOR<CH>:ANGLE
value: int = driver.source.areGenerator.sensor.angle.get(sensor = repcap.Sensor.
↳Default)
```

Sets the relative angle between radar sensor and origin.

param sensor

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Sensor’)

return

areg_sens_sto_angle: integer Range: -180 to 180

set(areg_sens_sto_angle: int, sensor=Sensor.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SENSOR<CH>:ANGLE
driver.source.areGenerator.sensor.angle.set(areg_sens_sto_angle = 1, sensor =
↳repcap.Sensor.Default)
```

Sets the relative angle between radar sensor and origin.

param areg_sens_sto_angle

integer Range: -180 to 180

param sensor

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Sensor’)

6.16.1.15.4 Bw

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:SENSOR<CH>:BW
```

class BwCls

Bw commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(sensor=Sensor.Default) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:SENSOR<CH>:BW
value: int = driver.source.areGenerator.sensor.bw.get(sensor = repcap.Sensor.
↳Default)
```

Sets the bandwidth for the radar sensor. Set it according to the bandwidth of the radar sensor included in the test setup.

param sensor

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Sensor’)

return

areg_sens_bw: integer Range: 0 to 10E9

set(areg_sens_bw: int, sensor=Sensor.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SENSOR<CH>:BW
driver.source.areGenerator.sensor.bw.set(areg_sens_bw = 1, sensor = repcap.
↳Sensor.Default)
```

Sets the bandwidth for the radar sensor. Set it according to the bandwidth of the radar sensor included in the test setup.

param areg_sens_bw
integer Range: 0 to 10E9

param sensor
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sensor')

6.16.1.15.5 Center

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:SENSOR<CH>:CENTER
```

class CenterCls

Center commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(sensor=Sensor.Default) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:SENSOR<CH>:CENTER
value: int = driver.source.areGenerator.sensor.center.get(sensor = repcap.
↳Sensor.Default)
```

Sets the center frequency for the radar sensor. Set it according to the center frequency of the radar sensor included in the test setup.

param sensor
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sensor')

return
areg_sens_cent_fre: integer Range: depends on settings to depends on settings

set(areg_sens_cent_fre: int, sensor=Sensor.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SENSOR<CH>:CENTER
driver.source.areGenerator.sensor.center.set(areg_sens_cent_fre = 1, sensor =
↳repcap.Sensor.Default)
```

Sets the center frequency for the radar sensor. Set it according to the center frequency of the radar sensor included in the test setup.

param areg_sens_cent_fre
integer Range: depends on settings to depends on settings

param sensor
optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sensor')

6.16.1.15.6 Cfactor

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:SENSOR<CH>:CFACtor
```

class CfactorCls

Cfactor commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*sensor=Sensor.Default*) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:SENSOR<CH>:CFACtor
value: float = driver.source.areGenerator.sensor.cfactor.get(sensor = repcap.
↳ Sensor.Default)
```

Sets the crest factor for the signal.

param sensor

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sensor')

return

areg_sens_crest_fa: float Range: 0 to 100

set(*areg_sens_crest_fa: float, sensor=Sensor.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SENSOR<CH>:CFACtor
driver.source.areGenerator.sensor.cfactor.set(areg_sens_crest_fa = 1.0, sensor.
↳ repcap.Sensor.Default)
```

Sets the crest factor for the signal.

param areg_sens_crest_fa

float Range: 0 to 100

param sensor

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sensor')

6.16.1.15.7 Count

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:SENSOR<CH>:COUNT
```

class CountCls

Count commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*sensor=Sensor.Default*) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:SENSOR<CH>:COUNT
value: int = driver.source.areGenerator.sensor.count.get(sensor = repcap.Sensor.
↳ Default)
```

Queries the number of radar sensors in the test setup.

param sensor

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Sensor’)

return

areg_sensor_count: integer Range: 0 to 8

6.16.1.15.8 Distance**SCPI Command :**

```
[SOURCE<HW>]:AREGenerator:SENSOR<CH>:DISTance
```

class DistanceCls

Distance commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(sensor=Sensor.Default) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:SENSOR<CH>:DISTance
value: int = driver.source.areGenerator.sensor.distance.get(sensor = repcap.
↳ Sensor.Default)
```

Sets the relative distance between radar sensor and origin.

param sensor

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Sensor’)

return

areg_sens_sto_distance: integer Range: 0 to 30

set(areg_sens_sto_distance: int, sensor=Sensor.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SENSOR<CH>:DISTance
driver.source.areGenerator.sensor.distance.set(areg_sens_sto_distance = 1,
↳ sensor = repcap.Sensor.Default)
```

Sets the relative distance between radar sensor and origin.

param areg_sens_sto_distance

integer Range: 0 to 30

param sensor

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Sensor’)

6.16.1.15.9 Dynamic

class DynamicCls

Dynamic commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.sensor.dynamic.clone()
```

Subgroups

6.16.1.15.9.1 Id

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:SENSOR<CH>:DYNAMIC:ID
```

class IdCls

Id commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(sensor=Sensor.Default) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:SENSOR<CH>:DYNAMIC:ID
value: int = driver.source.areGenerator.sensor.dynamic.id.get(sensor = repcap.
↳ Sensor.Default)
```

Requires: [:SOURCE<hw>]:AREGenerator:OSETup:REference MAPPed. Sets the ID of the radar sensor according to the definition in the used protocol, e.g. in a ZMQ OSI HiL protocol. The mapping is defined in the object list of the used protocol, e.g. the ‘sensor_id’ field in the osi3::sensorData struct for all OSI protocols.

param sensor

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Sensor’)

return

areg_sconf_dyn_id: integer Range: 0 to 1000

set(areg_sconf_dyn_id: int, sensor=Sensor.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SENSOR<CH>:DYNAMIC:ID
driver.source.areGenerator.sensor.dynamic.id.set(areg_sconf_dyn_id = 1, sensor_
↳ = repcap.Sensor.Default)
```

Requires: [:SOURCE<hw>]:AREGenerator:OSETup:REference MAPPed. Sets the ID of the radar sensor according to the definition in the used protocol, e.g. in a ZMQ OSI HiL protocol. The mapping is defined in the object list of the used protocol, e.g. the ‘sensor_id’ field in the osi3::sensorData struct for all OSI protocols.

param areg_sconf_dyn_id

integer Range: 0 to 1000

param sensor

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Sensor’)

6.16.1.15.10 Id**SCPI Command :**

```
[SOURCE<HW>]:AREGenerator:SENSOR<CH>:ID
```

class IdCls

Id commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*sensor=Sensor.Default*) → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:SENSOR<CH>:ID
value: int = driver.source.areGenerator.sensor.id.get(sensor = repcap.Sensor.
↳Default)
```

Queries the identification name of the radar sensor.

param sensor

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Sensor’)

return

areg_sens_id: integer Range: 0 to 1000

6.16.1.15.11 Rmv**SCPI Command :**

```
[SOURCE<HW>]:AREGenerator:SENSOR<CH>:RMV
```

class RmvCls

Rmv commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(*sensor=Sensor.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SENSOR<CH>:RMV
driver.source.areGenerator.sensor.rmv.set(sensor = repcap.Sensor.Default)
```

Removes the configuration of the radar sensor from the list.

param sensor

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Sensor’)

set_with_opc(*sensor=Sensor.Default, opc_timeout_ms: int = -1*) → None

6.16.1.16 Swunit

SCPI Commands :

```
[SOURCE<HW>]:AREGenerator:SWUNit:HOSTName
[SOURCE<HW>]:AREGenerator:SWUNit:RX
[SOURCE<HW>]:AREGenerator:SWUNit:STATUS
[SOURCE<HW>]:AREGenerator:SWUNit:TX
```

class SwunitCls

Swunit commands group definition. 16 total commands, 5 Subgroups, 4 group commands

get_hostname() → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUNit:HOSTName
value: str = driver.source.areGenerator.swunit.get_hostname()
```

Sets the IP address or hostname of the connected switching unit in the test setup.

```
return
    areg_swunit_host: string
```

get_rx() → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUNit:RX
value: str = driver.source.areGenerator.swunit.get_rx()
```

Requires [:SOURCE<hw>]:AREGenerator:OSETup:SWUNit[:STATe] 1. Selects the switching unit connector (relay) of the switching unit connected to the RX channel of the R&S AREG800A. Enter the name of the relay of the switching unit to connect to the RX channel.

```
return
    areg_swunit_rx_ch: string
```

get_status() → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUNit:STATUS
value: str = driver.source.areGenerator.swunit.get_status()
```

Queries the status of the switching unit. Displays if the switching unit is connected or disconnected.

```
return
    areg_sw_unit_status: string
```

get_tx() → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUNit:TX
value: str = driver.source.areGenerator.swunit.get_tx()
```

Requires [:SOURCE<hw>]:AREGenerator:OSETup:SWUNit[:STATe] 1. Selects the switching unit connector (relay) of the switching unit connected to the TX channel of the R&S AREG800A. Enter the name of the relay of the switching unit to connect to the TX channel.

```
return
    areg_swunit_tx_ch: string
```

set_hostname(*areg_swunit_host: str*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUnit:HOSTName
driver.source.areGenerator.swunit.set_hostname(areg_swunit_host = 'abc')
```

Sets the IP address or hostname of the connected switching unit in the test setup.

param areg_swunit_host
string

set_rx(*areg_swunit_rx_ch: str*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUnit:RX
driver.source.areGenerator.swunit.set_rx(areg_swunit_rx_ch = 'abc')
```

Requires [:SOURCE<hw>]:AREGenerator:OSETup:SWUnit[:STATE] 1. Selects the switching unit connector (relay) of the switching unit connected to the RX channel of the R&S AREG800A. Enter the name of the relay of the switching unit to connect to the RX channel.

param areg_swunit_rx_ch
string

set_tx(*areg_swunit_tx_ch: str*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUnit:TX
driver.source.areGenerator.swunit.set_tx(areg_swunit_tx_ch = 'abc')
```

Requires [:SOURCE<hw>]:AREGenerator:OSETup:SWUnit[:STATE] 1. Selects the switching unit connector (relay) of the switching unit connected to the TX channel of the R&S AREG800A. Enter the name of the relay of the switching unit to connect to the TX channel.

param areg_swunit_tx_ch
string

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.swunit.clone()
```

Subgroups

6.16.1.16.1 CableCorr

class CableCorrCls

CableCorr commands group definition. 8 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.swunit.cableCorr.clone()
```

Subgroups

6.16.1.16.1.1 Connector<Connector>

RepCap Settings

```
# Range: Nr1 .. Nr8
rc = driver.source.areGenerator.swunit.cableCorr.connector.repcap_connector_get()
driver.source.areGenerator.swunit.cableCorr.connector.repcap_connector_set(repcap.
↳Connector.Nr1)
```

class ConnectorCls

Connector commands group definition. 8 total commands, 2 Subgroups, 0 group commands Repeated Capability: Connector, default value after init: Connector.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.swunit.cableCorr.connector.clone()
```

Subgroups

6.16.1.16.1.2 Rx<RxIndex>

RepCap Settings

```
# Range: Nr1 .. Nr16
rc = driver.source.areGenerator.swunit.cableCorr.connector.rx.repcap_rxIndex_get()
driver.source.areGenerator.swunit.cableCorr.connector.rx.repcap_rxIndex_set(repcap.
↳RxIndex.Nr1)
```

class RxCls

Rx commands group definition. 4 total commands, 2 Subgroups, 0 group commands Repeated Capability: RxIndex, default value after init: RxIndex.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.swunit.cableCorr.connector.rx.clone()
```

Subgroups

6.16.1.16.1.3 Mode

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:SWUnit:CABLeCorr:CONNector<DI>:RX<ST>:MODE
```

class ModeCls

Mode commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(connector=Connector.Default, rxIndex=RxIndex.Default) → AregCableCorrSour

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUnit:CABLeCorr:CONNector<DI>:RX<ST>:MODE
value: enums.AregCableCorrSour = driver.source.areGenerator.swunit.cableCorr.
↪ connector.rx.mode.get(connector = repcap.Connector.Default, rxIndex = repcap.
↪ RxIndex.Default)
```

Selects the source for cable correction data.

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

areg_cabel_cor_mod: USER| S2P| FACTory USER Selects user-defined cable correction data, i.e. fixed values for delay and attenuation. S2P Selects cable correction data from a file with file extension *.s2p. FACTory For TRX-type frontends only. Selects cable correction data for the TRX frontend from factory specification.

set(areg_cabel_cor_mod: AregCableCorrSour, connector=Connector.Default, rxIndex=RxIndex.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUnit:CABLeCorr:CONNector<DI>:RX<ST>:MODE
driver.source.areGenerator.swunit.cableCorr.connector.rx.mode.set(areg_cabel_
↪ cor_mod = enums.AregCableCorrSour.FACTory, connector = repcap.Connector.
↪ Default, rxIndex = repcap.RxIndex.Default)
```

Selects the source for cable correction data.

param areg_cabel_cor_mod

USER| S2P| FACTory USER Selects user-defined cable correction data, i.e. fixed values for delay and attenuation. S2P Selects cable correction data from a file with file extension *.s2p. FACTory For TRX-type frontends only. Selects cable correction data for the TRX frontend from factory specification.

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

6.16.1.16.1.4 User**class UserCls**

User commands group definition. 3 total commands, 3 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.swunit.cableCorr.connector.rx.user.clone()
```

Subgroups**6.16.1.16.1.5 Attenuation****SCPI Command :**

```
[SOURce<HW>]:AREGenerator:SWUNit:CABLeCorr:CONNector<DI>:RX<ST>:USER:ATTenuation
```

class AttenuationCls

Attenuation commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(connector=Connector.Default, rxIndex=RxIndex.Default) → float

```
# SCPI: [SOURce<HW>]:AREGenerator:SWUNit:CABLeCorr:CONNector<DI>:RX<ST>
↳:USER:ATTenuation
value: float = driver.source.areGenerator.swunit.cableCorr.connector.rx.user.
↳attenuation.get(connector = repcap.Connector.Default, rxIndex = repcap.
↳RxIndex.Default)
```

Requires [:SOURce<hw>]:AREGenerator:SWUNit:CABLeCorr:CONNector<di>:RX|TX:MODE USER or [:SOURce<hw>]:AREGenerator:SWUNit:CABLeCorr:CONNector<di>:RX|TX:MODE S2P. Sets a user-defined attenuation value.

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

areg_cable_corr_at: float Range: -50 to 50

set(*areg_cable_corr_at*: float, *connector*=Connector.Default, *rxIndex*=RxIndex.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUNit:CABLe corr:CONNe ct or<DI>:RX<ST>
↳:USER:ATTenuation
driver.source.areGenerator.swunit.cableCorr.connector.rx.user.attenuation.
↳set(areg_cable_corr_at = 1.0, connector = repcap.Connector.Default, rxIndex =
↳repcap.RxIndex.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:SWUNit:CABLe corr:CONNe ct or<di>:RX|TX:MODE USER or [:SOURCE<hw>]:AREGenerator:SWUNit:CABLe corr:CONNe ct or<di>:RX|TX:MODE S2P. Sets a user-defined attenuation value.

param areg_cable_corr_at

float Range: -50 to 50

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

6.16.1.16.1.6 Delay

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:SWUNit:CABLe corr:CONNe ct or<DI>:RX<ST>:USER:DELay
```

class DelayCls

Delay commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*connector*=Connector.Default, *rxIndex*=RxIndex.Default) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUNit:CABLe corr:CONNe ct or<DI>:RX<ST>
↳:USER:DELay
value: float = driver.source.areGenerator.swunit.cableCorr.connector.rx.user.
↳delay.get(connector = repcap.Connector.Default, rxIndex = repcap.RxIndex.
↳Default)
```

Requires [:SOURCE<hw>]:AREGenerator:SWUNit:CABLe corr:CONNe ct or<di>:RX|TX:MODE USER. Sets a user-defined delay value.

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

areg_cable_cor_del: float Range: 0 to 50

set(*areg_cable_cor_del*: float, *connector*=Connector.Default, *rxIndex*=RxIndex.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUNit:CABLEcorr:CONNECTor<DI>:RX<ST>
↳:USER:DElay
driver.source.areGenerator.swunit.cableCorr.connector.rx.user.delay.set(areg_
↳cable_cor_del = 1.0, connector = repcap.Connector.Default, rxIndex = repcap.
↳RxIndex.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:SWUNit:CABLEcorr:CONNECTor<di>:RX|TX:MODE USER.
Sets a user-defined delay value.

param areg_cable_cor_del

float Range: 0 to 50

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

6.16.1.16.1.7 File

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:SWUNit:CABLEcorr:CONNECTor<DI>:RX<ST>:USER:FILE
```

class FileCls

File commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(connector=Connector.Default, rxIndex=RxIndex.Default) → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUNit:CABLEcorr:CONNECTor<DI>:RX<ST>
↳:USER:FILE
value: str = driver.source.areGenerator.swunit.cableCorr.connector.rx.user.file.
↳get(connector = repcap.Connector.Default, rxIndex = repcap.RxIndex.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:SWUNit:CABLEcorr:CONNECTor<di>:RX|TX:MODE S2P.
Loads a cable correction data file with file extension *.s2p from the default or the specified directory.

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

return

areg_cable_cor_fil: string

set(areg_cable_cor_fil: str, connector=Connector.Default, rxIndex=RxIndex.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUNit:CABLEcorr:CONNECTor<DI>:RX<ST>
↳:USER:FILE
driver.source.areGenerator.swunit.cableCorr.connector.rx.user.file.set(areg_
↳cable_cor_fil = 'abc', connector = repcap.Connector.Default, rxIndex = repcap.
↳RxIndex.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:SWUnit:CABLEcorr:CONNECTor<di>:RX|TX:MODE S2P.
Loads a cable correction data file with file extension *.s2p from the default or the specified directory.

param areg_cable_cor_fil

string

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param rxIndex

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Rx')

6.16.1.16.1.8 Tx<TxIndexNull>

RepCap Settings

```
# Range: Nr0 .. Nr15
rc = driver.source.areGenerator.swunit.cableCorr.connector.tx.repcap_txIndexNull_get()
driver.source.areGenerator.swunit.cableCorr.connector.tx.repcap_txIndexNull_set(repcap.
↳TxIndexNull.Nr0)
```

class TxCls

Tx commands group definition. 4 total commands, 2 Subgroups, 0 group commands Repeated Capability: TxIndexNull, default value after init: TxIndexNull.Nr0

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.swunit.cableCorr.connector.tx.clone()
```

Subgroups

6.16.1.16.1.9 Mode

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:SWUnit:CABLEcorr:CONNECTor<DI>:TX<ST0>:MODE
```

class ModeCls

Mode commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(connector=Connector.Default, txIndexNull=TxIndexNull.Default) → AregCableCorrSour

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUnit:CABLEcorr:CONNECTor<DI>:TX<ST0>:MODE
value: enums.AregCableCorrSour = driver.source.areGenerator.swunit.cableCorr.
↳connector.tx.mode.get(connector = repcap.Connector.Default, txIndexNull =
↳repcap.TxIndexNull.Default)
```

Selects the source for cable correction data.

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

areg_cabel_cor_mod: USER| S2P| FACTory USER Selects user-defined cable correction data, i.e. fixed values for delay and attenuation. S2P Selects cable correction data from a file with file extension *.s2p. FACTory For TRX-type frontends only. Selects cable correction data for the TRX frontend from factory specification.

set(areg_cabel_cor_mod: AregCableCorrSour, connector=Connector.Default, txIndexNull=TxIndexNull.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUnit:CABLeCorr:CONNeCtor<DI>:TX<ST0>:MODE
driver.source.areGenerator.swunit.cableCorr.connector.tx.mode.set(areg_cabel_
cor_mod = enums.AregCableCorrSour.FACTory, connector = repcap.Connector.
Default, txIndexNull = repcap.TxIndexNull.Default)
```

Selects the source for cable correction data.

param areg_cabel_cor_mod

USER| S2P| FACTory USER Selects user-defined cable correction data, i.e. fixed values for delay and attenuation. S2P Selects cable correction data from a file with file extension *.s2p. FACTory For TRX-type frontends only. Selects cable correction data for the TRX frontend from factory specification.

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

6.16.1.16.1.10 User**class UserCls**

User commands group definition. 3 total commands, 3 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.swunit.cableCorr.connector.tx.user.clone()
```

Subgroups

6.16.1.16.1.11 Attenuation

SCPI Command :

```
[SOURce<HW>]:AREGenerator:SWUNit:CABLe corr:CONNector<DI>:TX<ST0>:USER:ATTenuation
```

class AttenuationCls

Attenuation commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(connector=Connector.Default, txIndexNull=TxIndexNull.Default) → float

```
# SCPI: [SOURce<HW>]:AREGenerator:SWUNit:CABLe corr:CONNector<DI>:TX<ST0>
↳:USER:ATTenuation
value: float = driver.source.areGenerator.swunit.cableCorr.connector.tx.user.
↳attenuation.get(connector = repcap.Connector.Default, txIndexNull = repcap.
↳TxIndexNull.Default)
```

Requires [:SOURce<hw>]:AREGenerator:SWUNit:CABLe corr:CONNector<di>:RX|TX:MODE USER or [:SOURce<hw>]:AREGenerator:SWUNit:CABLe corr:CONNector<di>:RX|TX:MODE S2P. Sets a user-defined attenuation value.

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

areg_cable_corr_at: float Range: -50 to 50

set(areg_cable_corr_at: float, connector=Connector.Default, txIndexNull=TxIndexNull.Default) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:SWUNit:CABLe corr:CONNector<DI>:TX<ST0>
↳:USER:ATTenuation
driver.source.areGenerator.swunit.cableCorr.connector.tx.user.attenuation.
↳set(areg_cable_corr_at = 1.0, connector = repcap.Connector.Default,
↳txIndexNull = repcap.TxIndexNull.Default)
```

Requires [:SOURce<hw>]:AREGenerator:SWUNit:CABLe corr:CONNector<di>:RX|TX:MODE USER or [:SOURce<hw>]:AREGenerator:SWUNit:CABLe corr:CONNector<di>:RX|TX:MODE S2P. Sets a user-defined attenuation value.

param areg_cable_corr_at

float Range: -50 to 50

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

6.16.1.16.1.12 Delay

SCPI Command :

```
[SOURce<HW>]:AREGenerator:SWUNit:CABLeCorr:CONNector<DI>:TX<ST0>:USER:DElay
```

class DelayCls

Delay commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(connector=Connector.Default, txIndexNull=TxIndexNull.Default) → float

```
# SCPI: [SOURce<HW>]:AREGenerator:SWUNit:CABLeCorr:CONNector<DI>:TX<ST0>
↳:USER:DElay
value: float = driver.source.areGenerator.swunit.cableCorr.connector.tx.user.
↳delay.get(connector = repcap.Connector.Default, txIndexNull = repcap.
↳TxIndexNull.Default)
```

Requires [:SOURce<hw>]:AREGenerator:SWUNit:CABLeCorr:CONNector<di>:RX|TX:MODE USER.
Sets a user-defined delay value.

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

areg_cable_cor_del: float Range: 0 to 50

set(areg_cable_cor_del: float, connector=Connector.Default, txIndexNull=TxIndexNull.Default) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:SWUNit:CABLeCorr:CONNector<DI>:TX<ST0>
↳:USER:DElay
driver.source.areGenerator.swunit.cableCorr.connector.tx.user.delay.set(areg_
↳cable_cor_del = 1.0, connector = repcap.Connector.Default, txIndexNull =
↳repcap.TxIndexNull.Default)
```

Requires [:SOURce<hw>]:AREGenerator:SWUNit:CABLeCorr:CONNector<di>:RX|TX:MODE USER.
Sets a user-defined delay value.

param areg_cable_cor_del

float Range: 0 to 50

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

6.16.1.16.1.13 File

SCPI Command :

```
[SOURce<HW>]:AREGenerator:SWUNit:CABLe CORR:CONNeCTor<DI>:TX<ST0>:USER:FILE
```

class FileCls

File commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(connector=Connector.Default, txIndexNull=TxIndexNull.Default) → str

```
# SCPI: [SOURce<HW>]:AREGenerator:SWUNit:CABLe CORR:CONNeCTor<DI>:TX<ST0>
→:USER:FILE
value: str = driver.source.areGenerator.swunit.cableCorr.connector.tx.user.file.
→get(connector = repcap.Connector.Default, txIndexNull = repcap.TxIndexNull.
→Default)
```

Requires [:SOURce<hw>]:AREGenerator:SWUNit:CABLe CORR:CONNeCTor<di>:RX|TX:MODE S2P.
Loads a cable correction data file with file extension *.s2p from the default or the specified directory.

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

return

areg_cable_cor_fil: string

set(areg_cable_cor_fil: str, connector=Connector.Default, txIndexNull=TxIndexNull.Default) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:SWUNit:CABLe CORR:CONNeCTor<DI>:TX<ST0>
→:USER:FILE
driver.source.areGenerator.swunit.cableCorr.connector.tx.user.file.set(areg_
→cable_cor_fil = 'abc', connector = repcap.Connector.Default, txIndexNull =
→repcap.TxIndexNull.Default)
```

Requires [:SOURce<hw>]:AREGenerator:SWUNit:CABLe CORR:CONNeCTor<di>:RX|TX:MODE S2P.
Loads a cable correction data file with file extension *.s2p from the default or the specified directory.

param areg_cable_cor_fil

string

param connector

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Connector')

param txIndexNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Tx')

6.16.1.16.2 Connect

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:SWUnit:CONNECT
```

class ConnectCls

Connect commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUnit:CONNECT
driver.source.areGenerator.swunit.connect.set()
```

Triggers connection to the switching unit. The R&S AREG800A connects or disconnects the switching unit as configured by its IP address or hostname.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUnit:CONNECT
driver.source.areGenerator.swunit.connect.set_with_opc()
```

Triggers connection to the switching unit. The R&S AREG800A connects or disconnects the switching unit as configured by its IP address or hostname.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.16.1.16.3 Disconnect

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:SWUnit:DISConnect
```

class DisconnectCls

Disconnect commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUnit:DISConnect
driver.source.areGenerator.swunit.disconnect.set()
```

Triggers connection to the switching unit. The R&S AREG800A connects or disconnects the switching unit as configured by its IP address or hostname.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUnit:DISConnect
driver.source.areGenerator.swunit.disconnect.set_with_opc()
```


Triggers connection to the switching unit. The R&S AREG800A connects or disconnects the switching unit as configured by its IP address or hostname.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.16.1.16.4 Mapping<MappingChannel>

RepCap Settings

```
# Range: Nr1 .. Nr8
rc = driver.source.areGenerator.swunit.mapping.repcap_mappingChannel_get()
driver.source.areGenerator.swunit.mapping.repcap_mappingChannel_set(repcap.
↪MappingChannel.Nr1)
```

class MappingCls

Mapping commands group definition. 1 total commands, 1 Subgroups, 0 group commands Repeated Capability: MappingChannel, default value after init: MappingChannel.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.swunit.mapping.clone()
```

Subgroups

6.16.1.16.4.1 SubChannel<Subchannel>

RepCap Settings

```
# Range: Nr1 .. Nr16
rc = driver.source.areGenerator.swunit.mapping.subChannel.repcap_subchannel_get()
driver.source.areGenerator.swunit.mapping.subChannel.repcap_subchannel_set(repcap.
↪Subchannel.Nr1)
```

class SubChannelCls

SubChannel commands group definition. 1 total commands, 1 Subgroups, 0 group commands Repeated Capability: Subchannel, default value after init: Subchannel.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.swunit.mapping.subChannel.clone()
```

Subgroups

6.16.1.16.4.2 Config

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:SWUNit:MAPPING<CH>:[SUBChannel<ST>]:CONFig
```

class ConfigCls

Config commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(mappingChannel=MappingChannel.Default, subchannel=Subchannel.Default) → str

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUNit:MAPPING<CH>:[SUBChannel<ST>]:CONFig
value: str = driver.source.areGenerator.swunit.mapping.subChannel.config.
↪ get(mappingChannel = repcap.MappingChannel.Default, subchannel = repcap.
↪ Subchannel.Default)
```

Requires [:SOURCE<hw>]:AREGenerator:OSETup:SWUNit[:STATe] 1. Queries the channel RX / channel TX configuration between the switching unit and the R&S AREG800A.

param mappingChannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Mapping')

param subchannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sub-Channel')

return

areg_ext_sw_unit_con: No help available

6.16.1.16.5 Relays

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:SWUNit:RELAys:CATalog
```

class RelaysCls

Relays commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_catalog() → List[str]

```
# SCPI: [SOURCE<HW>]:AREGenerator:SWUNit:RELAys:CATalog
value: List[str] = driver.source.areGenerator.swunit.relays.get_catalog()
```

Requires [:SOURCE<hw>]:AREGenerator:OSETup:SWUNit[:STATe] 1. Queries all available relays of the switching unit. Lists all available relays as a comma-separated list.

```

return
    areg_ext_sw_chan_rx_tx_cat: No help available

```

6.16.1.17 Units

SCPI Commands :

```

[SOURCE<HW>]:AREGenerator:UNITs:ANGLE
[SOURCE<HW>]:AREGenerator:UNITs:C
[SOURCE<HW>]:AREGenerator:UNITs:DOPPler
[SOURCE<HW>]:AREGenerator:UNITs:KCONstant
[SOURCE<HW>]:AREGenerator:UNITs:RANGe
[SOURCE<HW>]:AREGenerator:UNITs:RCS
[SOURCE<HW>]:AREGenerator:UNITs:SHIFt
[SOURCE<HW>]:AREGenerator:UNITs:SPEEd

```

class UnitsCls

Units commands group definition. 8 total commands, 0 Subgroups, 8 group commands

get_angle() → UnitAngleAreg

```

# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:ANGLE
value: enums.UnitAngleAreg = driver.source.areGenerator.units.get_angle()

```

Sets the unit of the horizontal angle of the simulated radar object.

```

return
    areg_unit_agle: DEGREE|RADIAN

```

get_c() → int

```

# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:C
value: int = driver.source.areGenerator.units.get_c()

```

Sets the value of speed of light for internal calculations. The defined value of speed of light is used for calculation of the doppler shift, the distance and the RCS.

```

return
    areg_unit_ligth_sp: integer Range: 2E8 to 3E8

```

get_doppler() → AregDopplerUnit

```

# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:DOPPler
value: enums.AregDopplerUnit = driver.source.areGenerator.units.get_doppler()

```

Defines if the radial velocity is defined as Doppler speed or frequency.

```

return
    areg_obj_dopp_unit: SPEEd|FREQuency

```

get_kconstant() → AregAttRcsKeepConst

```

# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:KCONstant
value: enums.AregAttRcsKeepConst = driver.source.areGenerator.units.get_
↪kconstant()

```

Selects the parameter used as constant value for the calculation of the simulated radar object.

return

areg_keep_const: ATTenuation| RCS ATTenuation Uses the current value for attenuation as constant for the calculation. RCS Uses the current value for RCS as constant for the calculation.

get_range() → UnitLengthAreg

```
# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:RANGe
value: enums.UnitLengthAreg = driver.source.areGenerator.units.get_range()
```

Defines the range unit.

return

areg_unit_range: M| CM| FT M Meter CM Centimeter FT Feet

get_rcs() → UnitRcsAreg

```
# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:RCS
value: enums.UnitRcsAreg = driver.source.areGenerator.units.get_rcs()
```

Defines the unit of the radar cross section.

return

areg_unit_rcs: DBSM| SM DBSM dB relative to one square meter. SM m2 (square meters) .

get_shift() → UnitShiftAreg

```
# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:SHIFt
value: enums.UnitShiftAreg = driver.source.areGenerator.units.get_shift()
```

Defines the unit for the Doppler shift.

return

areg_unit_shift: HZ| KHZ| MHZ HZ Hertz KHZ Kilohertz MHZ Megahertz

get_speed() → UnitSpeedAreg

```
# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:SPEEd
value: enums.UnitSpeedAreg = driver.source.areGenerator.units.get_speed()
```

Defines the speed unit.

return

areg_unit_speed: KMH| MPH| MPS KMH Kilometer per hour MPH Miles per Hour MPS Meter per Seconds

set_angle(areg_unit_agle: UnitAngleAreg) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:ANGLE
driver.source.areGenerator.units.set_angle(areg_unit_agle = enums.UnitAngleAreg.
↪DEGREE)
```

Sets the unit of the horizontal angle of the simulated radar object.

param areg_unit_agle

DEGREE| RADian

set_c(*areg_unit_ligth_sp*: int) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:C
driver.source.areGenerator.units.set_c(areg_unit_ligth_sp = 1)
```

Sets the value of speed of light for internal calculations. The defined value of speed of light is used for calculation of the doppler shift, the distance and the RCS.

param areg_unit_ligth_sp
integer Range: 2E8 to 3E8

set_doppler(*areg_obj_dopp_unit*: AregDopplerUnit) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:DOPPler
driver.source.areGenerator.units.set_doppler(areg_obj_dopp_unit = enums.
↪AregDopplerUnit.FREQuency)
```

Defines if the radial velocity is defined as Doppler speed or frequency.

param areg_obj_dopp_unit
SPEed| FREQuency

set_kconstant(*areg_keep_const*: AregAttRcsKeepConst) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:KCONstant
driver.source.areGenerator.units.set_kconstant(areg_keep_const = enums.
↪AregAttRcsKeepConst.ATTenuation)
```

Selects the parameter used as constant value for the calculation of the simulated radar object.

param areg_keep_const
ATTenuation| RCS ATTenuation Uses the current value for attenuation as constant for the calculation. RCS Uses the current value for RCS as constant for the calculation.

set_range(*areg_unit_range*: UnitLengthAreg) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:RANGe
driver.source.areGenerator.units.set_range(areg_unit_range = enums.
↪UnitLengthAreg.CM)
```

Defines the range unit.

param areg_unit_range
M| CM| FT M Meter CM Centimeter FT Feet

set_rcs(*areg_unit_rcs*: UnitRcsAreg) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:RCS
driver.source.areGenerator.units.set_rcs(areg_unit_rcs = enums.UnitRcsAreg.DBSM)
```

Defines the unit of the radar cross section.

param areg_unit_rcs
DBSM| SM DBSM dB relative to one square meter. SM m2 (square meters) .

set_shift(*areg_unit_shift*: UnitShiftAreg) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:SHIFt
driver.source.areGenerator.units.set_shift(areg_unit_shift = enums.
↳UnitShiftAreg.HZ)
```

Defines the unit for the Doppler shift.

```
param areg_unit_shift
    HZ| KHZ| MHZ HZ Hertz KHZ Kilohertz MHZ Megahertz
```

```
set_speed(areg_unit_speed: UnitSpeedAreg) → None
```

```
# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:SPEEd
driver.source.areGenerator.units.set_speed(areg_unit_speed = enums.
↳UnitSpeedAreg.KMH)
```

Defines the speed unit.

```
param areg_unit_speed
    KMH| MPH| MPS KMH Kilometer per hour MPH Miles per Hour MPS Meter per
    Seconds
```

6.16.2 Bb

class BbCls

Bb commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.bb.clone()
```

Subgroups

6.16.2.1 Path

SCPI Command :

```
[SOURCE]:BB:PATH:COUNT
```

class PathCls

Path commands group definition. 1 total commands, 0 Subgroups, 1 group commands

```
get_count() → int
```

```
# SCPI: [SOURCE]:BB:PATH:COUNT
value: int = driver.source.bb.path.get_count()
```

No command help available

```
return
    count: No help available
```

6.16.3 InputPy

class InputPyCls

InputPy commands group definition. 8 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.inputPy.clone()
```

Subgroups

6.16.3.1 Trigger

SCPI Command :

```
[SOURce]:INPut:TRIGger:SLOPe
```

class TriggerCls

Trigger commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_slope() → SlopeType

```
# SCPI: [SOURce]:INPut:TRIGger:SLOPe
value: enums.SlopeType = driver.source.inputPy.trigger.get_slope()
```

No command help available

```
return
    slope: No help available
```

set_slope(slope: SlopeType) → None

```
# SCPI: [SOURce]:INPut:TRIGger:SLOPe
driver.source.inputPy.trigger.set_slope(slope = enums.SlopeType.NEGative)
```

No command help available

```
param slope
    No help available
```

6.16.3.2 User<UserIx>

RepCap Settings

```
# Range: Nr1 .. Nr48
rc = driver.source.inputPy.user.repcap_userIx_get()
driver.source.inputPy.user.repcap_userIx_set(repcap.UserIx.Nr1)
```

class UserCls

User commands group definition. 7 total commands, 3 Subgroups, 0 group commands Repeated Capability: UserIx, default value after init: UserIx.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.inputPy.user.clone()
```

Subgroups

6.16.3.2.1 Clock

SCPI Commands :

```
[SOURce]:INPut:USER:CLOCK:IMPedance
[SOURce]:INPut:USER:CLOCK:LEVe1
[SOURce]:INPut:USER:CLOCK:SLOPe
```

class ClockCls

Clock commands group definition. 3 total commands, 0 Subgroups, 3 group commands

get_impedance() → ImpG50G1KcoerceG10K

```
# SCPI: [SOURce]:INPut:USER:CLOCK:IMPedance
value: enums.ImpG50G1KcoerceG10K = driver.source.inputPy.user.clock.get_
↳ impedance()
```

No command help available

```
return
    impedance: No help available
```

get_level() → float

```
# SCPI: [SOURce]:INPut:USER:CLOCK:LEVe1
value: float = driver.source.inputPy.user.clock.get_level()
```

No command help available

```
return
    level: No help available
```

get_slope() → SlopeType

```
# SCPI: [SOURce]:INPut:USER:CLOCK:SLOPe
value: enums.SlopeType = driver.source.inputPy.user.clock.get_slope()
```

No command help available

```
return
    slope: No help available
```

set_impedance(impedance: ImpG50G1KcoerceG10K) → None

```
# SCPI: [SOURce]:INPut:USER:CLOCK:IMPedance
driver.source.inputPy.user.clock.set_impedance(impedance = enums.
↳ ImpG50G1KcoerceG10K.G1K)
```


No command help available

param impedance

No help available

set_level(*level: float*) → None

```
# SCPI: [SOURCE]:INPut:USER:CLOCK:LEVel
driver.source.inputPy.user.clock.set_level(level = 1.0)
```

No command help available

param level

No help available

set_slope(*slope: SlopeType*) → None

```
# SCPI: [SOURCE]:INPut:USER:CLOCK:SLOPe
driver.source.inputPy.user.clock.set_slope(slope = enums.SlopeType.NEGative)
```

No command help available

param slope

No help available

6.16.3.2.2 Direction

SCPI Command :

```
[SOURCE]:INPut:USER<CH>:DIRection
```

class DirectionCls

Direction commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*userIx=UserIx.Default*) → ConnDirection

```
# SCPI: [SOURCE]:INPut:USER<CH>:DIRection
value: enums.ConnDirection = driver.source.inputPy.user.direction.get(userIx =
↳repcap.UserIx.Default)
```

Determines whether the connector is used as an output or is not used.

param userIx

optional repeated capability selector. Default value: Nr1 (settable in the interface 'User')

return

direction: INPut| OUTPut| UNUSed OUTPut The connector is used as output. UN-Used The connector is not used.

set(*direction: ConnDirection, userIx=UserIx.Default*) → None

```
# SCPI: [SOURCE]:INPut:USER<CH>:DIRection
driver.source.inputPy.user.direction.set(direction = enums.ConnDirection.INPut,
↳userIx = repcap.UserIx.Default)
```

Determines whether the connector is used as an output or is not used.

param direction

INPut| OUTPut| UNUSed OUTPut The connector is used as output. UNUSed The connector is not used.

param userIx

optional repeated capability selector. Default value: Nr1 (settable in the interface 'User')

6.16.3.2.3 Trigger**SCPI Commands :**

```
[SOURce]:INPut:USER:TRIGger:IMPedance
[SOURce]:INPut:USER:TRIGger:LEVel
[SOURce]:INPut:USER:TRIGger:SLOPe
```

class TriggerCls

Trigger commands group definition. 3 total commands, 0 Subgroups, 3 group commands

get_impedance() → ImpG50G1KcoerceG10K

```
# SCPI: [SOURce]:INPut:USER:TRIGger:IMPedance
value: enums.ImpG50G1KcoerceG10K = driver.source.inputPy.user.trigger.get_
↳ impedance()
```

No command help available

return

impedance: No help available

get_level() → float

```
# SCPI: [SOURce]:INPut:USER:TRIGger:LEVel
value: float = driver.source.inputPy.user.trigger.get_level()
```

No command help available

return

level: No help available

get_slope() → SlopeType

```
# SCPI: [SOURce]:INPut:USER:TRIGger:SLOPe
value: enums.SlopeType = driver.source.inputPy.user.trigger.get_slope()
```

No command help available

return

slope: No help available

set_impedance(impedance: ImpG50G1KcoerceG10K) → None

```
# SCPI: [SOURce]:INPut:USER:TRIGger:IMPedance
driver.source.inputPy.user.trigger.set_impedance(impedance = enums.
↳ ImpG50G1KcoerceG10K.G1K)
```

No command help available

param impedance

No help available

set_level(*level: float*) → None

```
# SCPI: [SOURCE]:INPut:USER:TRIGger:LEVel
driver.source.inputPy.user.trigger.set_level(level = 1.0)
```

No command help available

param level

No help available

set_slope(*slope: SlopeType*) → None

```
# SCPI: [SOURCE]:INPut:USER:TRIGger:SLOPe
driver.source.inputPy.user.trigger.set_slope(slope = enums.SlopeType.NEGative)
```

No command help available

param slope

No help available

6.16.4 Modulation

class ModulationCls

Modulation commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.modulation.clone()
```

Subgroups

6.16.4.1 All

SCPI Command :

```
[SOURCE<HW>]:MODulation:[ALL]:[STATE]
```

class AllCls

All commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: [SOURCE<HW>]:MODulation:[ALL]:[STATE]
value: bool = driver.source.modulation.all.get_state()
```

No command help available

return

state: No help available

set_state(state: bool) → None

```
# SCPI: [SOURCE<HW>]:MODulation:[ALL]:[STATE]
driver.source.modulation.all.set_state(state = False)
```

No command help available

param state

No help available

6.16.5 Path

SCPI Command :

```
[SOURCE]:PATH:COUNT
```

class PathCls

Path commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_count() → int

```
# SCPI: [SOURCE]:PATH:COUNT
value: int = driver.source.path.get_count()
```

No command help available

return

count: No help available

6.16.6 Power

class PowerCls

Power commands group definition. 3 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.power.clone()
```

Subgroups

6.16.6.1 Level

class LevelCls

Level commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.power.level.clone()
```

Subgroups

6.16.6.1.1 Immediate

SCPI Command :

```
[SOURce<HW>]:POWer:[LEVel]:[IMMediate]:RCL
```

class ImmediateCls

Immediate commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_recall() → InclExcl

```
# SCPI: [SOURce<HW>]:POWer:[LEVel]:[IMMediate]:RCL
value: enums.InclExcl = driver.source.power.level.immediate.get_recall()
```

No command help available

```
return
    rcl: No help available
```

set_recall(rcl: InclExcl) → None

```
# SCPI: [SOURce<HW>]:POWer:[LEVel]:[IMMediate]:RCL
driver.source.power.level.immediate.set_recall(rcl = enums.InclExcl.EXCLUDE)
```

No command help available

```
param rcl
    No help available
```

6.16.6.2 Spc

class SpcCls

Spc commands group definition. 2 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.power.spc.clone()
```

Subgroups

6.16.6.2.1 Measure

SCPI Command :

```
[SOURce<HW>]:POWer:SPC:MEASure
```

class MeasureCls

Measure commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: [SOURce<HW>]:POWer:SPC:MEASure
driver.source.power.spc.measure.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURce<HW>]:POWer:SPC:MEASure
driver.source.power.spc.measure.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.16.6.2.2 Single

SCPI Command :

```
[SOURce<HW>]:POWer:SPC:SINGLe
```

class SingleCls

Single commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: [SOURCE<HW>]:POWER:SPC:SINGLE
driver.source.power.spc.single.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURCE<HW>]:POWER:SPC:SINGLE
driver.source.power.spc.single.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.16.7 Roscillator

SCPI Commands :

```
[SOURCE]:ROScillator:PRESet
[SOURCE]:ROScillator:SOURce
```

class RoscillatorCls

Roscillator commands group definition. 8 total commands, 3 Subgroups, 2 group commands

get_source() → RoscSourSetup

```
# SCPI: [SOURCE]:ROScillator:SOURce
value: enums.RoscSourSetup = driver.source.roscillator.get_source()
```

Selects between internal or external reference frequency.

return

source: INTERNAL| EXTERNAL

preset() → None

```
# SCPI: [SOURCE]:ROScillator:PRESet
driver.source.roscillator.preset()
```

Resets the reference oscillator settings.

preset_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURCE]:ROScillator:PRESet
driver.source.roscillator.preset_with_opc()
```

Resets the reference oscillator settings.

Same as preset, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

set_source(source: *RoscSourSetup*) → None

```
# SCPI: [SOURce]:ROSCillator:SOURce
driver.source.rosillator.set_source(source = enums.RoscSourSetup.ELoop)
```

Selects between internal or external reference frequency.

param source

INTernal| EXTernal

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.rosillator.clone()
```

Subgroups

6.16.7.1 External

SCPI Commands :

```
[SOURce]:ROSCillator:EXTernal:FREQuency
[SOURce]:ROSCillator:EXTernal:SBANdwidth
```

class ExternalCls

External commands group definition. 3 total commands, 1 Subgroups, 2 group commands

get_frequency() → RoscFreqExtAreg800A

```
# SCPI: [SOURce]:ROSCillator:EXTernal:FREQuency
value: enums.RoscFreqExtAreg800A = driver.source.rosillator.external.get_
↪frequency()
```

Sets the frequency of the external reference.

return

frequency: 10MHZ| 3200MHZ

get_sbandwidth() → RoscBandWidtExt

```
# SCPI: [SOURce]:ROSCillator:EXTernal:SBANdwidth
value: enums.RoscBandWidtExt = driver.source.rosillator.external.get_
↪sbandwidth()
```

Selects the synchronization bandwidth for the external reference signal. See [:SOURce]:ROSCillator:SOURce > External. Depending on the RF hardware version, and the installed options, the synchronization bandwidth varies. For more information, see data sheet.

return

sbandwidth: WIDE| NARRow NARRow The synchronization bandwidth is a few Hz.

WIDE Uses the widest possible synchronization bandwidth.

set_frequency(frequency: RoscFreqExtAreg800A) → None

```
# SCPI: [SOURce]:ROSCillator:EXternal:FREquency
driver.source.roscillator.external.set_frequency(frequency = enums.
↪RoscFreqExtAreg800A._10MHZ)
```

Sets the frequency of the external reference.

param frequency
10MHZ| 3200MHZ

set_sbandwidth(sbandwidth: RoscBandWidtExt) → None

```
# SCPI: [SOURce]:ROSCillator:EXternal:SBANdwidth
driver.source.roscillator.external.set_sbandwidth(sbandwidth = enums.
↪RoscBandWidtExt.NARRow)
```

Selects the synchronization bandwidth for the external reference signal. See [:SOURce]:ROSCillator:SOURce > External. Depending on the RF hardware version, and the installed options, the synchronization bandwidth varies. For more information, see data sheet.

param sbandwidth
WIDE| NARRow NARRow The synchronization bandwidth is a few Hz. WIDE Uses the widest possible synchronization bandwidth.

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.roscillator.external.clone()
```

Subgroups

6.16.7.1.1 RfOff

SCPI Command :

```
[SOURce]:ROSCillator:EXternal:RFOff:[STATe]
```

class RfOffCls

RfOff commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: [SOURce]:ROSCillator:EXternal:RFOff:[STATe]
value: bool = driver.source.roscillator.external.rfOff.get_state()
```

Determines that the RF output is turned off when the external reference signal is selected, but missing.

return
state: 1| ON| 0| OFF

set_state(state: bool) → None

```
# SCPI: [SOURce]:ROSCillator:EXTernal:RFOff:[STATe]
driver.source.roscillator.external.rfOff.set_state(state = False)
```

Determines that the RF output is turned off when the external reference signal is selected, but missing.

param state
1| ON| 0| OFF

6.16.7.2 Internal

class InternalCls

Internal commands group definition. 2 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.roscillator.internal.clone()
```

Subgroups

6.16.7.2.1 Adjust

SCPI Commands :

```
[SOURce]:ROSCillator:[INTernal]:ADJust:VALue
[SOURce]:ROSCillator:[INTernal]:ADJust:[STATe]
```

class AdjustCls

Adjust commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_state() → bool

```
# SCPI: [SOURce]:ROSCillator:[INTernal]:ADJust:[STATe]
value: bool = driver.source.roscillator.internal.adjust.get_state()
```

Determines whether the calibrated (off) or a user-defined (on) adjustment value is used for fine adjustment of the frequency.

return
state: 1| ON| 0| OFF 0 Fine adjustment with the calibrated frequency value 1 User-defined adjustment value. The instrument is no longer in the calibrated state. The calibration value is, however, not changed. The instrument resumes the calibrated state if you send SOURce:ROSCillator:INTernal:ADJust:STATe 0.

get_value() → int

```
# SCPI: [SOURce]:ROSCillator:[INTernal]:ADJust:VALue
value: int = driver.source.roscillator.internal.adjust.get_value()
```

Specifies the frequency correction value (adjustment value) .

return
value: integer

set_state(state: bool) → None

```
# SCPI: [SOURce]:ROSCillator:[INTernal]:ADJust:[STATe]
driver.source.roscillator.internal.adjust.set_state(state = False)
```

Determines whether the calibrated (off) or a user-defined (on) adjustment value is used for fine adjustment of the frequency.

param state

1| ON| 0| OFF 0 Fine adjustment with the calibrated frequency value 1 User-defined adjustment value. The instrument is no longer in the calibrated state. The calibration value is, however, not changed. The instrument resumes the calibrated state if you send SOURce:ROSCillator:INTernal:ADJust:STATe 0.

set_value(value: int) → None

```
# SCPI: [SOURce]:ROSCillator:[INTernal]:ADJust:VALue
driver.source.roscillator.internal.adjust.set_value(value = 1)
```

Specifies the frequency correction value (adjustment value) .

param value
integer

6.16.7.3 Output

class OutputCls

Output commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.roscillator.output.clone()
```

Subgroups

6.16.7.3.1 Frequency

SCPI Command :

```
[SOURce]:ROSCillator:OUTPut:FREQuency:MODE
```

class FrequencyCls

Frequency commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_mode() → RoscOutpFreqModeSmbb

```
# SCPI: [SOURCE]:ROSCillator:OUTPut:FREQuency:MODE
value: enums.RoscOutpFreqModeSmbb = driver.source.roscillator.output.frequency.
↳ get_mode()
```

Selects the mode for the output reference frequency.

return

outp_freq_mode: DER10M| OFF DER10M Sets the output reference frequency to 10 MHz. The reference frequency is derived from the internal reference frequency. OFF Disables the output.

set_mode(outp_freq_mode: *RoscOutpFreqModeSmbb*) → None

```
# SCPI: [SOURCE]:ROSCillator:OUTPut:FREQuency:MODE
driver.source.roscillator.output.frequency.set_mode(outp_freq_mode = enums.
↳ RoscOutpFreqModeSmbb.DER10M)
```

Selects the mode for the output reference frequency.

param outp_freq_mode

DER10M| OFF DER10M Sets the output reference frequency to 10 MHz. The reference frequency is derived from the internal reference frequency. OFF Disables the output.

6.17 Status

SCPI Command :

STATUS:PRESet

class StatusCls

Status commands group definition. 22 total commands, 3 Subgroups, 1 group commands

get_preset() → str

```
# SCPI: STATUS:PRESet
value: str = driver.status.get_preset()
```

Resets the status registers. All PTRansition parts are set to FFFFh (32767) , i.e. all transitions from 0 to 1 are detected. All NTRansition parts are set to 0, i.e. a transition from 1 to 0 in a CONDition bit is not detected. The ENABLE parts of STATUS:OPERation and STATUS:QUEStionable are set to 0, i.e. all events in these registers are not passed on.

return

preset: string

set_preset(preset: str) → None

```
# SCPI: STATUS:PRESet
driver.status.set_preset(preset = 'abc')
```

Resets the status registers. All PTRansition parts are set to FFFFh (32767) , i.e. all transitions from 0 to 1 are detected. All NTRansition parts are set to 0, i.e. a transition from 1 to 0 in a CONDition bit is not

detected. The ENABLE parts of STATUS:OPERation and STATUS:QUEStionable are set to 0, i.e. all events in these registers are not passed on.

```
param preset
    string
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.status.clone()
```

Subgroups

6.17.1 Operation

SCPI Commands :

```
STATUS:OPERation:CONDition
STATUS:OPERation:ENABLE
STATUS:OPERation:NTRansition
STATUS:OPERation:PTRansition
STATUS:OPERation:[EVENTt]
```

class OperationCls

Operation commands group definition. 10 total commands, 1 Subgroups, 5 group commands

get_condition() → str

```
# SCPI: STATUS:OPERation:CONDition
value: str = driver.status.operation.get_condition()
```

Queries the content of the CONDition part of the STATUS:OPERation register. This part contains information on the action currently being performed in the instrument. The content is not deleted after being read out because it indicates the current hardware status.

```
return
    condition: string
```

get_enable() → str

```
# SCPI: STATUS:OPERation:ENABLE
value: str = driver.status.operation.get_enable()
```

Sets the bits of the ENABLE part of the STATUS:OPERation register. This setting determines which events of the Status-Event part are forwarded to the sum bit in the status byte. These events can be used for a service request.

```
return
    enable: string
```

get_event() → str

```
# SCPI: STATUS:OPERation:[EVENTt]
value: str = driver.status.operation.get_event()
```

Queries the content of the EVENT part of the STATUS:OPERation register. This part contains information on the actions performed in the instrument since the last readout. The content of the EVENT part is deleted after being read out.

return
value: No help available

get_ntransition() → str

```
# SCPI: STATUS:OPERation:NTRansition
value: str = driver.status.operation.get_ntransition()
```

Sets the bits of the NTRansition part of the STATUS:OPERation register. If a bit is set, a transition from 1 to 0 in the condition part causes an entry to be made in the EVENT part of the register. The disappearance of an event in the hardware is thus registered, for example the end of an adjustment.

return
ntransition: string

get_ptransition() → str

```
# SCPI: STATUS:OPERation:PTRansition
value: str = driver.status.operation.get_ptransition()
```

Sets the bits of the PTRansition part of the STATUS:OPERation register. If a bit is set, a transition from 0 to 1 in the condition part causes an entry to be made in the EVENT part of the register. A new event in the hardware is thus registered, for example the start of an adjustment.

return
ptransition: string

set_enable(enable: str) → None

```
# SCPI: STATUS:OPERation:ENABLE
driver.status.operation.set_enable(enable = 'abc')
```

Sets the bits of the ENABLE part of the STATUS:OPERation register. This setting determines which events of the Status-Event part are forwarded to the sum bit in the status byte. These events can be used for a service request.

param enable
string

set_event(value: str) → None

```
# SCPI: STATUS:OPERation:[EVENT]
driver.status.operation.set_event(value = 'abc')
```

Queries the content of the EVENT part of the STATUS:OPERation register. This part contains information on the actions performed in the instrument since the last readout. The content of the EVENT part is deleted after being read out.

param value
string

set_ntransition(ntransition: str) → None

```
# SCPI: STATUS:OPERation:NTRansition
driver.status.operation.set_ntransition(ntransition = 'abc')
```

Sets the bits of the NTRansition part of the STATus:OPERation register. If a bit is set, a transition from 1 to 0 in the condition part causes an entry to be made in the EVENT part of the register. The disappearance of an event in the hardware is thus registered, for example the end of an adjustment.

param ntransition
string

set_ptransition(ptransition: str) → None

```
# SCPI: STATus:OPERation:PTRansition
driver.status.operation.set_ptransition(ptransition = 'abc')
```

Sets the bits of the PTRansition part of the STATus:OPERation register. If a bit is set, a transition from 0 to 1 in the condition part causes an entry to be made in the EVENT part of the register. A new event in the hardware is thus registered, for example the start of an adjustment.

param ptransition
string

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.status.operation.clone()
```

Subgroups

6.17.1.1 Bit<BitNumberNull>

RepCap Settings

```
# Range: Nr0 .. Nr15
rc = driver.status.operation.bit.repcap_bitNumberNull_get()
driver.status.operation.bit.repcap_bitNumberNull_set(repcap.BitNumberNull.Nr0)
```

class BitCls

Bit commands group definition. 5 total commands, 5 Subgroups, 0 group commands Repeated Capability: Bit-NumberNull, default value after init: BitNumberNull.Nr0

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.status.operation.bit.clone()
```

Subgroups

6.17.1.1.1 Condition

SCPI Command :

STATus:OPERation:BIT<BITNR>:CONDition

class ConditionCls

Condition commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*bitNumberNull=BitNumberNull.Default*) → str

```
# SCPI: STATus:OPERation:BIT<BITNR>:CONDition
value: str = driver.status.operation.bit.condition.get(bitNumberNull = repcap.
↳BitNumberNull.Default)
```

No command help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

return

condition: No help available

6.17.1.1.2 Enable

SCPI Command :

STATus:OPERation:BIT<BITNR>:ENABle

class EnableCls

Enable commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*bitNumberNull=BitNumberNull.Default*) → str

```
# SCPI: STATus:OPERation:BIT<BITNR>:ENABle
value: str = driver.status.operation.bit.enable.get(bitNumberNull = repcap.
↳BitNumberNull.Default)
```

No command help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

return

enable: No help available

set(*enable: str, bitNumberNull=BitNumberNull.Default*) → None

```
# SCPI: STATus:OPERation:BIT<BITNR>:ENABle
driver.status.operation.bit.enable.set(enable = 'abc', bitNumberNull = repcap.
↳BitNumberNull.Default)
```

No command help available

param enable

No help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

6.17.1.1.3 Event**SCPI Command :**

```
STATus:OPERation:BIT<BITNR>:[EVENT]
```

class EventCls

Event commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*bitNumberNull=BitNumberNull.Default*) → str

```
# SCPI: STATus:OPERation:BIT<BITNR>:[EVENT]
value: str = driver.status.operation.bit.event.get(bitNumberNull = repcap.
↳ BitNumberNull.Default)
```

No command help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

return

event: No help available

6.17.1.1.4 Ntransition**SCPI Command :**

```
STATus:OPERation:BIT<BITNR>:NTRansition
```

class NtransitionCls

Ntransition commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*bitNumberNull=BitNumberNull.Default*) → str

```
# SCPI: STATus:OPERation:BIT<BITNR>:NTRansition
value: str = driver.status.operation.bit.ntransition.get(bitNumberNull = repcap.
↳ BitNumberNull.Default)
```

No command help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

return

ntransition: No help available

set(*ntransition: str*, *bitNumberNull=BitNumberNull.Default*) → None

```
# SCPI: STATus:OPERation:BIT<BITNR>:NTRansition
driver.status.operation.bit.ntransition.set(ntransition = 'abc', bitNumberNull_
↳= repcap.BitNumberNull.Default)
```

No command help available

param ntransition
No help available

param bitNumberNull
optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

6.17.1.1.5 Ptransition

SCPI Command :

```
STATus:OPERation:BIT<BITNR>:PTRansition
```

class PtransitionCls

Ptransition commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*bitNumberNull=BitNumberNull.Default*) → str

```
# SCPI: STATus:OPERation:BIT<BITNR>:PTRansition
value: str = driver.status.operation.bit.ptransition.get(bitNumberNull = repcap.
↳BitNumberNull.Default)
```

No command help available

param bitNumberNull
optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

return
ptransition: No help available

set(*ptransition: str*, *bitNumberNull=BitNumberNull.Default*) → None

```
# SCPI: STATus:OPERation:BIT<BITNR>:PTRansition
driver.status.operation.bit.ptransition.set(ptransition = 'abc', bitNumberNull_
↳= repcap.BitNumberNull.Default)
```

No command help available

param ptransition
No help available

param bitNumberNull
optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

6.17.2 Questionable

SCPI Commands :

```

STATus:QUESTionable:CONDition
STATus:QUESTionable:ENABle
STATus:QUESTionable:NTRansition
STATus:QUESTionable:PTRansition
STATus:QUESTionable:[EVENT]

```

class QuestionableCls

Questionable commands group definition. 10 total commands, 1 Subgroups, 5 group commands

get_condition() → str

```

# SCPI: STATus:QUESTionable:CONDition
value: str = driver.status.questionable.get_condition()

```

Queries the content of the CONDition part of the STATus:QUESTionable register. This part contains information on the action currently being performed in the instrument. The content is not deleted after being read out since it indicates the current hardware status.

```

return
    condition: string

```

get_enable() → str

```

# SCPI: STATus:QUESTionable:ENABle
value: str = driver.status.questionable.get_enable()

```

Sets the bits of the ENABle part of the STATus:QUESTionable register. The enable part determines which events of the STATus:EVENT part are enabled for the summary bit in the status byte. These events can be used for a service request. If a bit in the ENABle part is 1, and the corresponding EVENT bit is true, a positive transition occurs in the summary bit. This transition is reportet to the next higher level.

```

return
    enable: string

```

get_event() → str

```

# SCPI: STATus:QUESTionable:[EVENT]
value: str = driver.status.questionable.get_event()

```

Queries the content of the EVENT part of the method RsAreg800.Status.Questionable.event register. This part contains information on the actions performed in the instrument since the last readout. The content of the EVENT part is deleted after being read out.

```

return
    value: No help available

```

get_ntransition() → str

```

# SCPI: STATus:QUESTionable:NTRansition
value: str = driver.status.questionable.get_ntransition()

```

Sets the bits of the NTRansition part of the STATus:QUESTionable register. If a bit is set, a transition from 1 to 0 in the condition part causes an entry to be made in the EVENT part of the register.

return
ntransition: string

get_ptransition() → str

```
# SCPI: STATus:QUEStionable:PTRansition
value: str = driver.status.questionable.get_ptransition()
```

Sets the bits of the NTRansition part of the STATUS:QUEStionable register. If a bit is set, a transition from 1 to 0 in the condition part causes an entry to be made in the EVENT part of the register.

return
ptransition: string

set_condition(condition: str) → None

```
# SCPI: STATus:QUEStionable:CONDition
driver.status.questionable.set_condition(condition = 'abc')
```

Queries the content of the CONDition part of the STATUS:QUEStionable register. This part contains information on the action currently being performed in the instrument. The content is not deleted after being read out since it indicates the current hardware status.

param condition
string

set_enable(enable: str) → None

```
# SCPI: STATus:QUEStionable:ENABle
driver.status.questionable.set_enable(enable = 'abc')
```

Sets the bits of the ENABle part of the STATUS:QUEStionable register. The enable part determines which events of the STATUS:EVENT part are enabled for the summary bit in the status byte. These events can be used for a service request. If a bit in the ENABle part is 1, and the corresponding EVENT bit is true, a positive transition occurs in the summary bit. This transition is reportet to the next higher level.

param enable
string

set_event(value: str) → None

```
# SCPI: STATus:QUEStionable:[EVENT]
driver.status.questionable.set_event(value = 'abc')
```

Queries the content of the EVENT part of the method RsAreg800.Status.Questionable.event register. This part contains information on the actions performed in the instrument since the last readout. The content of the EVENT part is deleted after being read out.

param value
string

set_ntransition(ntransition: str) → None

```
# SCPI: STATus:QUEStionable:NTRansition
driver.status.questionable.set_ntransition(ntransition = 'abc')
```

Sets the bits of the NTRansition part of the STATUS:QUEStionable register. If a bit is set, a transition from 1 to 0 in the condition part causes an entry to be made in the EVENT part of the register.

param ntransition
string

set_ptransition(ptransition: str) → None

```
# SCPI: STATus:QUEStionable:PTRansition
driver.status.questionable.set_ptransition(ptransition = 'abc')
```

Sets the bits of the NTRansition part of the STATus:QUEStionable register. If a bit is set, a transition from 1 to 0 in the condition part causes an entry to be made in the EVENt part of the register.

param ptransition
string

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.status.questionable.clone()
```

Subgroups

6.17.2.1 Bit<BitNumberNull>

RepCap Settings

```
# Range: Nr0 .. Nr15
rc = driver.status.questionable.bit.repcap_bitNumberNull_get()
driver.status.questionable.bit.repcap_bitNumberNull_set(repcap.BitNumberNull.Nr0)
```

class BitCls

Bit commands group definition. 5 total commands, 5 Subgroups, 0 group commands Repeated Capability: Bit-NumberNull, default value after init: BitNumberNull.Nr0

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.status.questionable.bit.clone()
```

Subgroups

6.17.2.1.1 Condition

SCPI Command :

```
STATus:QUEStionable:BIT<BITNR>:CONDition
```

class ConditionCls

Condition commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*bitNumberNull=BitNumberNull.Default*) → str

```
# SCPI: STATus:QUEStionable:BIT<BITNR>:CONDition
value: str = driver.status.questionable.bit.condition.get(bitNumberNull = ↵
↵repcap.BitNumberNull.Default)
```

No command help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

return

condition: No help available

6.17.2.1.2 Enable

SCPI Command :

```
STATus:QUEStionable:BIT<BITNR>:ENABLE
```

class EnableCls

Enable commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*bitNumberNull=BitNumberNull.Default*) → str

```
# SCPI: STATus:QUEStionable:BIT<BITNR>:ENABLE
value: str = driver.status.questionable.bit.enable.get(bitNumberNull = repcap.
↵BitNumberNull.Default)
```

No command help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

return

enable: No help available

set(*enable: str, bitNumberNull=BitNumberNull.Default*) → None

```
# SCPI: STATus:QUEStionable:BIT<BITNR>:ENABLE
driver.status.questionable.bit.enable.set(enable = 'abc', bitNumberNull = ↵
↵repcap.BitNumberNull.Default)
```

No command help available

param enable

No help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

6.17.2.1.3 Event

SCPI Command :

```
STATus:QUESTionable:BIT<BITNR>:[EVENT]
```

class EventCls

Event commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*bitNumberNull=BitNumberNull.Default*) → str

```
# SCPI: STATus:QUESTionable:BIT<BITNR>:[EVENT]
value: str = driver.status.questionable.bit.event.get(bitNumberNull = repcap.
↳BitNumberNull.Default)
```

No command help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

return

event: No help available

6.17.2.1.4 Ntransition

SCPI Command :

```
STATus:QUESTionable:BIT<BITNR>:NTRansition
```

class NtransitionCls

Ntransition commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*bitNumberNull=BitNumberNull.Default*) → str

```
# SCPI: STATus:QUESTionable:BIT<BITNR>:NTRansition
value: str = driver.status.questionable.bit.ntransition.get(bitNumberNull =
↳repcap.BitNumberNull.Default)
```

No command help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

return

ntransition: No help available

set(*ntransition: str, bitNumberNull=BitNumberNull.Default*) → None

```
# SCPI: STATus:QUESTionable:BIT<BITNR>:NTRansition
driver.status.questionable.bit.ntransition.set(ntransition = 'abc',
↳bitNumberNull = repcap.BitNumberNull.Default)
```

No command help available

param ntransition

No help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface ‘Bit’)

6.17.2.1.5 Ptransition

SCPI Command :

```
STATUS:QUESTionable:BIT<BITNR>:PTRansition
```

class PtransitionCls

Ptransition commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*bitNumberNull=BitNumberNull.Default*) → str

```
# SCPI: STATUS:QUESTionable:BIT<BITNR>:PTRansition
value: str = driver.status.questionable.bit.ptransition.get(bitNumberNull =
↳repcap.BitNumberNull.Default)
```

No command help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface ‘Bit’)

return

ptransition: No help available

set(*ptransition: str, bitNumberNull=BitNumberNull.Default*) → None

```
# SCPI: STATUS:QUESTionable:BIT<BITNR>:PTRansition
driver.status.questionable.bit.ptransition.set(ptransition = 'abc',
↳bitNumberNull = repcap.BitNumberNull.Default)
```

No command help available

param ptransition

No help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface ‘Bit’)

6.17.3 Queue

SCPI Command :

```
STATUS:QUEue: [NEXT]
```

class QueueCls

Queue commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_next() → str

```
# SCPI: STATUS:QUEue: [NEXT]
value: str = driver.status.queue.get_next()
```


Queries the oldest entry in the error queue and then deletes it. Positive error numbers denote device-specific errors, and negative error numbers denote error messages defined by SCPI. If the error queue is empty, 0 ('No error') is returned. The command is identical to SYSTem:ERRor[:NEXT]?

```

return
    next_py: string

```

6.18 System

SCPI Commands :

```

SYSTem:CRASH
SYSTem:DID
SYSTem:IMPort
SYSTem:IRESpone
SYSTem:LANGuage
SYSTem:NINformation
SYSTem:ORESpone
SYSTem:OSYStem
SYSTem:PRESet
SYSTem:PRESet:ALL
SYSTem:PRESet:BASE
SYSTem:RCL
SYSTem:RESet
SYSTem:RESet:ALL
SYSTem:RESet:BASE
SYSTem:SAV
SYSTem:SIMulation
SYSTem:SRCat
SYSTem:SREStore
SYSTem:SRMode
SYSTem:SRSel
SYSTem:SSAVe
SYSTem:TZONE
SYSTem:UPTime
SYSTem:VERsion
SYSTem:WAIT

```

class SystemCls

System commands group definition. 197 total commands, 34 Subgroups, 26 group commands

get_did() → str

```

# SCPI: SYSTem:DID
value: str = driver.system.get_did()

```

No command help available

```

return
    pseudo_string: No help available

```

get_iresponse() → str

```
# SCPI: SYSTem:IResponse
value: str = driver.system.get_iresponse()
```

Defines the user defined identification string for **IDN*. Note: While working in an emulation mode, the instrument's specific command set is disabled, i.e. the SCPI command method RsAreg800.System.iresponse is discarded.

```
return
    idn_response: string
```

get_language() → str

```
# SCPI: SYSTem:LANGuage
value: str = driver.system.get_language()
```

Sets the remote control command set.

```
return
    language: string
```

get_ninformation() → str

```
# SCPI: SYSTem:NINformation
value: str = driver.system.get_ninformation()
```

Queries the oldest information message ('Error History > Level > Info') in the error/event queue.

```
return
    next_info: string
```

get_oresponse() → str

```
# SCPI: SYSTem:OResponse
value: str = driver.system.get_oresponse()
```

Defines the user defined response string for **OPT*. Note: While working in an emulation mode, the instrument's specific command set is disabled, i.e. the SCPI command method RsAreg800.System.oresponse is discarded.

```
return
    oresponse: string
```

get_osystem() → str

```
# SCPI: SYSTem:OSYStem
value: str = driver.system.get_osystem()
```

Queries the operating system of the instrument.

```
return
    oper_system: string
```

get_simulation() → bool

```
# SCPI: SYSTem:SIMulation
value: bool = driver.system.get_simulation()
```

No command help available

return
status: No help available

get_sr_cat() → List[str]

```
# SCPI: SYSTem:SRCat
value: List[str] = driver.system.get_sr_cat()
```

No command help available

return
catalog: No help available

get_sr_mode() → RecScpiCmdMode

```
# SCPI: SYSTem:SRMode
value: enums.RecScpiCmdMode = driver.system.get_sr_mode()
```

No command help available

return
mode: No help available

get_sr_sel() → str

```
# SCPI: SYSTem:SRSel
value: str = driver.system.get_sr_sel()
```

No command help available

return
filename: No help available

get_tzone() → str

```
# SCPI: SYSTem:TZONe
value: str = driver.system.get_tzone()
```

No command help available

return
pseudo_string: No help available

get_up_time() → str

```
# SCPI: SYSTem:UPTime
value: str = driver.system.get_up_time()
```

Queries the up time of the operating system.

return
up_time: 'ddd.hh:mm:ss'

get_version() → str

```
# SCPI: SYSTem:VERsion
value: str = driver.system.get_version()
```

Queries the SCPI version the instrument's command set complies with.

return

version: string

preset(*pseudo_string: str*) → None

```
# SCPI: SYSTem:PRESet
driver.system.preset(pseudo_string = 'abc')
```

INTRO_CMD_HELP: Triggers an instrument reset. It has the same effect **as**:

- The *RST command

:param pseudo_string: No help available

preset_all(*pseudo_string: str*) → None

```
# SCPI: SYSTem:PRESet:ALL
driver.system.preset_all(pseudo_string = 'abc')
```

No command help available

param pseudo_string

No help available

preset_base(*pseudo_string: str*) → None

```
# SCPI: SYSTem:PRESet:BASE
driver.system.preset_base(pseudo_string = 'abc')
```

No command help available

param pseudo_string

No help available

recall(*path_name: str*) → None

```
# SCPI: SYSTem:RCL
driver.system.recall(path_name = 'abc')
```

Selects and uploads a *.savrc.txt file with previously saved R&S AREG800A settings from the default or a specified directory.

param path_name

string

reset(*pseudo_string: str*) → None

```
# SCPI: SYSTem:RESet
driver.system.reset(pseudo_string = 'abc')
```

No command help available

param pseudo_string

No help available

reset_all(*pseudo_string: str*) → None

```
# SCPI: SYSTem:RESet:ALL
driver.system.reset_all(pseudo_string = 'abc')
```

No command help available

param pseudo_string
No help available

reset_base(*pseudo_string: str*) → None

```
# SCPI: SYSTem:RESet:BASE
driver.system.reset_base(pseudo_string = 'abc')
```

No command help available

param pseudo_string
No help available

save(*path_name: str*) → None

```
# SCPI: SYSTem:SAV
driver.system.save(path_name = 'abc')
```

Saves the current R&S AREG800A settings in a file. To determine the file name and storage location, enter the directory and file name with the command. According to the file type, the R&S AREG800A assigns the extension (*.savrltxt) automatically.

param path_name
string

set_crash(*test_scp_i_generic: float*) → None

```
# SCPI: SYSTem:CRASH
driver.system.set_crash(test_scp_i_generic = 1.0)
```

No command help available

param test_scp_i_generic
No help available

set_import_py(*filename: str*) → None

```
# SCPI: SYSTem:IMPort
driver.system.set_import_py(filename = 'abc')
```

No command help available

param filename
No help available

set_iresponse(*idn_response: str*) → None

```
# SCPI: SYSTem:IRESpone
driver.system.set_iresponse(idn_response = 'abc')
```

Defines the user defined identification string for **IDN*. Note: While working in an emulation mode, the instrument's specific command set is disabled, i.e. the SCPI command method RsAreg800.System.iresponse is discarded.

param idn_response
string

set_language(*language: str*) → None

```
# SCPI: SYSTem:LANGuage
driver.system.set_language(language = 'abc')
```

Sets the remote control command set.

param language
string

set_oresponse(*oresponse: str*) → None

```
# SCPI: SYSTem:ORESpouse
driver.system.set_oresponse(oresponse = 'abc')
```

Defines the user defined response string for **OPT*. Note: While working in an emulation mode, the instrument's specific command set is disabled, i.e. the SCPI command method RsAreg800.System.oresponse is discarded.

param oresponse
string

set_sr_mode(*mode: RecScpiCmdMode*) → None

```
# SCPI: SYSTem:SRMode
driver.system.set_sr_mode(mode = enums.RecScpiCmdMode.AUTO)
```

No command help available

param mode
No help available

set_sr_sel(*filename: str*) → None

```
# SCPI: SYSTem:SRSel
driver.system.set_sr_sel(filename = 'abc')
```

No command help available

param filename
No help available

set_srestore(*data_set: int*) → None

```
# SCPI: SYSTem:SREStore
driver.system.set_srestore(data_set = 1)
```

No command help available

param data_set
No help available

set_ssave(data_set: int) → None

```
# SCPI: SYSTem:SSAVe
driver.system.set_ssave(data_set = 1)
```

No command help available

param data_set
No help available

set_tzone(pseudo_string: str) → None

```
# SCPI: SYSTem:TZONe
driver.system.set_tzone(pseudo_string = 'abc')
```

No command help available

param pseudo_string
No help available

set_wait(time_ms: int) → None

```
# SCPI: SYSTem:WAIT
driver.system.set_wait(time_ms = 1)
```

Delays the execution of the subsequent remote command by the specified time. This function is useful, for example to execute an SCPI sequence automatically but with a defined time delay between some commands. See 'How to assign actions to the [User] key'.

param time_ms
integer Wait time in ms Range: 0 to 10000

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.clone()
```

Subgroups

6.18.1 Beeper

SCPI Command :

```
SYSTem:BEEPer:STATe
```

class BeeperCls

Beeper commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:BEEPer:STATe
value: bool = driver.system.beeper.get_state()
```

No command help available

```
        return
            state: No help available

set_state(state: bool) → None
```

```
# SCPI: SYSTem:BEEPer:STAtE
driver.system.beeper.set_state(state = False)
```

No command help available

```
param state
    No help available
```

6.18.2 Bios

SCPI Command :

```
SYSTem:BIOS:VERsion
```

class BiosCls

Bios commands group definition. 1 total commands, 0 Subgroups, 1 group commands

```
get_version() → str
```

```
# SCPI: SYSTem:BIOS:VERsion
value: str = driver.system.bios.get_version()
```

Queries the BIOS version of the instrument.

```
return
    version: string
```

6.18.3 Communicate

class CommunicateCls

Communicate commands group definition. 39 total commands, 9 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.communicate.clone()
```


Subgroups

6.18.3.1 Gpib

SCPI Commands :

```
SYSTEM:COMMunicate:GPIB:LTERminator
SYSTEM:COMMunicate:GPIB:RESource
```

class GpibCls

Gpib commands group definition. 3 total commands, 1 Subgroups, 2 group commands

get_lterminator() → IecTermMode

```
# SCPI: SYSTEM:COMMunicate:GPIB:LTERminator
value: enums.IecTermMode = driver.system.communicate.gpib.get_lterminator()
```

Sets the terminator recognition for remote control via GPIB interface.

return

Iterminator: STANDARD|EOI EOI Recognizes an LF (Line Feed) as the terminator only when it is sent with the line message EOI (End of Line) . This setting is recommended particularly for binary block transmissions, as binary blocks may coincidentally contain a character with value LF (Line Feed) , although it is not determined as a terminator. STANDARD Recognizes an LF (Line Feed) as the terminator regardless of whether it is sent with or without EOI.

get_resource() → str

```
# SCPI: SYSTEM:COMMunicate:GPIB:RESource
value: str = driver.system.communicate.gpib.get_resource()
```

Queries the visa resource string for remote control via the GPIB interface. To change the GPIB address, use the command method RsAreg800.System.Communicate.Gpib.Self.address.

return

resource: string

set_lterminator(lterminator: IecTermMode) → None

```
# SCPI: SYSTEM:COMMunicate:GPIB:LTERminator
driver.system.communicate.gpib.set_lterminator(lterminator = enums.IecTermMode.
↳EOI)
```

Sets the terminator recognition for remote control via GPIB interface.

param lterminator

STANDARD|EOI EOI Recognizes an LF (Line Feed) as the terminator only when it is sent with the line message EOI (End of Line) . This setting is recommended particularly for binary block transmissions, as binary blocks may coincidentally contain a character with value LF (Line Feed) , although it is not determined as a terminator. STANDARD Recognizes an LF (Line Feed) as the terminator regardless of whether it is sent with or without EOI.

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.communicate.gpib.clone()
```

Subgroups

6.18.3.1.1 Self

SCPI Command :

```
SYSTem:COMMunicate:GPIB:[SELF]:ADDRess
```

class SelfCls

Self commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_address() → int

```
# SCPI: SYSTem:COMMunicate:GPIB:[SELF]:ADDRess
value: int = driver.system.communicate.gpib.self.get_address()
```

Sets the GPIB address.

return
address: integer Range: 0 to 30

set_address(address: int) → None

```
# SCPI: SYSTem:COMMunicate:GPIB:[SELF]:ADDRess
driver.system.communicate.gpib.self.set_address(address = 1)
```

Sets the GPIB address.

param address
integer Range: 0 to 30

6.18.3.2 Hislip

SCPI Command :

```
SYSTem:COMMunicate:HISLip:RESource
```

class HislipCls

Hislip commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_resource() → str

```
# SCPI: SYSTem:COMMunicate:HISLip:RESource
value: str = driver.system.communicate.hislip.get_resource()
```

Queries the VISA resource string. This string is used for remote control of the instrument with HiSLIP protocol.

```

return
    resource: string

```

6.18.3.3 Network

SCPI Commands :

```

SYSTEM:COMMunicate:NETWork:MACaddress
SYSTEM:COMMunicate:NETWork:RESource
SYSTEM:COMMunicate:NETWork:STATus

```

class NetworkCls

Network commands group definition. 12 total commands, 3 Subgroups, 3 group commands

get_mac_address() → str

```

# SCPI: SYSTEM:COMMunicate:NETWork:MACaddress
value: str = driver.system.communicate.network.get_mac_address()

```

Queries the MAC address of the network adapter. This is a password-protected function. Unlock the protection level 1 to access it. See method RsAreg800.System.Protect.State.set.

```

return
    mac_address: string

```

get_resource() → str

```

# SCPI: SYSTEM:COMMunicate:NETWork:RESource
value: str = driver.system.communicate.network.get_resource()

```

Queries the visa resource string for Ethernet instruments.

```

return
    resource: string

```

get_status() → bool

```

# SCPI: SYSTEM:COMMunicate:NETWork:STATus
value: bool = driver.system.communicate.network.get_status()

```

Queries the network configuration state.

```

return
    state: 1| ON| 0| OFF

```

set_mac_address(mac_address: str) → None

```

# SCPI: SYSTEM:COMMunicate:NETWork:MACaddress
driver.system.communicate.network.set_mac_address(mac_address = 'abc')

```

Queries the MAC address of the network adapter. This is a password-protected function. Unlock the protection level 1 to access it. See method RsAreg800.System.Protect.State.set.

```

param mac_address
    string

```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.communicate.network.clone()
```

Subgroups

6.18.3.3.1 Common

SCPI Commands :

```
SYSTEM:COMMunicate:NETWork:[COMMON]:DOMain
SYSTEM:COMMunicate:NETWork:[COMMON]:HOSTname
SYSTEM:COMMunicate:NETWork:[COMMON]:WORKgroup
```

class CommonCls

Common commands group definition. 3 total commands, 0 Subgroups, 3 group commands

get_domain() → str

```
# SCPI: SYSTEM:COMMunicate:NETWork:[COMMON]:DOMain
value: str = driver.system.communicate.network.common.get_domain()
```

Determines the primary suffix of the network domain.

```
return
    domain: string
```

get_hostname() → str

```
# SCPI: SYSTEM:COMMunicate:NETWork:[COMMON]:HOSTname
value: str = driver.system.communicate.network.common.get_hostname()
```

Sets an individual hostname for the Automotive Radar Echo Generator. Note: We recommend that you do not change the hostname to avoid problems with the network connection. If you change the hostname, be sure to use a unique name. This is a password-protected function. Unlock the protection level 1 to access it. See method RsAreg800.System.Protect.State.set.

```
return
    hostname: string
```

get_workgroup() → str

```
# SCPI: SYSTEM:COMMunicate:NETWork:[COMMON]:WORKgroup
value: str = driver.system.communicate.network.common.get_workgroup()
```

Sets an individual workgroup name for the instrument.

```
return
    workgroup: string
```

set_domain(domain: str) → None

```
# SCPI: SYSTEM:COMMunicate:NETWork:[COMMON]:DOMain
driver.system.communicate.network.common.set_domain(domain = 'abc')
```

Determines the primary suffix of the network domain.

param domain
string

set_hostname(hostname: str) → None

```
# SCPI: SYSTem:COMMunicate:NETWork:[COMMON]:HOSTname
driver.system.communicate.network.common.set_hostname(hostname = 'abc')
```

Sets an individual hostname for the Automotive Radar Echo Generator. Note: We recommend that you do not change the hostname to avoid problems with the network connection. If you change the hostname, be sure to use a unique name. This is a password-protected function. Unlock the protection level 1 to access it. See method RsAreg800.System.Protect.State.set.

param hostname
string

set_workgroup(workgroup: str) → None

```
# SCPI: SYSTem:COMMunicate:NETWork:[COMMON]:WORKgroup
driver.system.communicate.network.common.set_workgroup(workgroup = 'abc')
```

Sets an individual workgroup name for the instrument.

param workgroup
string

6.18.3.3.2 IpAddress

SCPI Commands :

```
SYSTem:COMMunicate:NETWork:IPAddress:MODE
SYSTem:COMMunicate:NETWork:[IPAddress]:DNS
SYSTem:COMMunicate:NETWork:[IPAddress]:GATeway
SYSTem:COMMunicate:NETWork:IPAddress
```

class IpAddressCls

IpAddress commands group definition. 5 total commands, 1 Subgroups, 4 group commands

get_dns() → str

```
# SCPI: SYSTem:COMMunicate:NETWork:[IPAddress]:DNS
value: str = driver.system.communicate.network.ipAddress.get_dns()
```

Determines or queries the network DNS server to resolve the name.

return
dns: string

get_gateway() → str

```
# SCPI: SYSTem:COMMunicate:NETWork:[IPAddress]:GATeway
value: str = driver.system.communicate.network.ipAddress.get_gateway()
```

Sets the IP address of the default gateway.

return
gateway: string Range: 0.0.0.0 to ff.ff.ff.ff

get_mode() → NetMode

```
# SCPI: SYSTem:COMMunicate:NETWork:IPAdDress:MODE
value: enums.NetMode = driver.system.communicate.network.ipAddress.get_mode()
```

Selects manual or automatic setting of the IP address.

return
mode: AUTO| STATic

get_value() → str

```
# SCPI: SYSTem:COMMunicate:NETWork:IPAdDress
value: str = driver.system.communicate.network.ipAddress.get_value()
```

Sets the IP address.

return
ip_address: string Range: 0.0.0.0. to ff.ff.ff.ff

set_dns(dns: str) → None

```
# SCPI: SYSTem:COMMunicate:NETWork:[IPAdDress]:DNS
driver.system.communicate.network.ipAddress.set_dns(dns = 'abc')
```

Determines or queries the network DNS server to resolve the name.

param dns
string

set_gateway(gateway: str) → None

```
# SCPI: SYSTem:COMMunicate:NETWork:[IPAdDress]:GATeway
driver.system.communicate.network.ipAddress.set_gateway(gateway = 'abc')
```

Sets the IP address of the default gateway.

param gateway
string Range: 0.0.0.0 to ff.ff.ff.ff

set_mode(mode: NetMode) → None

```
# SCPI: SYSTem:COMMunicate:NETWork:IPAdDress:MODE
driver.system.communicate.network.ipAddress.set_mode(mode = enums.NetMode.AUTO)
```

Selects manual or automatic setting of the IP address.

param mode
AUTO| STATic

set_value(ip_address: str) → None

```
# SCPI: SYSTem:COMMunicate:NETWork:IPAdDress
driver.system.communicate.network.ipAddress.set_value(ip_address = 'abc')
```

Sets the IP address.

param ip_address
string Range: 0.0.0.0. to ff.ff.ff.ff

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.communicate.network.ipAddress.clone()
```

Subgroups

6.18.3.3.2.1 Subnet

SCPI Command :

```
SYSTem:COMMunicate:NETWork:[IPAddress]:SUBNet:MASK
```

class SubnetCls

Subnet commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_mask() → str

```
# SCPI: SYSTem:COMMunicate:NETWork:[IPAddress]:SUBNet:MASK
value: str = driver.system.communicate.network.ipAddress.subnet.get_mask()
```

Sets the subnet mask.

return
mask: string

set_mask(mask: str) → None

```
# SCPI: SYSTem:COMMunicate:NETWork:[IPAddress]:SUBNet:MASK
driver.system.communicate.network.ipAddress.subnet.set_mask(mask = 'abc')
```

Sets the subnet mask.

param mask
string

6.18.3.3.3 Restart

SCPI Command :

```
SYSTem:COMMunicate:NETWork:REStArt
```

class RestartCls

Restart commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:COMMunicate:NETWork:REStart
driver.system.communicate.network.restart.set()
```

Restarts the network.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:COMMunicate:NETWork:REStart
driver.system.communicate.network.restart.set_with_opc()
```

Restarts the network.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.18.3.4 Rt

class RtCls

Rt commands group definition. 8 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.communicate.rt.clone()
```

Subgroups

6.18.3.4.1 Network

SCPI Commands :

```
SYSTem:COMMunicate:RT:NETWork:MACaddress
SYSTem:COMMunicate:RT:NETWork:STATus
```

class NetworkCls

Network commands group definition. 8 total commands, 3 Subgroups, 2 group commands

get_mac_address() → str

```
# SCPI: SYSTem:COMMunicate:RT:NETWork:MACaddress
value: str = driver.system.communicate.rt.network.get_mac_address()
```

Queries the MAC address of the instrument connected to the R&S AREG800A via the realtime control interface.

return

zynq_mac_address: string

get_status() → bool

```
# SCPI: SYSTem:COMMunicate:RT:NETWork:STATus
value: bool = driver.system.communicate.rt.network.get_status()
```

Queries the network configuration state.

```
return
    zynq_net_status: 1| ON| 0| OFF
```

set_mac_address(zynq_mac_address: str) → None

```
# SCPI: SYSTem:COMMunicate:RT:NETWork:MACaddress
driver.system.communicate.rt.network.set_mac_address(zynq_mac_address = 'abc')
```

Queries the MAC address of the instrument connected to the R&S AREG800A via the realtime control interface.

```
param zynq_mac_address
    string
```

set_status(zynq_net_status: bool) → None

```
# SCPI: SYSTem:COMMunicate:RT:NETWork:STATus
driver.system.communicate.rt.network.set_status(zynq_net_status = False)
```

Queries the network configuration state.

```
param zynq_net_status
    1| ON| 0| OFF
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.communicate.rt.network.clone()
```

Subgroups

6.18.3.4.1.1 Common

SCPI Commands :

```
SYSTem:COMMunicate:RT:NETWork:[COMMon]:HOSTname
SYSTem:COMMunicate:RT:NETWork:[COMMon]:WORKgroup
```

class CommonCls

Common commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_hostname() → str

```
# SCPI: SYSTem:COMMunicate:RT:NETWork:[COMMon]:HOSTname
value: str = driver.system.communicate.rt.network.common.get_hostname()
```

Queries the hostname of the instrument connected to the R&S AREG800A via the realtime control interface.

```

return
    zynq_hostname: string

```

get_workgroup() → str

```

# SCPI: SYSTem:COMMunicate:RT:NETWork:[COMMON]:WORKgroup
value: str = driver.system.communicate.rt.network.common.get_workgroup()

```

No command help available

```

return
    zynq_workgroup: No help available

```

set_hostname(zynq_hostname: str) → None

```

# SCPI: SYSTem:COMMunicate:RT:NETWork:[COMMON]:HOSTName
driver.system.communicate.rt.network.common.set_hostname(zynq_hostname = 'abc')

```

Queries the hostname of the instrument connected to the R&S AREG800A via the realtime control interface.

```

param zynq_hostname
    string

```

set_workgroup(zynq_workgroup: str) → None

```

# SCPI: SYSTem:COMMunicate:RT:NETWork:[COMMON]:WORKgroup
driver.system.communicate.rt.network.common.set_workgroup(zynq_workgroup = 'abc
↪ ')

```

No command help available

```

param zynq_workgroup
    No help available

```

6.18.3.4.1.2 IpAddress

SCPI Commands :

```

SYSTem:COMMunicate:RT:NETWork:IPAddress:MODE
SYSTem:COMMunicate:RT:NETWork:IPAddress

```

class IpAddressCls

IpAddress commands group definition. 3 total commands, 1 Subgroups, 2 group commands

get_mode() → NetMode

```

# SCPI: SYSTem:COMMunicate:RT:NETWork:IPAddress:MODE
value: enums.NetMode = driver.system.communicate.rt.network.ipAddress.get_mode()

```

Selects manual or automatic setting of the IP address.

```

return
    zynq_mode: AUTO|STATIC

```

get_value() → bytes

```
# SCPI: SYSTem:COMMunicate:RT:NETWork:IPAdDress
value: bytes = driver.system.communicate.rt.network.ipAddress.get_value()
```

Sets the IP address.

```
return
areg_zynq_net_ip_address: No help available
```

set_mode(zynq_mode: NetMode) → None

```
# SCPI: SYSTem:COMMunicate:RT:NETWork:IPAdDress:MODE
driver.system.communicate.rt.network.ipAddress.set_mode(zynq_mode = enums.
↳ NetMode.AUTO)
```

Selects manual or automatic setting of the IP address.

```
param zynq_mode
    AUTO|STATic
```

set_value(areg_zynq_net_ip_address: bytes) → None

```
# SCPI: SYSTem:COMMunicate:RT:NETWork:IPAdDress
driver.system.communicate.rt.network.ipAddress.set_value(areg_zynq_net_ip_
↳ address = b'ABCDEFGH')
```

Sets the IP address.

```
param areg_zynq_net_ip_address
    No help available
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.communicate.rt.network.ipAddress.clone()
```

Subgroups

6.18.3.4.1.3 Subnet

SCPI Command :

```
SYSTem:COMMunicate:RT:NETWork:[IPAdDress]:SUBNet:MASK
```

class SubnetCls

Subnet commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_mask() → bytes

```
# SCPI: SYSTem:COMMunicate:RT:NETWork:[IPAdDress]:SUBNet:MASK
value: bytes = driver.system.communicate.rt.network.ipAddress.subnet.get_mask()
```

Sets the subnet mask.

```
    return
    areg_zynq_net_sub_net_mask: No help available

set_mask(areg_zynq_net_sub_net_mask: bytes) → None
```

```
# SCPI: SYSTem:COMMunicate:RT:NETWork:[IPAddress]:SUBNet:MASK
driver.system.communicate.rt.network.ipAddress.subnet.set_mask(areg_zynq_net_
↳sub_net_mask = b'ABCDEFGH')
```

Sets the subnet mask.

```
param areg_zynq_net_sub_net_mask
    No help available
```

6.18.3.4.1.4 Restart

SCPI Command :

```
SYSTem:COMMunicate:RT:NETWork:REStart
```

class RestartCls

Restart commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:COMMunicate:RT:NETWork:REStart
driver.system.communicate.rt.network.restart.set()
```

Restarts the network.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:COMMunicate:RT:NETWork:REStart
driver.system.communicate.rt.network.restart.set_with_opc()
```

Restarts the network.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

```
param opc_timeout_ms
    Maximum time to wait in milliseconds, valid only for this call.
```

6.18.3.5 Scpi

class ScpiCls

Scpi commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.communicate.scpi.clone()
```

Subgroups

6.18.3.5.1 Ethernet

SCPI Command :

```
SYSTem:COMMunicate:SCPI:ETHernet:[ACTive]
```

class EthernetCls

Ethernet commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_active() → str

```
# SCPI: SYSTem:COMMunicate:SCPI:ETHernet:[ACTive]
value: str = driver.system.communicate.scpi.ethernet.get_active()
```

No command help available

```
return
    active_connection: No help available
```

6.18.3.6 Serial

SCPI Commands :

```
SYSTem:COMMunicate:SERial:BAUD
SYSTem:COMMunicate:SERial:PARity
SYSTem:COMMunicate:SERial:RESource
SYSTem:COMMunicate:SERial:SBITs
```

class SerialCls

Serial commands group definition. 4 total commands, 0 Subgroups, 4 group commands

get_baud() → Rs232BdRate

```
# SCPI: SYSTem:COMMunicate:SERial:BAUD
value: enums.Rs232BdRate = driver.system.communicate.serial.get_baud()
```

Defines the baudrate for the serial remote control interface.

```
return
    baud: 2400| 4800| 9600| 19200| 38400| 57600| 115200
```

get_parity() → Parity

```
# SCPI: SYSTem:COMMunicate:SERial:PARity
value: enums.Parity = driver.system.communicate.serial.get_parity()
```

Enters the parity for the serial remote control interface.

return
parity: NONE| ODD| EVEN

get_resource() → str

```
# SCPI: SYSTem:COMMunicate:SERIal:RESource
value: str = driver.system.communicate.serial.get_resource()
```

Queries the visa resource string for the serial remote control interface. This string is used for remote control of the instrument.

return
resource: string

get_sbits() → Rs232StopBits

```
# SCPI: SYSTem:COMMunicate:SERIal:SBITS
value: enums.Rs232StopBits = driver.system.communicate.serial.get_sbits()
```

Defines the number of stop bits for the serial remote control interface.

return
sbits: 1| 2

set_baud(baud: Rs232BdRate) → None

```
# SCPI: SYSTem:COMMunicate:SERIal:BAUD
driver.system.communicate.serial.set_baud(baud = enums.Rs232BdRate._115200)
```

Defines the baudrate for the serial remote control interface.

param baud
2400| 4800| 9600| 19200| 38400| 57600| 115200

set_parity(parity: Parity) → None

```
# SCPI: SYSTem:COMMunicate:SERIal:PARity
driver.system.communicate.serial.set_parity(parity = enums.Parity.EVEN)
```

Enters the parity for the serial remote control interface.

param parity
NONE| ODD| EVEN

set_sbits(sbits: Rs232StopBits) → None

```
# SCPI: SYSTem:COMMunicate:SERIal:SBITS
driver.system.communicate.serial.set_sbits(sbits = enums.Rs232StopBits._1)
```

Defines the number of stop bits for the serial remote control interface.

param sbits
1| 2

6.18.3.7 Socket

SCPI Command :

```
SYSTem:COMMunicate:SOCKet:RESource
```

class SocketCls

Socket commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_resource() → str

```
# SCPI: SYSTem:COMMunicate:SOCKet:RESource
value: str = driver.system.communicate.socket.get_resource()
```

Queries the visa resource string for remote control via LAN interface, using TCP/IP socket protocol.

```
return
resource: string
```

6.18.3.8 Syst

class SystCls

Syst commands group definition. 8 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.communicate.syst.clone()
```

Subgroups

6.18.3.8.1 Network

SCPI Commands :

```
SYSTem:COMMunicate:SYST:NETWork:MACaddress
SYSTem:COMMunicate:SYST:NETWork:STATus
```

class NetworkCls

Network commands group definition. 8 total commands, 3 Subgroups, 2 group commands

get_mac_address() → str

```
# SCPI: SYSTem:COMMunicate:SYST:NETWork:MACaddress
value: str = driver.system.communicate.syst.network.get_mac_address()
```

Queries the MAC address of the instrument connected to the R&S AREG800A via the system control interface.

```
return
zynq_mac_address: string
```

get_status() → bool

```
# SCPI: SYSTem:COMMunicate:SYST:NETWork:STATus
value: bool = driver.system.communicate.syst.network.get_status()
```

Queries the network configuration state.

```
return
    zynq_net_status: 1| ON| 0| OFF
```

set_mac_address(zynq_mac_address: str) → None

```
# SCPI: SYSTem:COMMunicate:SYST:NETWork:MACaddress
driver.system.communicate.syst.network.set_mac_address(zynq_mac_address = 'abc')
```

Queries the MAC address of the instrument connected to the R&S AREG800A via the system control interface.

```
param zynq_mac_address
    string
```

set_status(zynq_net_status: bool) → None

```
# SCPI: SYSTem:COMMunicate:SYST:NETWork:STATus
driver.system.communicate.syst.network.set_status(zynq_net_status = False)
```

Queries the network configuration state.

```
param zynq_net_status
    1| ON| 0| OFF
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.communicate.syst.network.clone()
```

Subgroups

6.18.3.8.1.1 Common

SCPI Commands :

```
SYSTem:COMMunicate:SYST:NETWork:[COMMON]:HOSTname
SYSTem:COMMunicate:SYST:NETWork:[COMMON]:WORKgroup
```

class CommonCls

Common commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_hostname() → str

```
# SCPI: SYSTem:COMMunicate:SYST:NETWork:[COMMON]:HOSTname
value: str = driver.system.communicate.syst.network.common.get_hostname()
```

Queries the hostname of the instrument connected to the R&S AREG800A via the system control interface.


```

    return
    zynq_hostname: string
get_workgroup() → str

```

```

# SCPI: SYSTem:COMMunicate:SYST:NETWork:[COMMON]:WORKgroup
value: str = driver.system.communicate.syst.network.common.get_workgroup()

```

No command help available

```

    return
    zynq_workgroup: No help available
set_hostname(zynq_hostname: str) → None

```

```

# SCPI: SYSTem:COMMunicate:SYST:NETWork:[COMMON]:HOSTname
driver.system.communicate.syst.network.common.set_hostname(zynq_hostname = 'abc
↪')

```

Queries the hostname of the instrument connected to the R&S AREG800A via the system control interface.

```

    param zynq_hostname
    string
set_workgroup(zynq_workgroup: str) → None

```

```

# SCPI: SYSTem:COMMunicate:SYST:NETWork:[COMMON]:WORKgroup
driver.system.communicate.syst.network.common.set_workgroup(zynq_workgroup =
↪'abc')

```

No command help available

```

    param zynq_workgroup
    No help available

```

6.18.3.8.1.2 IpAddress

SCPI Commands :

```

SYSTem:COMMunicate:SYST:NETWork:IPAddress:MODE
SYSTem:COMMunicate:SYST:NETWork:IPAddress

```

class IpAddressCls

IpAddress commands group definition. 3 total commands, 1 Subgroups, 2 group commands

```
get_mode() → NetMode
```

```

# SCPI: SYSTem:COMMunicate:SYST:NETWork:IPAddress:MODE
value: enums.NetMode = driver.system.communicate.syst.network.ipAddress.get_
↪mode()

```

Selects manual or automatic setting of the IP address.

```

    return
    zynq_mode: AUTO|STAtic

```

get_value() → bytes

```
# SCPI: SYSTem:COMMunicate:SYST:NETWork:IPAddress
value: bytes = driver.system.communicate.syst.network.ipAddress.get_value()
```

Sets the IP address.

```
return
areg_zynq_net_ip_address: No help available
```

set_mode(zynq_mode: NetMode) → None

```
# SCPI: SYSTem:COMMunicate:SYST:NETWork:IPAddress:MODE
driver.system.communicate.syst.network.ipAddress.set_mode(zynq_mode = enums.
↳ NetMode.AUTO)
```

Selects manual or automatic setting of the IP address.

```
param zynq_mode
    AUTO|STATic
```

set_value(areg_zynq_net_ip_address: bytes) → None

```
# SCPI: SYSTem:COMMunicate:SYST:NETWork:IPAddress
driver.system.communicate.syst.network.ipAddress.set_value(areg_zynq_net_ip_
↳ address = b'ABCDEFGH')
```

Sets the IP address.

```
param areg_zynq_net_ip_address
    No help available
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.communicate.syst.network.ipAddress.clone()
```

Subgroups

6.18.3.8.1.3 Subnet

SCPI Command :

```
SYSTem:COMMunicate:SYST:NETWork:[IPAddress]:SUBNet:MASK
```

class SubnetCls

Subnet commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_mask() → bytes

```
# SCPI: SYSTem:COMMunicate:SYST:NETWork:[IPAddress]:SUBNet:MASK
value: bytes = driver.system.communicate.syst.network.ipAddress.subnet.get_
↳ mask()
```

Sets the subnet mask.

```

return
    areg_zynq_net_sub_net_mask: No help available

```

set_mask(*areg_zynq_net_sub_net_mask: bytes*) → None

```

# SCPI: SYSTem:COMMunicate:SYST:NETWork:[IPAddress]:SUBNet:MASK
driver.system.communicate.syst.network.ipAddress.subnet.set_mask(areg_zynq_net_
↳sub_net_mask = b'ABCDEFGH')

```

Sets the subnet mask.

```

param areg_zynq_net_sub_net_mask
    No help available

```

6.18.3.8.1.4 Restart

SCPI Command :

```
SYSTEM:COMMunicate:SYST:NETWork:REStart
```

class RestartCls

Restart commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```

# SCPI: SYSTem:COMMunicate:SYST:NETWork:REStart
driver.system.communicate.syst.network.restart.set()

```

Restarts the network.

set_with_opc(*opc_timeout_ms: int = -1*) → None

```

# SCPI: SYSTem:COMMunicate:SYST:NETWork:REStart
driver.system.communicate.syst.network.restart.set_with_opc()

```

Restarts the network.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

```

param opc_timeout_ms
    Maximum time to wait in milliseconds, valid only for this call.

```

6.18.3.9 Usb

SCPI Command :

```
SYSTEM:COMMunicate:USB:RESource
```

class UsbCls

Usb commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_resource() → str

```
# SCPI: SYSTem:COMMunicate:USB:RESource
value: str = driver.system.communicate.usb.get_resource()
```

Queries the visa resource string for remote control via the USB interface.

return
resource: string

6.18.4 Date

SCPI Commands :

```
SYSTem:DATE
SYSTem:DATE:LOCal
SYSTem:DATE:UTC
```

class DateCls

Date commands group definition. 3 total commands, 0 Subgroups, 3 group commands

class DateStruct

Response structure. Fields:

- Year: List[int]: integer
- Month: int: integer Range: 1 to 12
- Day: int: integer Range: 1 to 31

get() → DateStruct

```
# SCPI: SYSTem:DATE
value: DateStruct = driver.system.date.get()
```

Queries or sets the date for the instrument-internal calendar. This is a password-protected function. Unlock the protection level 1 to access it. See method RsAreg800.System.Protect.State.set.

return
structure: for return value, see the help for DateStruct structure arguments.

get_local() → str

```
# SCPI: SYSTem:DATE:LOCal
value: str = driver.system.date.get_local()
```

No command help available

return
pseudo_string: No help available

get_utc() → str

```
# SCPI: SYSTem:DATE:UTC
value: str = driver.system.date.get_utc()
```

No command help available

return

pseudo_string: No help available

set(year: List[int], month: int, day: int) → None

```
# SCPI: SYSTem:DATE
driver.system.date.set(year = [1, 2, 3], month = 1, day = 1)
```

Queries or sets the date for the instrument-internal calendar. This is a password-protected function. Unlock the protection level 1 to access it. See method RsAreg800.System.Protect.State.set.

param year

integer

param month

integer Range: 1 to 12

param day

integer Range: 1 to 31

set_local(pseudo_string: str) → None

```
# SCPI: SYSTem:DATE:LOCaL
driver.system.date.set_local(pseudo_string = 'abc')
```

No command help available

param pseudo_string

No help available

set_utc(pseudo_string: str) → None

```
# SCPI: SYSTem:DATE:UTC
driver.system.date.set_utc(pseudo_string = 'abc')
```

No command help available

param pseudo_string

No help available

6.18.5 Device

SCPI Command :

```
SYSTem:DEVIce:ID
```

class DeviceCls

Device commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_id() → str

```
# SCPI: SYSTem:DEVIce:ID
value: str = driver.system.device.get_id()
```

No command help available

return

pseudo_string: No help available

6.18.6 DeviceFootprint

SCPI Command :

```
SYSTem:DFPRint
```

class DeviceFootprintCls

DeviceFootprint commands group definition. 3 total commands, 1 Subgroups, 1 group commands

get() → str

```
# SCPI: SYSTem:DFPRint
value: str = driver.system.deviceFootprint.get()
```

Queries the device footprint of the instrument. The retrieved information is in machine-readable form suitable for automatic further processing.

return

device_footprint: string Information on the instrument type, device identification and details on the installed FW version, hardware and software options.

set(directory: str) → None

```
# SCPI: SYSTem:DFPRint
driver.system.deviceFootprint.set(directory = 'abc')
```

Queries the device footprint of the instrument. The retrieved information is in machine-readable form suitable for automatic further processing.

param directory

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.deviceFootprint.clone()
```

Subgroups

6.18.6.1 History

SCPI Commands :

```
SYSTem:DFPRint:HISTory:COUNT
SYSTem:DFPRint:HISTory:ENTRY
```

class HistoryCls

History commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_count() → str

```
# SCPI: SYSTem:DFPRint:HISTory:COUNT
value: str = driver.system.deviceFootprint.history.get_count()
```

No command help available

return
pseudo_string: No help available

get_entry() → str

```
# SCPI: SYSTem:DFPPrint:HISTory:ENTry
value: str = driver.system.deviceFootprint.history.get_entry()
```

No command help available

return
pseudo_string: No help available

6.18.7 Dexchange

SCPI Commands :

```
SYSTem:DEXChange:CATalog
SYSTem:DEXChange:DEBug
SYSTem:DEXChange:DELeTe
SYSTem:DEXChange:FORMat
SYSTem:DEXChange:SElect
```

class DexchangeCls

Dexchange commands group definition. 12 total commands, 3 Subgroups, 5 group commands

delete(filename: str) → None

```
# SCPI: SYSTem:DEXChange:DELeTe
driver.system.dexchange.delete(filename = 'abc')
```

No command help available

param filename
No help available

get_catalog() → List[str]

```
# SCPI: SYSTem:DEXChange:CATalog
value: List[str] = driver.system.dexchange.get_catalog()
```

No command help available

return
catalog: No help available

get_debug() → bool

```
# SCPI: SYSTem:DEXChange:DEBug
value: bool = driver.system.dexchange.get_debug()
```

No command help available

return
debug: No help available

get_format_py() → DevExpFormat

```
# SCPI: SYSTem:DEXChange:FORMat
value: enums.DevExpFormat = driver.system.dexchange.get_format_py()
```

No command help available

```
return
    format_py: No help available
```

get_select() → str

```
# SCPI: SYSTem:DEXChange:SElect
value: str = driver.system.dexchange.get_select()
```

No command help available

```
return
    filename: No help available
```

set_debug(debug: bool) → None

```
# SCPI: SYSTem:DEXChange:DEBug
driver.system.dexchange.set_debug(debug = False)
```

No command help available

```
param debug
    No help available
```

set_format_py(format_py: DevExpFormat) → None

```
# SCPI: SYSTem:DEXChange:FORMat
driver.system.dexchange.set_format_py(format_py = enums.DevExpFormat.
↳ CGPREDEFINED)
```

No command help available

```
param format_py
    No help available
```

set_select(filename: str) → None

```
# SCPI: SYSTem:DEXChange:SElect
driver.system.dexchange.set_select(filename = 'abc')
```

No command help available

```
param filename
    No help available
```


Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.dexchange.clone()
```

Subgroups

6.18.7.1 Execute

SCPI Command :

```
SYSTem:DEXChange:EXECute
```

class ExecuteCls

Execute commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:DEXChange:EXECute
driver.system.dexchange.execute.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:DEXChange:EXECute
driver.system.dexchange.execute.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.18.7.2 Template

class TemplateCls

Template commands group definition. 5 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.dexchange.template.clone()
```

Subgroups

6.18.7.2.1 Predefined

SCPI Commands :

```
SYSTEM:DEXChange:TEMPlate:PREDefined:CATalog  
SYSTEM:DEXChange:TEMPlate:PREDefined:SElect
```

class PredefinedCls

Predefined commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_catalog() → List[str]

```
# SCPI: SYSTem:DEXChange:TEMPlate:PREDefined:CATalog  
value: List[str] = driver.system.dexchange.template.predefined.get_catalog()
```

No command help available

return
catalog: No help available

get_select() → str

```
# SCPI: SYSTem:DEXChange:TEMPlate:PREDefined:SElect  
value: str = driver.system.dexchange.template.predefined.get_select()
```

No command help available

return
filename: No help available

set_select(filename: str) → None

```
# SCPI: SYSTem:DEXChange:TEMPlate:PREDefined:SElect  
driver.system.dexchange.template.predefined.set_select(filename = 'abc')
```

No command help available

param filename
No help available

6.18.7.2.2 User

SCPI Commands :

```
SYSTEM:DEXChange:TEMPlate:USER:CATalog  
SYSTEM:DEXChange:TEMPlate:USER:DElete  
SYSTEM:DEXChange:TEMPlate:USER:SElect
```

class UserCls

User commands group definition. 3 total commands, 0 Subgroups, 3 group commands

delete(filename: str) → None

```
# SCPI: SYSTem:DEXChange:TEMPlate:USER:DELeTe
driver.system.dexchange.template.user.delete(filename = 'abc')
```

No command help available

param filename
No help available

get_catalog() → List[str]

```
# SCPI: SYSTem:DEXChange:TEMPlate:USER:CATalog
value: List[str] = driver.system.dexchange.template.user.get_catalog()
```

No command help available

return
catalog: No help available

get_select() → str

```
# SCPI: SYSTem:DEXChange:TEMPlate:USER:SELeCt
value: str = driver.system.dexchange.template.user.get_select()
```

No command help available

return
filename: No help available

set_select(filename: str) → None

```
# SCPI: SYSTem:DEXChange:TEMPlate:USER:SELeCt
driver.system.dexchange.template.user.set_select(filename = 'abc')
```

No command help available

param filename
No help available

6.18.7.3 Transaction

SCPI Command :

```
SYSTem:DEXChange:TRANsaction:STATe
```

class TransactionCls

Transaction commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:DEXChange:TRANsaction:STATe
value: bool = driver.system.dexchange.transaction.get_state()
```

No command help available

return

state: No help available

set_state(state: bool) → None

```
# SCPI: SYSTem:DEXChange:TRANsaction:STATe
driver.system.dexchange.transaction.set_state(state = False)
```

No command help available

param state

No help available

6.18.8 Error

SCPI Commands :

```
SYSTem:ERRor:ALL
SYSTem:ERRor:COUNt
SYSTem:ERRor:STATic
```

class ErrorCls

Error commands group definition. 7 total commands, 2 Subgroups, 3 group commands

get_all() → str

```
# SCPI: SYSTem:ERRor:ALL
value: str = driver.system.error.get_all()
```

Queries the error/event queue for all unread items and removes them from the queue.

return

all_py: string Error/event_number,'Error/event_description[:Device-dependent info]'

A comma separated list of error number and a short description of the error in FIFO order. If the queue is empty, the response is 0,'No error' Positive error numbers are instrument-dependent. Negative error numbers are reserved by the SCPI standard. Volatile errors are reported once, at the time they appear. Identical errors are reported repeatedly only if the original error has already been retrieved from (and hence not any more present in) the error queue.

get_count() → str

```
# SCPI: SYSTem:ERRor:COUNt
value: str = driver.system.error.get_count()
```

Queries the number of entries in the error queue.

return

count: integer 0 The error queue is empty.

get_static() → str

```
# SCPI: SYSTem:ERRor:STATic
value: str = driver.system.error.get_static()
```

Returns a list of all errors existing at the time when the query is started. This list corresponds to the display on the info page under manual control.

```
return
    static_errors: string
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.error.clone()
```

Subgroups

6.18.8.1 Code

SCPI Commands :

```
SYSTem:ERRor:CODE:ALL
SYSTem:ERRor:CODE:[NEXT]
```

class CodeCls

Code commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_all() → str

```
# SCPI: SYSTem:ERRor:CODE:ALL
value: str = driver.system.error.code.get_all()
```

Queries the error numbers of all entries in the error queue and then deletes them.

```
return
    all_py: string Returns the error numbers. To retrieve the entire error text, send the
    command method RsAreg800.System.Error.all. 0 'No error', i.e. the error queue is
    empty Positive value Positive error numbers denote device-specific errors Negative
    value Negative error numbers denote error messages defined by SCPI.
```

get_next() → str

```
# SCPI: SYSTem:ERRor:CODE:[NEXT]
value: str = driver.system.error.code.get_next()
```

Queries the error number of the oldest entry in the error queue and then deletes it.

```
return
    next_py: string Returns the error number. To retrieve the entire error text, send the
    command method RsAreg800.System.Error.all. 0 'No error', i.e. the error queue is
    empty Positive value Positive error numbers denote device-specific errors Negative
    value Negative error numbers denote error messages defined by SCPI.
```

6.18.8.2 History

SCPI Commands :

```
SYSTem:ERRor:HISTory:CLEar
SYSTem:ERRor:HISTory
```

class HistoryCls

History commands group definition. 2 total commands, 0 Subgroups, 2 group commands

clear() → None

```
# SCPI: SYSTem:ERRor:HISTory:CLEar
driver.system.error.history.clear()
```

Clears the error history.

clear_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:ERRor:HISTory:CLEar
driver.system.error.history.clear_with_opc()
```

Clears the error history.

Same as clear, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

get_value() → str

```
# SCPI: SYSTem:ERRor:HISTory
value: str = driver.system.error.history.get_value()
```

No command help available

return

error_history: No help available

6.18.9 ExtDevices

class ExtDevicesCls

ExtDevices commands group definition. 5 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.extDevices.clone()
```

Subgroups

6.18.9.1 Update

SCPI Command :

```
SYSTem:EXTDevices:UPDate
```

class UpdateCls

Update commands group definition. 5 total commands, 3 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:EXTDevices:UPDate
driver.system.extDevices.update.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:EXTDevices:UPDate
driver.system.extDevices.update.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.extDevices.update.clone()
```

Subgroups

6.18.9.1.1 Check

SCPI Command :

```
SYSTem:EXTDevices:UPDate:CHECK
```

class CheckCls

Check commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:EXTDevices:UPDate:CHECK
driver.system.extDevices.update.check.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:EXTDevices:UPDate:CHECK
driver.system.extDevices.update.check.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.18.9.1.2 Needed**SCPI Command :**

```
SYSTem:EXTDevices:UPDate:NEEDed:[STATe]
```

class NeededCls

Needed commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:EXTDevices:UPDate:NEEDed:[STATe]
value: bool = driver.system.extDevices.update.needed.get_state()
```

No command help available

return

update_needed: No help available

6.18.9.1.3 Tselected**SCPI Commands :**

```
SYSTem:EXTDevices:UPDate:TSElected:CATalog
SYSTem:EXTDevices:UPDate:TSElected:STEP
```

class TselectedCls

Tselected commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_catalog() → str

```
# SCPI: SYSTem:EXTDevices:UPDate:TSElected:CATalog
value: str = driver.system.extDevices.update.tselected.get_catalog()
```

No command help available

```
return
    catalog: No help available
```

get_step() → str

```
# SCPI: SYSTem:EXTDevices:UPDate:TSElected:STEP
value: str = driver.system.extDevices.update.tselected.get_step()
```

No command help available

```
return
    sel_string: No help available
```

set_step(sel_string: str) → None

```
# SCPI: SYSTem:EXTDevices:UPDate:TSElected:STEP
driver.system.extDevices.update.tselected.set_step(sel_string = 'abc')
```

No command help available

```
param sel_string
    No help available
```

6.18.10 Fpreset

SCPI Command :

SYSTem:FPRreset

class FpresetCls

Fpreset commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:FPRreset
driver.system.fpreset.set()
```

Triggers an instrument reset to the original state of delivery.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:FPRreset
driver.system.fpreset.set_with_opc()
```

Triggers an instrument reset to the original state of delivery.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.18.11 Generic

SCPI Command :

```
SYSTem:GENeric:MSG
```

class GenericCls

Generic commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_msg() → str

```
# SCPI: SYSTem:GENeric:MSG
value: str = driver.system.generic.get_msg()
```

No command help available

return

generic_message: No help available

set_msg(generic_message: str) → None

```
# SCPI: SYSTem:GENeric:MSG
driver.system.generic.set_msg(generic_message = 'abc')
```

No command help available

param generic_message

No help available

6.18.12 Help

SCPI Commands :

```
SYSTem:HELP:EXPort
SYSTem:HELP:HEADers
```

class HelpCls

Help commands group definition. 4 total commands, 1 Subgroups, 2 group commands

export() → None

```
# SCPI: SYSTem:HELP:EXPort
driver.system.help.export()
```

Saves the online help as zip archive in the user directory.

export_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:HELP:EXPort
driver.system.help.export_with_opc()
```

Saves the online help as zip archive in the user directory.

Same as export, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

get_headers() → str

```
# SCPI: SYSTem:HELP:HEADers
value: str = driver.system.help.get_headers()
```

No command help available

return

headers: No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.help.clone()
```

Subgroups

6.18.12.1 Syntax

SCPI Commands :

```
SYSTem:HELP:SYNTAX:ALL
SYSTem:HELP:SYNTAX
```

class SyntaxCls

Syntax commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_all() → str

```
# SCPI: SYSTem:HELP:SYNTAX:ALL
value: str = driver.system.help.syntax.get_all()
```

No command help available

return

pseudo_string: No help available

get_value() → str

```
# SCPI: SYSTem:HELP:SYNTAX
value: str = driver.system.help.syntax.get_value()
```

No command help available

return

pseudo_string: No help available

6.18.13 Identification

SCPI Commands :

```
SYSTem:IDENtification:PRESet
SYSTem:IDENtification
```

class IdentificationCls

Identification commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_value() → IecDevId

```
# SCPI: SYSTem:IDENtification
value: enums.IecDevId = driver.system.identification.get_value()
```

Selects the mode to determine the 'IDN String' and the 'OPT String' for the instrument, selected with command method RsAreg800.System.language. Note: While working in an emulation mode, the R&S AREG800A specific command set is disabled, that is, the SCPI command method RsAreg800.System.Identification.value is discarded.

return

identification: AUTO| USER AUTO Automatically determines the strings. USER User-defined strings can be selected.

preset() → None

```
# SCPI: SYSTem:IDENtification:PRESet
driver.system.identification.preset()
```

Sets the *IDN and *OPT strings in user defined mode to default values.

preset_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:IDENtification:PRESet
driver.system.identification.preset_with_opc()
```

Sets the *IDN and *OPT strings in user defined mode to default values.

Same as preset, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

set_value(identification: IecDevId) → None

```
# SCPI: SYSTem:IDENtification
driver.system.identification.set_value(identification = enums.IecDevId.AUTO)
```

Selects the mode to determine the 'IDN String' and the 'OPT String' for the instrument, selected with command method RsAreg800.System.language. Note: While working in an emulation mode, the R&S AREG800A specific command set is disabled, that is, the SCPI command method RsAreg800.System.Identification.value is discarded.

param identification

AUTO| USER AUTO Automatically determines the strings. USER User-defined strings can be selected.

6.18.14 Information

SCPI Command :

```
SYSTem:INformation:SR
```

class InformationCls

Information commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_sr() → str

```
# SCPI: SYSTem:INformation:SR
value: str = driver.system.information.get_sr()
```

No command help available

```
return
sr_info: No help available
```

set_sr(sr_info: str) → None

```
# SCPI: SYSTem:INformation:SR
driver.system.information.set_sr(sr_info = 'abc')
```

No command help available

```
param sr_info
No help available
```

6.18.15 Linux

class LinuxCls

Linux commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.linux.clone()
```

Subgroups

6.18.15.1 Kernel

SCPI Command :

```
SYSTem:LINux:KERNel:VERSion
```

class KernelCls

Kernel commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_version() → str

```
# SCPI: SYSTem:LINux:KERNel:VERSion
value: str = driver.system.linux.kernel.get_version()
```

No command help available

return
version: No help available

6.18.16 Lock

SCPI Command :

```
SYSTem:LOCK:TIMEout
```

class LockCls

Lock commands group definition. 10 total commands, 5 Subgroups, 1 group commands

get_timeout() → int

```
# SCPI: SYSTem:LOCK:TIMEout
value: int = driver.system.lock.get_timeout()
```

No command help available

return
time_ms: No help available

set_timeout(time_ms: int) → None

```
# SCPI: SYSTem:LOCK:TIMEout
driver.system.lock.set_timeout(time_ms = 1)
```

No command help available

param time_ms
No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.lock.clone()
```

Subgroups

6.18.16.1 Name

SCPI Commands :

```
SYSTem:LOCK:NAME:DETAiled
SYSTem:LOCK:NAME
```

class NameCls

Name commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_detailed() → str

```
# SCPI: SYSTem:LOCK:NAME:DETAiled
value: str = driver.system.lock.name.get_detailed()
```

No command help available

```
return
    details: No help available
```

get_value() → str

```
# SCPI: SYSTem:LOCK:NAME
value: str = driver.system.lock.name.get_value()
```

No command help available

```
return
    name: No help available
```

6.18.16.2 Owner

SCPI Commands :

```
SYSTem:LOCK:OWNer:DETAiled
SYSTem:LOCK:OWNer
```

class OwnerCls

Owner commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_detailed() → str

```
# SCPI: SYSTem:LOCK:OWNer:DETAiled
value: str = driver.system.lock.owner.get_detailed()
```

No command help available

```
return
    details: No help available
```

get_value() → str

```
# SCPI: SYSTem:LOCK:OWNeR
value: str = driver.system.lock.owner.get_value()
```

Queries the sessions that have locked the instrument currently. If an exclusive lock is set, the query returns the owner of this exclusive lock, otherwise it returns NONE.

```
return
    owner: string
```

6.18.16.3 Release

SCPI Commands :

```
SYSTem:LOCK:RELease:ALL
SYSTem:LOCK:RELease
```

class ReleaseCls

Release commands group definition. 2 total commands, 0 Subgroups, 2 group commands

set_all(pseudo_string: str) → None

```
# SCPI: SYSTem:LOCK:RELease:ALL
driver.system.lock.release.set_all(pseudo_string = 'abc')
```

Revokes the exclusive access to the instrument.

```
param pseudo_string
    No help available
```

set_value(pseudo_string: str) → None

```
# SCPI: SYSTem:LOCK:RELease
driver.system.lock.release.set_value(pseudo_string = 'abc')
```

No command help available

```
param pseudo_string
    No help available
```

6.18.16.4 Request

SCPI Command :

```
SYSTem:LOCK:REQuest:[EXCLusive]
```

class RequestCls

Request commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get_exclusive() → int

```
# SCPI: SYSTem:LOCK:REQuest:[EXCLusive]
value: int = driver.system.lock.request.get_exclusive()
```


Queries whether a lock for exclusive access to the instrument via ethernet exists. If successful, the query returns a 1, otherwise 0.

```
return
    success: integer
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.lock.request.clone()
```

Subgroups

6.18.16.4.1 Shared

SCPI Command :

```
SYSTem:LOCK:REQuest:SHARed
```

class SharedCls

Shared commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(name: str, timeout_ms: int) → int

```
# SCPI: SYSTem:LOCK:REQuest:SHARed
value: int = driver.system.lock.request.shared.get(name = 'abc', timeout_ms = 1)
```

No command help available

param name

No help available

param timeout_ms

No help available

return

success: No help available

6.18.16.5 Shared

SCPI Command :

```
SYSTem:LOCK:SHARed:STRing
```

class SharedCls

Shared commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_string() → str

```
# SCPI: SYSTem:LOCK:SHARed:STRing
value: str = driver.system.lock.shared.get_string()
```

No command help available

```
return
    string: No help available
```

6.18.17 MassMemory

class MassMemoryCls

MassMemory commands group definition. 2 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.massMemory.clone()
```

Subgroups

6.18.17.1 Path

SCPI Commands :

```
SYSTem:MMEMory:PATH
SYSTem:MMEMory:PATH:USER
```

class PathCls

Path commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get(*path_type: str*) → str

```
# SCPI: SYSTem:MMEMory:PATH
value: str = driver.system.massMemory.path.get(path_type = 'abc')
```

No command help available

```
    param path_type
        No help available
```

```
    return
        path: No help available
```

get_user() → str

```
# SCPI: SYSTem:MMEMory:PATH:USER
value: str = driver.system.massMemory.path.get_user()
```

Queries the user directory, that means the directory the R&S AREG800A stores user files on.

```
    return
        path_user: string
```

6.18.18 Ntp

SCPI Command :

```
SYSTem:NTP:HOSTname
```

class NtpCls

Ntp commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_hostname() → str

```
# SCPI: SYSTem:NTP:HOSTname
value: str = driver.system.ntp.get_hostname()
```

Sets the address of the NTP server. You can enter the IP address, or the hostname of the time server, or even set up an own vendor zone. See the Internet for more information on NTP.

return
ntp_name: string

set_hostname(ntp_name: str) → None

```
# SCPI: SYSTem:NTP:HOSTname
driver.system.ntp.set_hostname(ntp_name = 'abc')
```

Sets the address of the NTP server. You can enter the IP address, or the hostname of the time server, or even set up an own vendor zone. See the Internet for more information on NTP.

param ntp_name
string

6.18.19 Package

class PackageCls

Package commands group definition. 3 total commands, 3 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.package.clone()
```

Subgroups

6.18.19.1 ChartDisplay

SCPI Command :

```
SYSTem:PACKage:CHARTdisplay:VERSion
```

class ChartDisplayCls

ChartDisplay commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_version() → str

```
# SCPI: SYSTem:PACKage:CHARTdisplay:VERsion
value: str = driver.system.package.chartDisplay.get_version()
```

No command help available

```
return
    version: No help available
```

6.18.19.2 GuiFramework

SCPI Command :

```
SYSTem:PACKage:GUIFramework:VERsion
```

class GuiFrameworkCls

GuiFramework commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_version() → str

```
# SCPI: SYSTem:PACKage:GUIFramework:VERsion
value: str = driver.system.package.guiFramework.get_version()
```

No command help available

```
return
    version: No help available
```

6.18.19.3 Qt

SCPI Command :

```
SYSTem:PACKage:QT:VERsion
```

class QtCls

Qt commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_version() → str

```
# SCPI: SYSTem:PACKage:QT:VERsion
value: str = driver.system.package.qt.get_version()
```

No command help available

```
return
    version: No help available
```

6.18.20 PciFpga

class PciFpgaCls

PciFpga commands group definition. 4 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.pciFpga.clone()
```

Subgroups

6.18.20.1 Update

class UpdateCls

Update commands group definition. 4 total commands, 3 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.pciFpga.update.clone()
```

Subgroups

6.18.20.1.1 Check

SCPI Command :

```
SYSTem:PCIFpga:UPDate:CHECK
```

class CheckCls

Check commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:PCIFpga:UPDate:CHECK
driver.system.pciFpga.update.check.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:PCIFpga:UPDate:CHECK
driver.system.pciFpga.update.check.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.18.20.1.2 Needed

SCPI Command :

```
SYSTem:PCIFpga:UPDate:NEEDed:[STATe]
```

class NeededCls

Needed commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:PCIFpga:UPDate:NEEDed:[STATe]
value: bool = driver.system.pciFpga.update.needed.get_state()
```

No command help available

return

update_needed: No help available

6.18.20.1.3 Tselected

SCPI Commands :

```
SYSTem:PCIFpga:UPDate:TSElected:CATalog
SYSTem:PCIFpga:UPDate:TSElected:STEP
```

class TselectedCls

Tselected commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_catalog() → str

```
# SCPI: SYSTem:PCIFpga:UPDate:TSElected:CATalog
value: str = driver.system.pciFpga.update.tselected.get_catalog()
```

No command help available

return

catalog: No help available

get_step() → str

```
# SCPI: SYSTem:PCIFpga:UPDate:TSElected:STEP
value: str = driver.system.pciFpga.update.tselected.get_step()
```

No command help available

return

sel_string: No help available

set_step(sel_string: str) → None

```
# SCPI: SYSTem:PCIFpga:UPDate:TSElected:STEP
driver.system.pciFpga.update.tselected.set_step(sel_string = 'abc')
```

No command help available

param sel_string
No help available

6.18.21 Profiling

SCPI Command :

SYSTem:PROFiling:STATe

class ProfilingCls

Profiling commands group definition. 18 total commands, 6 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:PROFiling:STATe
value: bool = driver.system.profiling.get_state()
```

No command help available

return
state: No help available

set_state(state: bool) → None

```
# SCPI: SYSTem:PROFiling:STATe
driver.system.profiling.set_state(state = False)
```

No command help available

param state
No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.profiling.clone()
```

Subgroups

6.18.21.1 HwAccess

SCPI Commands :

```
SYSTem:PROFiling:HWACcess:DESCRiption
SYSTem:PROFiling:HWACcess:PDURation
SYSTem:PROFiling:HWACcess:STATe
```

class HwAccessCls

HwAccess commands group definition. 3 total commands, 0 Subgroups, 3 group commands

get_description() → str

```
# SCPI: SYSTem:PROFiling:HWACcess:DESCRiption
value: str = driver.system.profiling.hwAccess.get_description()
```

No command help available

```
return
    description: No help available
```

get_pduration() → int

```
# SCPI: SYSTem:PROFiling:HWACcess:PDURation
value: int = driver.system.profiling.hwAccess.get_pduration()
```

No command help available

```
return
    duration_us: No help available
```

get_state() → bool

```
# SCPI: SYSTem:PROFiling:HWACcess:STATe
value: bool = driver.system.profiling.hwAccess.get_state()
```

No command help available

```
return
    state: No help available
```

set_pduration(duration_us: int) → None

```
# SCPI: SYSTem:PROFiling:HWACcess:PDURation
driver.system.profiling.hwAccess.set_pduration(duration_us = 1)
```

No command help available

```
param duration_us
    No help available
```

set_state(state: bool) → None

```
# SCPI: SYSTem:PROFiling:HWACcess:STATe
driver.system.profiling.hwAccess.set_state(state = False)
```


No command help available

param state

No help available

6.18.21.2 Logging

SCPI Command :

```
SYSTem:PROFiling:LOGGing:STATe
```

class LoggingCls

Logging commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:PROFiling:LOGGing:STATe
value: bool = driver.system.profiling.logging.get_state()
```

No command help available

return

state: No help available

set_state(state: bool) → None

```
# SCPI: SYSTem:PROFiling:LOGGing:STATe
driver.system.profiling.logging.set_state(state = False)
```

No command help available

param state

No help available

6.18.21.3 Module

SCPI Commands :

```
SYSTem:PROFiling:MODule:CATalog
SYSTem:PROFiling:MODule:STATe
```

class ModuleCls

Module commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_catalog() → List[str]

```
# SCPI: SYSTem:PROFiling:MODule:CATalog
value: List[str] = driver.system.profiling.module.get_catalog()
```

No command help available

return

catalog: No help available

get_state() → bool

```
# SCPI: SYSTem:PROFiling:MODule:StAtE
value: bool = driver.system.profiling.module.get_state()
```

No command help available

```
return
    state: No help available
```

set_state(state: bool) → None

```
# SCPI: SYSTem:PROFiling:MODule:StAtE
driver.system.profiling.module.set_state(state = False)
```

No command help available

```
param state
    No help available
```

6.18.21.4 Record

SCPI Commands :

```
SYSTem:PROFiling:RECORD
SYSTem:PROFiling:RECORD:CLEAR
SYSTem:PROFiling:RECORD:IGNORE
SYSTem:PROFiling:RECORD:SAVE
```

class RecordCls

Record commands group definition. 7 total commands, 2 Subgroups, 4 group commands

clear() → None

```
# SCPI: SYSTem:PROFiling:RECORD:CLEAR
driver.system.profiling.record.clear()
```

No command help available

clear_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:PROFiling:RECORD:CLEAR
driver.system.profiling.record.clear_with_opc()
```

No command help available

Same as clear, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

```
param opc_timeout_ms
    Maximum time to wait in milliseconds, valid only for this call.
```

get(index: List[str]) → List[str]

```
# SCPI: SYSTem:PROFiling:RECORD
value: List[str] = driver.system.profiling.record.get(index = ['abc1', 'abc2',
↪ 'abc3'])
```

No command help available

param index

No help available

return

index: No help available

get_ignore() → float

```
# SCPI: SYSTem:PROFiling:RECORD:IGNore
value: float = driver.system.profiling.record.get_ignore()
```

No command help available

return

count: No help available

save(filename: str) → None

```
# SCPI: SYSTem:PROFiling:RECORD:SAVE
driver.system.profiling.record.save(filename = 'abc')
```

No command help available

param filename

No help available

set_ignore(count: float) → None

```
# SCPI: SYSTem:PROFiling:RECORD:IGNore
driver.system.profiling.record.set_ignore(count = 1.0)
```

No command help available

param count

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.profiling.record.clone()
```

Subgroups

6.18.21.4.1 Count

SCPI Commands :

```
SYSTem:PROFiling:RECORD:COUNT:MAX
SYSTem:PROFiling:RECORD:COUNT
```

class CountCls

Count commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_max() → float

```
# SCPI: SYSTem:PROFiling:RECORD:COUNT:MAX
value: float = driver.system.profiling.record.count.get_max()
```

No command help available

```
return
count: No help available
```

get_value() → float

```
# SCPI: SYSTem:PROFiling:RECORD:COUNT
value: float = driver.system.profiling.record.count.get_value()
```

No command help available

```
return
count: No help available
```

set_max(count: float) → None

```
# SCPI: SYSTem:PROFiling:RECORD:COUNT:MAX
driver.system.profiling.record.count.set_max(count = 1.0)
```

No command help available

```
param count
No help available
```

6.18.21.4.2 Wrap

SCPI Command :

```
SYSTem:PROFiling:RECORD:WRAP:STATE
```

class WrapCls

Wrap commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:PROFiling:RECORD:WRAP:STATE
value: bool = driver.system.profiling.record.wrap.get_state()
```

No command help available

```
return
state: No help available
```

set_state(state: bool) → None

```
# SCPI: SYSTem:PROFiling:RECORD:WRAP:STATE
driver.system.profiling.record.wrap.set_state(state = False)
```

No command help available

param state
No help available

6.18.21.5 Tick

SCPI Command :

```
SYSTem:PROFiling:TICK
```

class TickCls

Tick commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get_value() → str

```
# SCPI: SYSTem:PROFiling:TICK
value: str = driver.system.profiling.tick.get_value()
```

No command help available

return
answer: No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.profiling.tick.clone()
```

Subgroups

6.18.21.5.1 Enable

SCPI Command :

```
SYSTem:PROFiling:TICK:ENABle
```

class EnableCls

Enable commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:PROFiling:TICK:ENABle
driver.system.profiling.tick.enable.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:PROFiling:TICK:ENABle
driver.system.profiling.tick.enable.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.18.21.6 Tpoint

SCPI Command :

```
SYSTem:PROFiling:TPOint:REStart
```

class TpointCls

Tpoint commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get_restart() → List[str]

```
# SCPI: SYSTem:PROFiling:TPOint:REStart
value: List[str] = driver.system.profiling.tpoint.get_restart()
```

No command help available

return

module_and_tp: No help available

set_restart(module_and_tp: List[str]) → None

```
# SCPI: SYSTem:PROFiling:TPOint:REStart
driver.system.profiling.tpoint.set_restart(module_and_tp = ['abc1', 'abc2',
↪ 'abc3'])
```

No command help available

param module_and_tp

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.profiling.tpoint.clone()
```

Subgroups

6.18.21.6.1 Catalog

SCPI Command :

```
SYSTem:PROFiling:TPOint:CATalog
```

class CatalogCls

Catalog commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(name: str) → List[str]

```
# SCPI: SYSTem:PROFiling:TPOint:CATalog
value: List[str] = driver.system.profiling.tpoint.catalog.get(name = 'abc')
```

No command help available

param name

No help available

return

value: No help available

6.18.22 Protect<Level>**RepCap Settings**

```
# Range: Nr1 .. Nr16
rc = driver.system.protect.repcap_level_get()
driver.system.protect.repcap_level_set(repcap.Level.Nr1)
```

class ProtectCls

Protect commands group definition. 1 total commands, 1 Subgroups, 0 group commands Repeated Capability: Level, default value after init: Level.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.protect.clone()
```

Subgroups**6.18.22.1 State****SCPI Command :**

```
SYSTem:PROTect<CH>:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(level=Level.Default) → bool

```
# SCPI: SYSTem:PROTect<CH>:[STATe]
value: bool = driver.system.protect.state.get(level = repcap.Level.Default)
```

Activates and deactivates the specified protection level.

param level

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Protect’)

return

state: 1| ON| 0| OFF

set(state: bool, key: int = None, level=Level.Default) → None

```
# SCPI: SYSTem:PROTect<CH>:[STATe]
driver.system.protect.state.set(state = False, key = 1, level = repcap.Level.
↳Default)
```

Activates and deactivates the specified protection level.

param state

1| ON| 0| OFF

param key

integer The respective functions are disabled when the protection level is activated. No password is required for activation of a level. A password must be entered to deactivate the protection level. The default password for the first level is 123456. This protection level is required to unlock internal adjustments for example.

param level

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Protect’)

6.18.23 Reboot

SCPI Command :

```
SYSTem:REBoot
```

class RebootCls

Reboot commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:REBoot
driver.system.reboot.set()
```

Reboots the instrument including the operating system.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:REBoot
driver.system.reboot.set_with_opc()
```

Reboots the instrument including the operating system.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.18.24 Restart

SCPI Command :

```
SYSTem:REStart
```

class RestartCls

Restart commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:REStart
driver.system.restart.set()
```

Restarts the instrument without restarting the operating system.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:REStart
driver.system.restart.set_with_opc()
```

Restarts the instrument without restarting the operating system.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.18.25 Scrpt

SCPI Commands :

```
SYSTem:SCRpt:ARG
SYSTem:SCRpt:CMD
SYSTem:SCRpt:DATA
SYSTem:SCRpt:RUN
```

class ScrptCls

Scrpt commands group definition. 5 total commands, 1 Subgroups, 4 group commands

get_arg() → str

```
# SCPI: SYSTem:SCRpt:ARG
value: str = driver.system.scrpt.get_arg()
```

No command help available

return

arguments: No help available

get_cmd() → str

```
# SCPI: SYSTem:SCRpt:CMD
value: str = driver.system.scrpt.get_cmd()
```

No command help available

return
cmd_file: No help available

get_data() → str

```
# SCPI: SYSTem:SCRPt:DATA
value: str = driver.system.scrpt.get_data()
```

No command help available

return
data_file: No help available

run() → None

```
# SCPI: SYSTem:SCRPt:RUN
driver.system.scrpt.run()
```

No command help available

run_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:SCRPt:RUN
driver.system.scrpt.run_with_opc()
```

No command help available

Same as run, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms
Maximum time to wait in milliseconds, valid only for this call.

set_arg(arguments: str) → None

```
# SCPI: SYSTem:SCRPt:ARG
driver.system.scrpt.set_arg(arguments = 'abc')
```

No command help available

param arguments
No help available

set_cmd(cmd_file: str) → None

```
# SCPI: SYSTem:SCRPt:CMD
driver.system.scrpt.set_cmd(cmd_file = 'abc')
```

No command help available

param cmd_file
No help available

set_data(data_file: str) → None

```
# SCPI: SYSTem:SCRPt:DATA
driver.system.scrpt.set_data(data_file = 'abc')
```

No command help available

param data_file

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.scrpt.clone()
```

Subgroups

6.18.25.1 Discard

SCPI Command :

```
SYSTem:SCRpt:DISCard
```

class DiscardCls

Discard commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:SCRpt:DISCard
driver.system.scrpt.discard.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:SCRpt:DISCard
driver.system.scrpt.discard.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.18.26 Security

SCPI Command :

```
SYSTem:SECurity:[STAtE]
```

class SecurityCls

Security commands group definition. 18 total commands, 6 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:SECurity:[STAtE]
value: bool = driver.system.security.get_state()
```

No command help available

```
return
state: No help available
```

set_state(state: bool) → None

```
# SCPI: SYSTem:SECurity:[STAtE]
driver.system.security.set_state(state = False)
```

No command help available

```
param state
No help available
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.clone()
```

Subgroups

6.18.26.1 Mmem

class MmemCls

Mmem commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.mmem.clone()
```

Subgroups

6.18.26.1.1 Protect

class ProtectCls

Protect commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.mmem.protect.clone()
```

Subgroups

6.18.26.1.1.1 State

SCPI Command :

```
SYSTem:SECurity:MMEM:PROTect:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:MMEM:PROTect:[STATe]
value: bool = driver.system.security.mmem.protect.state.get()
```

No command help available

```
return
    mmem_prot_state: No help available
```

set(sec_pass_word: str, mmem_prot_state: bool) → None

```
# SCPI: SYSTem:SECurity:MMEM:PROTect:[STATe]
driver.system.security.mmem.protect.state.set(sec_pass_word = 'abc', mmem_prot_
↪state = False)
```

No command help available

```
param sec_pass_word
    No help available
```

```
param mmem_prot_state
    No help available
```

6.18.26.2 Network

class NetworkCls

Network commands group definition. 12 total commands, 12 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.clone()
```

Subgroups

6.18.26.2.1 Avahi

class AvahiCls

Avahi commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.avahi.clone()
```

Subgroups

6.18.26.2.1.1 State

SCPI Command :

```
SYSTem:SECurity:NETWork:AVAHi:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:NETWork:AVAHi:[STATe]
value: bool = driver.system.security.network.avahi.state.get()
```

Disables the Avahi service for automatic configuration of the instrument in a network.

```
return
    avahi_state: 1| ON| 0| OFF
```

set(sec_pass_word: str, avahi_state: bool) → None

```
# SCPI: SYSTem:SECurity:NETWork:AVAHi:[STATe]
driver.system.security.network.avahi.state.set(sec_pass_word = 'abc', avahi_
↪state = False)
```

Disables the Avahi service for automatic configuration of the instrument in a network.

```
param sec_pass_word
    string Current security password.
```

```
param avahi_state
    1| ON| 0| OFF
```

6.18.26.2.2 Ftp

class FtpCls

Ftp commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.ftp.clone()
```

Subgroups

6.18.26.2.2.1 State

SCPI Command :

```
SYSTem:SECurity:NETWork:FTP:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:NETWork:FTP:[STATe]
value: bool = driver.system.security.network.ftp.state.get()
```

Disables FTP protocol for file transfer between the instrument and host.

```
return
    ftp_state: 1| ON| 0| OFF
```

set(sec_pass_word: str, ftp_state: bool) → None

```
# SCPI: SYSTem:SECurity:NETWork:FTP:[STATe]
driver.system.security.network.ftp.state.set(sec_pass_word = 'abc', ftp_state =
False)
```

Disables FTP protocol for file transfer between the instrument and host.

```
param sec_pass_word
    string Current security password.
```

```
param ftp_state
    1| ON| 0| OFF
```

6.18.26.2.3 Http

class HttpCls

Http commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.http.clone()
```

Subgroups

6.18.26.2.3.1 State

SCPI Command :

```
SYSTem:SECurity:NETWork:HTTP:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:NETWork:HTTP:[STATe]
value: bool = driver.system.security.network.http.state.get()
```

Disables control of the instrument over HTTP, the protocol for hypermedia information systems.

return

http_state: 1| ON| 0| OFF

set(sec_pass_word: str, http_state: bool) → None

```
# SCPI: SYSTem:SECurity:NETWork:HTTP:[STATe]
driver.system.security.network.http.state.set(sec_pass_word = 'abc', http_state_
↪= False)
```

Disables control of the instrument over HTTP, the protocol for hypermedia information systems.

param sec_pass_word

string Current security password.

param http_state

1| ON| 0| OFF

6.18.26.2.4 Raw

class RawCls

Raw commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.raw.clone()
```

Subgroups

6.18.26.2.4.1 State

SCPI Command :

```
SYSTem:SECurity:NETWork:RAW:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:NETWork:RAW:[STATe]
value: bool = driver.system.security.network.raw.state.get()
```

Disables the LAN interface for remote control of the instrument over raw socket port.

return
raw_state: 1| ON| 0| OFF

set(sec_pass_word: str, raw_state: bool) → None

```
# SCPI: SYSTem:SECurity:NETWork:RAW:[STATe]
driver.system.security.network.raw.state.set(sec_pass_word = 'abc', raw_state =
False)
```

Disables the LAN interface for remote control of the instrument over raw socket port.

param sec_pass_word
string Current security password.

param raw_state
1| ON| 0| OFF

6.18.26.2.5 RemSupport

SCPI Command :

```
SYSTem:SECurity:NETWork:REMSupport:[STATe]
```

class RemSupportCls

RemSupport commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:SECurity:NETWork:REMSupport:[STATe]
value: bool = driver.system.security.network.remSupport.get_state()
```

Disables communication over SSH (SCP) for service purposes.

```
return
    net_rem_support: 1| ON| 0| OFF
```

set_state(*net_rem_support: bool*) → None

```
# SCPI: SYSTem:SECurity:NETWork:REMSupport:[STATe]
driver.system.security.network.remSupport.set_state(net_rem_support = False)
```

Disables communication over SSH (SCP) for service purposes.

```
param net_rem_support
    1| ON| 0| OFF
```

6.18.26.2.6 Rpc

class RpcCls

Rpc commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.rpc.clone()
```

Subgroups

6.18.26.2.6.1 State

SCPI Command :

```
SYSTem:SECurity:NETWork:RPC:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:NETWork:RPC:[STaTe]
value: bool = driver.system.security.network.rpc.state.get()
```

Enables the LAN interface for remote control of the instrument via remote procedure calls (RPC) .

```
return
    rpc_state: 1| ON| 0| OFF
```

set(sec_pass_word: str, rpc_state: bool) → None

```
# SCPI: SYSTem:SECurity:NETWork:RPC:[STaTe]
driver.system.security.network.rpc.state.set(sec_pass_word = 'abc', rpc_state =
False)
```

Enables the LAN interface for remote control of the instrument via remote procedure calls (RPC) .

```
param sec_pass_word
    string Current security password.

param rpc_state
    1| ON| 0| OFF
```

6.18.26.2.7 Smb

class SmbCls

Smb commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.smb.clone()
```

Subgroups

6.18.26.2.7.1 State

SCPI Command :

```
SYSTem:SECurity:NETWork:SMB:[STaTe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:NETWork:SMB:[STaTe]
value: bool = driver.system.security.network.smb.state.get()
```

Disables access to the file system, printers and serial ports in a network over SMB.

```

    return
        smb_state: 1| ON| 0| OFF

set(sec_pass_word: str, smb_state: bool) → None

```

```

# SCPI: SYSTem:SECurity:NETWork:SMB:[STaTe]
driver.system.security.network.smb.state.set(sec_pass_word = 'abc', smb_state =
↪False)

```

Disables access to the file system, printers and serial ports in a network over SMB.

```

param sec_pass_word
    string Current security password.

param smb_state
    1| ON| 0| OFF

```

6.18.26.2.8 Soe

class SoeCls

Soe commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```

# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.soe.clone()

```

Subgroups

6.18.26.2.8.1 State

SCPI Command :

```
SYSTem:SECurity:NETWork:SOE:[STaTe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

```
get() → bool
```

```

# SCPI: SYSTem:SECurity:NETWork:SOE:[STaTe]
value: bool = driver.system.security.network.soe.state.get()

```

Disables control of the instrument over LAN using SCPI commands.

```

    return
        soe_state: 1| ON| 0| OFF

set(sec_pass_word: str, soe_state: bool) → None

```

```

# SCPI: SYSTem:SECurity:NETWork:SOE:[STaTe]
driver.system.security.network.soe.state.set(sec_pass_word = 'abc', soe_state =
↪False)

```

Disables control of the instrument over LAN using SCPI commands.

```

param sec_pass_word
    string Current security password.

param soe_state
    1| ON| 0| OFF

```

6.18.26.2.9 Ssh

class SshCls

Ssh commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```

# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.ssh.clone()

```

Subgroups

6.18.26.2.9.1 State

SCPI Command :

```
SYSTEM:SECurity:NETWork:SSH:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```

# SCPI: SYSTEM:SECurity:NETWork:SSH:[STATe]
value: bool = driver.system.security.network.ssh.state.get()

```

Disables control of the instrument over LAN using the SSH network protocol.

```

return
    ssh_state: 1| ON| 0| OFF

```

set(sec_pass_word: str, ssh_state: bool) → None

```

# SCPI: SYSTEM:SECurity:NETWork:SSH:[STATe]
driver.system.security.network.ssh.state.set(sec_pass_word = 'abc', ssh_state = False)

```

Disables control of the instrument over LAN using the SSH network protocol.

```

param sec_pass_word
    string Current security password.

param ssh_state
    1| ON| 0| OFF

```

6.18.26.2.10 State

SCPI Command :

SYSTEM:SECurity:NETWork:[STaTe]

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTEM:SECurity:NETWork:[STaTe]
value: bool = driver.system.security.network.state.get()
```

Disables the LAN interface in general, including all services.

```
return
    lan_stor_state: 1| ON| 0| OFF
```

set(sec_pass_word: str, lan_stor_state: bool) → None

```
# SCPI: SYSTEM:SECurity:NETWork:[STaTe]
driver.system.security.network.state.set(sec_pass_word = 'abc', lan_stor_state_
↳ False)
```

Disables the LAN interface in general, including all services.

```
param sec_pass_word
    string Current security password. The default password is 123456.

param lan_stor_state
    1| ON| 0| OFF
```

6.18.26.2.11 SwUpdate

class SwUpdateCls

SwUpdate commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.swUpdate.clone()
```

Subgroups

6.18.26.2.11.1 State

SCPI Command :

```
SYSTem:SECurity:NETWork:SWUpdate:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:NETWork:SWUpdate:[STATe]
value: bool = driver.system.security.network.swUpdate.state.get()
```

Disables software update over LAN.

```
return
    sw_update_state: 1| ON| 0| OFF
```

set(sec_pass_word: str, sw_update_state: bool) → None

```
# SCPI: SYSTem:SECurity:NETWork:SWUpdate:[STATe]
driver.system.security.network.swUpdate.state.set(sec_pass_word = 'abc', sw_
    ↪update_state = False)
```

Disables software update over LAN.

```
param sec_pass_word
    string Current security password.

param sw_update_state
    1| ON| 0| OFF
```

6.18.26.2.12 Vnc

class VncCls

Vnc commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.vnc.clone()
```

Subgroups

6.18.26.2.12.1 State

SCPI Command :

```
SYSTem:SECurity:NETWork:VNC:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:NETWork:VNC:[STATe]
value: bool = driver.system.security.network.vnc.state.get()
```

Disables the VNC interface for remote control of the instrument.

```
return
    vnc_state: 1| ON| 0| OFF
```

set(sec_pass_word: str, vnc_state: bool) → None

```
# SCPI: SYSTem:SECurity:NETWork:VNC:[STATe]
driver.system.security.network.vnc.state.set(sec_pass_word = 'abc', vnc_state =
↪False)
```

Disables the VNC interface for remote control of the instrument.

```
param sec_pass_word
    string Current security password.

param vnc_state
    1| ON| 0| OFF
```

6.18.26.3 Sanitize

class SanitizeCls

Sanitize commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.sanitize.clone()
```


Subgroups

6.18.26.3.1 State

SCPI Command :

```
SYSTem:SECurity:SANitize:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:SANitize:[STATe]
value: bool = driver.system.security.sanitize.state.get()
```

Sanitizes the internal memory.

```
return
    mmem_prot_state: 0| 1| OFF| ON
```

set(sec_pass_word: str, mmem_prot_state: bool) → None

```
# SCPI: SYSTem:SECurity:SANitize:[STATe]
driver.system.security.sanitize.state.set(sec_pass_word = 'abc', mmem_prot_
↳state = False)
```

Sanitizes the internal memory.

```
param sec_pass_word
    string

param mmem_prot_state
    0| 1| OFF| ON
```

6.18.26.4 SuPolicy

SCPI Command :

```
SYSTem:SECurity:SUPolicy
```

class SuPolicyCls

SuPolicy commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → UpdPolicyMode

```
# SCPI: SYSTem:SECurity:SUPolicy
value: enums.UpdPolicyMode = driver.system.security.suPolicy.get()
```

Configures the automatic signature verification for firmware installation.

```
return
    update_policy: STRict| CONFirm| IGNore
```

set(sec_pass_word: str, update_policy: UpdPolicyMode) → None

```
# SCPI: SYSTem:SECurity:SUPolicy
driver.system.security.suPolicy.set(sec_pass_word = 'abc', update_policy =
↳enums.UpdPolicyMode.CONFirm)
```

Configures the automatic signature verification for firmware installation.

```
param sec_pass_word
    string
param update_policy
    STRict| CONFirm| IGNore
```

6.18.26.5 UsbStorage

class UsbStorageCls

UsbStorage commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.usbStorage.clone()
```

Subgroups

6.18.26.5.1 State

SCPI Command :

```
SYSTem:SECurity:USBStorage:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:USBStorage:[STATe]
value: bool = driver.system.security.usbStorage.state.get()
```

No command help available

```
return
    usb_stor_state: No help available
```

set(sec_pass_word: str, usb_stor_state: bool) → None

```
# SCPI: SYSTem:SECurity:USBStorage:[STATe]
driver.system.security.usbStorage.state.set(sec_pass_word = 'abc', usb_stor_
↳state = False)
```

No command help available

param sec_pass_word

No help available

param usb_stor_state

No help available

6.18.26.6 VolMode

class VolModeCls

VolMode commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.volMode.clone()
```

Subgroups

6.18.26.6.1 State

SCPI Command :

```
SYSTem:SECurity:VOLMode:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:VOLMode:[STATe]
value: bool = driver.system.security.volMode.state.get()
```

Activates volatile mode, so that no user data can be written to the internal memory permanently. To enable volatile mode, reboot the instrument. Otherwise the change has no effect.

return

mmem_prot_state: 0| 1| OFF| ON

set(sec_pass_word: str, mmem_prot_state: bool) → None

```
# SCPI: SYSTem:SECurity:VOLMode:[STATe]
driver.system.security.volMode.state.set(sec_pass_word = 'abc', mmem_prot_state_
↪ False)
```

Activates volatile mode, so that no user data can be written to the internal memory permanently. To enable volatile mode, reboot the instrument. Otherwise the change has no effect.

param sec_pass_word

string Current security password The default password is 123456.

param mmem_prot_state

0| 1| OFF| ON

6.18.27 Shutdown

SCPI Command :

```
SYSTem:SHUTdown
```

class ShutdownCls

Shutdown commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:SHUTdown
driver.system.shutdown.set()
```

Shuts down the instrument.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:SHUTdown
driver.system.shutdown.set_with_opc()
```

Shuts down the instrument.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.18.28 SrData

SCPI Commands :

```
SYSTem:SRData:DELeTe
SYSTem:SRData
```

class SrDataCls

SrData commands group definition. 2 total commands, 0 Subgroups, 2 group commands

delete() → None

```
# SCPI: SYSTem:SRData:DELeTe
driver.system.srData.delete()
```

No command help available

delete_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:SRData:DELeTe
driver.system.srData.delete_with_opc()
```

No command help available

Same as delete, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

get_value() → bytes

```
# SCPI: SYSTem:SRData
value: bytes = driver.system.srData.get_value()
```

Queries the SCPI recording data from the internal file. This feature enables you to transfer an instrument configuration to other test environments, as e.g. laboratory virtual instruments.

return

file_data: block data

6.18.29 Srexec

SCPI Command :

```
SYSTem:SREXec
```

class SrexecCls

Srexec commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:SREXec
driver.system.srexec.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:SREXec
driver.system.srexec.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.18.30 Srtime

SCPI Command :

```
SYSTem:SRTIME:STATe
```

class SrtimeCls

Srtime commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:SRTIME:STATE
value: bool = driver.system.srtime.get_state()
```

No command help available

return
state: No help available

set_state(state: bool) → None

```
# SCPI: SYSTem:SRTIME:STATE
driver.system.srtime.set_state(state = False)
```

No command help available

param state
No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.srtime.clone()
```

Subgroups

6.18.30.1 Synchronize

SCPI Command :

```
SYSTem:SRTIME:SYNChronize
```

class SynchronizeCls

Synchronize commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(time: str) → str

```
# SCPI: SYSTem:SRTIME:SYNChronize
value: str = driver.system.srtime.synchronize.get(time = 'abc')
```

No command help available

param time
No help available

return
time: No help available

6.18.31 Startup

SCPI Command :

```
SYSTem:STARtup:COMPLete
```

class StartupCls

Startup commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_complete() → bool

```
# SCPI: SYSTem:STARtup:COMPLete
value: bool = driver.system.startup.get_complete()
```

Queries if the startup of the instrument is completed.

```
return
    complete: 1| ON| 0| OFF
```

6.18.32 Time

SCPI Commands :

```
SYSTem:TIME
SYSTem:TIME:LOCal
SYSTem:TIME:PROTOcol
SYSTem:TIME:UTC
```

class TimeCls

Time commands group definition. 12 total commands, 3 Subgroups, 4 group commands

class TimeStruct

Response structure. Fields:

- Hour: List[int]: integer Range: 0 to 23
- Minute: int: integer Range: 0 to 59
- Second: int: integer Range: 0 to 59

get() → TimeStruct

```
# SCPI: SYSTem:TIME
value: TimeStruct = driver.system.time.get()
```

Queries or sets the time for the instrument-internal clock. This is a password-protected function. Unlock the protection level 1 to access it. See method RsAreg800.System.Protect.State.set.

```
return
    structure: for return value, see the help for TimeStruct structure arguments.
```

get_local() → str

```
# SCPI: SYSTem:TIME:LOCal
value: str = driver.system.time.get_local()
```

No command help available

return

pseudo_string: No help available

get_protocol() → TimeProtocolWithGptp

```
# SCPI: SYSTem:TIME:PROTocol
value: enums.TimeProtocolWithGptp = driver.system.time.get_protocol()
```

Sets the date and time of the operating system.

return

time_protocol: NONE| OFF| 0| NTP| ON| 1| GPTP NONE Sets the date and time according to the selected timezone, see method RsAreg800.System.Time.Zone.catalog and method RsAreg800.System.Time.Zone.value. NTP Sets the date and time derived from the network time protocol. To select the NTP time server, use the commands method RsAreg800.System.Ntp.hostname and SYSTem:NTP:STATe. GPTP Sets the date and time derived from the generic precision time protocol (gPTP) .

get_utc() → str

```
# SCPI: SYSTem:TIME:UTC
value: str = driver.system.time.get_utc()
```

No command help available

return

pseudo_string: No help available

set(hour: List[int], minute: int, second: int) → None

```
# SCPI: SYSTem:TIME
driver.system.time.set(hour = [1, 2, 3], minute = 1, second = 1)
```

Queries or sets the time for the instrument-internal clock. This is a password-protected function. Unlock the protection level 1 to access it. See method RsAreg800.System.Protect.State.set.

param hour

integer Range: 0 to 23

param minute

integer Range: 0 to 59

param second

integer Range: 0 to 59

set_local(pseudo_string: str) → None

```
# SCPI: SYSTem:TIME:LOCaL
driver.system.time.set_local(pseudo_string = 'abc')
```

No command help available

param pseudo_string

No help available

set_protocol(time_protocol: TimeProtocolWithGptp) → None


```
# SCPI: SYSTem:TIME:PROToCol
driver.system.time.set_protocol(time_protocol = enums.TimeProtocolWithGptp._0)
```

Sets the date and time of the operating system.

param time_protocol

NONE| OFF| 0| NTP| ON| 1| GPTP NONE Sets the date and time according to the selected timezone, see method RsAreg800.System.Time.Zone.catalog and method RsAreg800.System.Time.Zone.value. NTP Sets the date and time derived from the network time protocol. To select the NTP time server, use the commands method RsAreg800.System.Ntp.hostname and SYSTem:NTP:STATe. GPTP Sets the date and time derived from the generic precision time protocol (gPTP) .

set_utc(pseudo_string: str) → None

```
# SCPI: SYSTem:TIME:UTC
driver.system.time.set_utc(pseudo_string = 'abc')
```

No command help available

param pseudo_string

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.time.clone()
```

Subgroups

6.18.32.1 DaylightSavingTime

SCPI Command :

```
SYSTem:TIME:DSTime:MODE
```

class DaylightSavingTimeCls

DaylightSavingTime commands group definition. 3 total commands, 1 Subgroups, 1 group commands

get_mode() → str

```
# SCPI: SYSTem:TIME:DSTime:MODE
value: str = driver.system.time.daylightSavingTime.get_mode()
```

No command help available

return

pseudo_string: No help available

set_mode(pseudo_string: str) → None

```
# SCPI: SYSTem:TIME:DSTime:MODE
driver.system.time.daylightSavingTime.set_mode(pseudo_string = 'abc')
```

No command help available

param pseudo_string

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.time.daylightSavingTime.clone()
```

Subgroups

6.18.32.1.1 Rule

SCPI Commands :

```
SYSTem:TIME:DSTime:RULE:CATalog
SYSTem:TIME:DSTime:RULE
```

class RuleCls

Rule commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_catalog() → str

```
# SCPI: SYSTem:TIME:DSTime:RULE:CATalog
value: str = driver.system.time.daylightSavingTime.rule.get_catalog()
```

No command help available

return

pseudo_string: No help available

get_value() → str

```
# SCPI: SYSTem:TIME:DSTime:RULE
value: str = driver.system.time.daylightSavingTime.rule.get_value()
```

No command help available

return

pseudo_string: No help available

set_value(pseudo_string: str) → None

```
# SCPI: SYSTem:TIME:DSTime:RULE
driver.system.time.daylightSavingTime.rule.set_value(pseudo_string = 'abc')
```

No command help available

param pseudo_string

No help available

6.18.32.2 HrTimer

SCPI Command :

```
SYSTem:TIME:HRTimer:RELative
```

class HrTimerCls

HrTimer commands group definition. 3 total commands, 1 Subgroups, 1 group commands

set_relative(pseudo_string: str) → None

```
# SCPI: SYSTem:TIME:HRTimer:RELative
driver.system.time.hrTimer.set_relative(pseudo_string = 'abc')
```

No command help available

param pseudo_string

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.time.hrTimer.clone()
```

Subgroups

6.18.32.2.1 Absolute

SCPI Commands :

```
SYSTem:TIME:HRTimer:ABSolute:SET
SYSTem:TIME:HRTimer:ABSolute
```

class AbsoluteCls

Absolute commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_set() → str

```
# SCPI: SYSTem:TIME:HRTimer:ABSolute:SET
value: str = driver.system.time.hrTimer.absolute.get_set()
```

No command help available

return

pseudo_string: No help available

set_set(pseudo_string: str) → None

```
# SCPI: SYSTem:TIME:HRTimer:ABSolute:SET
driver.system.time.hrTimer.absolute.set_set(pseudo_string = 'abc')
```

No command help available

param pseudo_string

No help available

set_value(pseudo_string: str) → None

```
# SCPI: SYSTem:TIME:HRTimer:ABSolute
driver.system.time.hrTimer.absolute.set_value(pseudo_string = 'abc')
```

No command help available

param pseudo_string

No help available

6.18.32.3 Zone

SCPI Commands :

```
SYSTem:TIME:ZONE:CATalog
SYSTem:TIME:ZONE
```

class ZoneCls

Zone commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_catalog() → List[str]

```
# SCPI: SYSTem:TIME:ZONE:CATalog
value: List[str] = driver.system.time.zone.get_catalog()
```

Querys the list of available timezones.

return

catalog: No help available

get_value() → str

```
# SCPI: SYSTem:TIME:ZONE
value: str = driver.system.time.zone.get_value()
```

Sets the timezone. You can query the list of the available timezones with method RsAreg800.System.Time.Zone.catalog.

return

time_zone: string

set_value(time_zone: str) → None

```
# SCPI: SYSTem:TIME:ZONE
driver.system.time.zone.set_value(time_zone = 'abc')
```

Sets the timezone. You can query the list of the available timezones with method RsAreg800.System.Time.Zone.catalog.

param time_zone

string

6.18.33 Ulock

SCPI Command :

SYSTem:ULOCK

class UlockCls

Ulock commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → DispKeybLockMode

```
# SCPI: SYSTem:ULOCK
value: enums.DispKeybLockMode = driver.system.uunlock.get()
```

Locks or unlocks the user interface of the instrument.

return

mode: ENABLEd| DONLy| DISAbled| TOFF| VNConly ENABLEd Unlocks the display, the touchscreen and all controls for the manual operation. DONLy Locks the touchscreen and controls for the manual operation of the instrument. The display shows the current settings. VNConly Locks the touchscreen and controls for the manual operation, and enables remote operation over VNC. The display shows the current settings. TOFF Locks the touchscreen for the manual operation of the instrument. The display shows the current settings. DISAbled Locks the display, the touchscreen and all controls for the manual operation.

set(sec_pass_word: str, mode: DispKeybLockMode) → None

```
# SCPI: SYSTem:ULOCK
driver.system.uunlock.set(sec_pass_word = 'abc', mode = enums.DispKeybLockMode.
↳DISAbled)
```

Locks or unlocks the user interface of the instrument.

param sec_pass_word

No help available

param mode

ENABLEd| DONLy| DISAbled| TOFF| VNConly ENABLEd Unlocks the display, the touchscreen and all controls for the manual operation. DONLy Locks the touchscreen and controls for the manual operation of the instrument. The display shows the current settings. VNConly Locks the touchscreen and controls for the manual operation, and enables remote operation over VNC. The display shows the current settings. TOFF Locks the touchscreen for the manual operation of the instrument. The display shows the current settings. DISAbled Locks the display, the touchscreen and all controls for the manual operation.

6.18.34 Undo

SCPI Command :

SYSTem:UNDO:STATe

class UndoCls

Undo commands group definition. 5 total commands, 3 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:UNDO:STATe
value: bool = driver.system.undo.get_state()
```

No command help available

return
state: No help available

set_state(state: bool) → None

```
# SCPI: SYSTem:UNDO:STATe
driver.system.undo.set_state(state = False)
```

No command help available

param state
No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.undo.clone()
```

Subgroups

6.18.34.1 Hclear

SCPI Command :

SYSTem:UNDO:HCLear

class HclearCls

Hclear commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:UNDO:HCLear
driver.system.undo.hclear.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:UNDO:HCLear
driver.system.undo.hclear.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.18.34.2 Hid

SCPI Command :

```
SYSTem:UNDO:HID:SElect
```

class HidCls

Hid commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set_select(select: int) → None

```
# SCPI: SYSTem:UNDO:HID:SElect
driver.system.undo.hid.set_select(select = 1)
```

No command help available

param select

No help available

6.18.34.3 Hlable

SCPI Commands :

```
SYSTem:UNDO:HLABLE:CATalog
SYSTem:UNDO:HLABLE:SElect
```

class HlableCls

Hlable commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_catalog() → List[str]

```
# SCPI: SYSTem:UNDO:HLABLE:CATalog
value: List[str] = driver.system.undo.hlable.get_catalog()
```

No command help available

return

catalog: No help available

set_select(label: str) → None

```
# SCPI: SYSTem:UNDO:HLAbLe:SElect
driver.system.undo.hlable.set_select(label = 'abc')
```

No command help available

param label

No help available

6.19 Test

SCPI Commands :

```
TEST:HS
TEST:LEVel
TEST:NRPTriGger
TEST:PRESet
```

class TestCls

Test commands group definition. 21 total commands, 8 Subgroups, 4 group commands

get_hs() → str

```
# SCPI: TEST:HS
value: str = driver.test.get_hs()
```

No command help available

return

arg_test_int_face: No help available

get_level() → SelfLev

```
# SCPI: TEST:LEVel
value: enums.SelfLev = driver.test.get_level()
```

No command help available

return

level: No help available

preset() → None

```
# SCPI: TEST:PRESet
driver.test.preset()
```

No command help available

preset_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: TEST:PRESet
driver.test.preset_with_opc()
```


No command help available

Same as preset, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

set_hs(*areg_test_int_face: str*) → None

```
# SCPI: TEST:HS
driver.test.set_hs(areg_test_int_face = 'abc')
```

No command help available

param areg_test_int_face

No help available

set_level(*level: SelftLev*) → None

```
# SCPI: TEST:LEVel
driver.test.set_level(level = enums.SelftLev.CUSTOMer)
```

No command help available

param level

No help available

set_nrp_trigger(*nrp_trigger: bool*) → None

```
# SCPI: TEST:NRPTriGger
driver.test.set_nrp_trigger(nrp_trigger = False)
```

No command help available

param nrp_trigger

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.test.clone()
```

Subgroups

6.19.1 All

SCPI Commands :

```
TEST<HW>:ALL:RESult
TEST<HW>:ALL:START
```

class AllCls

All commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_result() → Test

```
# SCPI: TEST<HW>:ALL:RESult
value: enums.Test = driver.test.all.get_result()
```

Queries the result of the performed selftest. Start the selftest with method RsAreg800.Test.All.start.

return
result: 0| 1| RUNning| STOPped

start() → None

```
# SCPI: TEST<HW>:ALL:START
driver.test.all.start()
```

No command help available

start_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: TEST<HW>:ALL:START
driver.test.all.start_with_opc()
```

No command help available

Same as start, but waits for the operation to complete before continuing further. Use the RsAreg800.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms
Maximum time to wait in milliseconds, valid only for this call.

6.19.2 Device

class DeviceCls

Device commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.test.device.clone()
```

Subgroups

6.19.2.1 Internal

SCPI Command :

```
TEST:DEvice:INternal
```

class InternalCls

Internal commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*argument: str*) → Test

```
# SCPI: TEST:DEVIce:INTernal
value: enums.Test = driver.test.device.internal.get(argument = 'abc')
```

No command help available

param argument

No help available

return

result: No help available

6.19.3 Pixel

SCPI Commands :

```
TEST:PIXel:COLor
TEST:PIXel:GRADient
TEST:PIXel:POINtsize
TEST:PIXel:RGBA
TEST:PIXel:TEXT
TEST:PIXel:WINDow
```

class PixelCls

Pixel commands group definition. 6 total commands, 0 Subgroups, 6 group commands

get_gradient() → bool

```
# SCPI: TEST:PIXel:GRADient
value: bool = driver.test.pixel.get_gradient()
```

Activates the gradient for display screen test.

return

pix_test_grad_stat: 1| ON| 0| OFF

get_point_size() → int

```
# SCPI: TEST:PIXel:POINtsize
value: int = driver.test.pixel.get_point_size()
```

Sets the point size of the test text.

return

pix_test_grad_stat: integer Range: 0 to 999

get_rgba() → List[int]

```
# SCPI: TEST:PIXel:RGBA
value: List[int] = driver.test.pixel.get_rgba()
```

Sets a specific RGBA color for the screen.

return

pixel_test_rgba: No help available

get_text() → bool

```
# SCPI: TEST:PIXel:TEXT
value: bool = driver.test.pixel.get_text()
```

Activats the test text mode.

```
return
    pix_test_grad_stat: 1| ON| 0| OFF
```

set_color(*pix_test_color: PixelTestPredefined*) → None

```
# SCPI: TEST:PIXel:COLor
driver.test.pixel.set_color(pix_test_color = enums.PixelTestPredefined.AUTO)
```

Selects the color of the screen. 'AUTO' switches from one color to the next in tme intervals of approximately 3 s per color.

```
param pix_test_color
    RED| BLUE| WHITE| GREen| AUTO| GR25| GR50| GR75| BLACK
```

set_gradient(*pix_test_grad_stat: bool*) → None

```
# SCPI: TEST:PIXel:GRADient
driver.test.pixel.set_gradient(pix_test_grad_stat = False)
```

Activates the gradient for display screen test.

```
param pix_test_grad_stat
    1| ON| 0| OFF
```

set_point_size(*pix_test_grad_stat: int*) → None

```
# SCPI: TEST:PIXel:POINTsize
driver.test.pixel.set_point_size(pix_test_grad_stat = 1)
```

Sets the point size of the test text.

```
param pix_test_grad_stat
    integer Range: 0 to 999
```

set_rgba(*pixel_test_rgba: List[int]*) → None

```
# SCPI: TEST:PIXel:RGBA
driver.test.pixel.set_rgba(pixel_test_rgba = [1, 2, 3])
```

Sets a specific RGBA color for the screen.

```
param pixel_test_rgba
    No help available
```

set_text(*pix_test_grad_stat: bool*) → None

```
# SCPI: TEST:PIXel:TEXT
driver.test.pixel.set_text(pix_test_grad_stat = False)
```

Activats the test text mode.

```
param pix_test_grad_stat
    1| ON| 0| OFF
```

set_window(*pix_test_window: bool*) → None

```
# SCPI: TEST:PIXel:WINDow
driver.test.pixel.set_window(pix_test_window = False)
```

Activates the check display screen.

param pix_test_window
1| ON| 0| OFF

6.19.4 Remote

class RemoteCls

Remote commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.test.remote.clone()
```

Subgroups

6.19.4.1 Lockout

SCPI Command :

```
TEST<HW>:REMOte:LOCKout:[STATe]
```

class LockoutCls

Lockout commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set_state(*state: bool*) → None

```
# SCPI: TEST<HW>:REMOte:LOCKout:[STATe]
driver.test.remote.lockout.set_state(state = False)
```

No command help available

param state
No help available

6.19.5 Res

SCPI Commands :

```
TEST:RES:COLor
TEST:RES:TEXT
TEST:RES:WIND
```

class ResCls

Res commands group definition. 3 total commands, 0 Subgroups, 3 group commands

get_color() → Colour

```
# SCPI: TEST:RES:COLor
value: enums.Colour = driver.test.res.get_color()
```

No command help available

```
return
    color: No help available
```

get_text() → str

```
# SCPI: TEST:RES:TEXT
value: str = driver.test.res.get_text()
```

No command help available

```
return
    text: No help available
```

get_wind() → bool

```
# SCPI: TEST:RES:WIND
value: bool = driver.test.res.get_wind()
```

No command help available

```
return
    state: No help available
```

set_color(color: Colour) → None

```
# SCPI: TEST:RES:COLor
driver.test.res.set_color(color = enums.Colour.GREEN)
```

No command help available

```
param color
    No help available
```

set_text(text: str) → None

```
# SCPI: TEST:RES:TEXT
driver.test.res.set_text(text = 'abc')
```

No command help available

```
param text
    No help available
```

set_wind(state: bool) → None

```
# SCPI: TEST:RES:WIND
driver.test.res.set_wind(state = False)
```

No command help available

param state
No help available

6.19.6 Serror

SCPI Command :

```
TEST:SERRor:UNSet
```

class SerrorCls

Error commands group definition. 2 total commands, 1 Subgroups, 1 group commands

set_unset(path: int) → None

```
# SCPI: TEST:SERRor:UNSet
driver.test.serror.set_unset(path = 1)
```

No command help available

param path
No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.test.serror.clone()
```

Subgroups

6.19.6.1 Set

SCPI Command :

```
TEST:SERRor:SET
```

class SetCls

Set commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(err_code: int, path: int) → None

```
# SCPI: TEST:SERRor:SET
driver.test.serror.set.set(err_code = 1, path = 1)
```

No command help available

param err_code
No help available

param path
No help available

6.19.7 Sw

class SwCls

Sw commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.test.sw.clone()
```

Subgroups

6.19.7.1 Scmd

SCPI Command :

```
TEST<HW>:SW:SCMD
```

class ScmdCls

Scmd commands group definition. 1 total commands, 0 Subgroups, 1 group commands

class ScmdStruct

Response structure. Fields:

- Scmd: str: No parameter help available
- What_Is_This: str: No parameter help available

get() → ScmdStruct

```
# SCPI: TEST<HW>:SW:SCMD
value: ScmdStruct = driver.test.sw.scmd.get()
```

No command help available

return

structure: for return value, see the help for ScmdStruct structure arguments.

set(scmd: str, what_is_this: str) → None

```
# SCPI: TEST<HW>:SW:SCMD
driver.test.sw.scmd.set(scmd = 'abc', what_is_this = 'abc')
```

No command help available

param scmd

No help available

param what_is_this

No help available

6.19.8 Write

SCPI Command :

```
TEST:WRITE:RESult
```

class WriteCls

Write commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set_result(*result: SelftLevWrite*) → None

```
# SCPI: TEST:WRITE:RESult
driver.test.write.set_result(result = enums.SelftLevWrite.CUSTOMer)
```

No command help available

param result
No help available

6.20 Unit

SCPI Commands :

```
UNIT:ANGLE
UNIT:POWer
UNIT:VELOCITY
```

class UnitCls

Unit commands group definition. 3 total commands, 0 Subgroups, 3 group commands

get_angle() → UnitAngle

```
# SCPI: UNIT:ANGLE
value: enums.UnitAngle = driver.unit.get_angle()
```

No command help available

return
angle: No help available

get_power() → UnitPower

```
# SCPI: UNIT:POWer
value: enums.UnitPower = driver.unit.get_power()
```

No command help available

return
power: No help available

get_velocity() → UnitSpeed

```
# SCPI: UNIT:VELOCITY
value: enums.UnitSpeed = driver.unit.get_velocity()
```

No command help available

return

velocity: No help available

set_angle(*angle: UnitAngle*) → None

```
# SCPI: UNIT:ANGLE
driver.unit.set_angle(angle = enums.UnitAngle.DEGree)
```

No command help available

param angle

No help available

set_power(*power: UnitPower*) → None

```
# SCPI: UNIT:POWer
driver.unit.set_power(power = enums.UnitPower.DBM)
```

No command help available

param power

No help available

set_velocity(*velocity: UnitSpeed*) → None

```
# SCPI: UNIT:VELOCITY
driver.unit.set_velocity(velocity = enums.UnitSpeed.KMH)
```

No command help available

param velocity

No help available

RSAREG800 UTILITIES

class Utilities

Common utility class. Utility functions common for all types of drivers.

Access snippet: `utils = RsAreg800.utilities`

property logger: *ScpiLogger*

Scpi Logger interface, see [here](#)

Access snippet: `logger = RsAreg800.utilities.logger`

property driver_version: `str`

Returns the instrument driver version.

property idn_string: `str`

Returns instrument's identification string - the response on the SCPI command `*IDN?`

property manufacturer: `str`

Returns manufacturer of the instrument.

property full_instrument_model_name: `str`

Returns the current instrument's full name e.g. 'FSW26'.

property instrument_model_name: `str`

Returns the current instrument's family name e.g. 'FSW'.

property supported_models: `List[str]`

Returns a list of the instrument models supported by this instrument driver.

property instrument_firmware_version: `str`

Returns instrument's firmware version.

property instrument_serial_number: `str`

Returns instrument's serial_number.

query_opc(*timeout: int = 0*) → `int`

SCPI command: `*OPC?` Queries the instrument's OPC bit and hence it waits until the instrument reports operation complete. If you define `timeout > 0`, the VISA timeout is set to that value just for this method call.

property instrument_status_checking: `bool`

Sets / returns Instrument Status Checking. When True (default is True), all the driver methods and properties are sending "SYSTem:ERRor?" at the end to immediately react on error that might have occurred. We recommend to keep the state checking ON all the time. Switch it OFF only in rare cases when you require maximum speed. The default state after initializing the session is ON.

property encoding: str

Returns string<=>bytes encoding of the session.

property opc_query_after_write: bool

Sets / returns Instrument *OPC? query sending after each command write. When True, (default is False) the driver sends *OPC? every time a write command is performed. Use this if you want to make sure your sequence is performed command-after-command.

property bin_float_numbers_format: BinFloatFormat

Sets / returns format of float numbers when transferred as binary data.

property bin_int_numbers_format: BinIntFormat

Sets / returns format of integer numbers when transferred as binary data.

clear_status() → None

Clears instrument's status system, the session's I/O buffers and the instrument's error queue.

query_all_errors() → List[str]

Queries and clears all the errors from the instrument's error queue. The method returns list of strings as error messages. If no error is detected, the return value is None. The process is: querying 'SYSTEM:ERRor?' in a loop until the error queue is empty. If you want to include the error codes, call the query_all_errors_with_codes()

query_all_errors_with_codes() → List[Tuple[int, str]]

Queries and clears all the errors from the instrument's error queue. The method returns list of tuples (code: int, message: str). If no error is detected, the return value is None. The process is: querying 'SYSTEM:ERRor?' in a loop until the error queue is empty.

property instrument_options: List[str]

Returns all the instrument options. The options are sorted in the ascending order starting with K-options and continuing with B-options.

reset() → None

SCPI command: *RST Sends *RST command + calls the clear_status().

default_instrument_setup() → None

Custom steps performed at the init and at the reset().

self_test(timeout: int = None) → Tuple[int, str]

SCPI command: *TST? Performs instrument's self-test. Returns tuple (code:int, message: str). Code 0 means the self-test passed. You can define the custom timeout in milliseconds. If you do not define it, the default selftest timeout is used (usually 60 secs).

is_connection_active() → bool

Returns true, if the VISA connection is active and the communication with the instrument still works.

reconnect(force_close: bool = False) → bool

If the connection is not active, the method tries to reconnect to the device. If the connection is active, and force_close is False, the method does nothing. If the connection is active, and force_close is True, the method closes, and opens the session again. Returns True, if the reconnection has been performed.

property resource_name: int

Returns the resource name used in the constructor

property opc_timeout: int

Sets / returns timeout in milliseconds for all the operations that use OPC synchronization.

property visa_timeout: int

Sets / returns visa IO timeout in milliseconds.

property data_chunk_size: int

Sets / returns the maximum size of one block transferred during write/read operations

property visa_manufacturer: int

Returns the manufacturer of the current VISA session.

process_all_commands() → None

SCPI command: ***WAI** Stops further commands processing until all commands sent before ***WAI** have been executed.

write_str(cmd: str) → None

Writes the command to the instrument.

write(cmd: str) → None

This method is an alias to the write_str(). Writes the command to the instrument as string.

write_int(cmd: str, param: int) → None

Writes the command to the instrument followed by the integer parameter: e.g.: cmd = 'SELECT:INPUT' param = '2', result command = 'SELECT:INPUT 2'

write_int_with_opc(cmd: str, param: int, timeout: int = None) → None

Writes the command with OPC to the instrument followed by the integer parameter: e.g.: cmd = 'SELECT:INPUT' param = '2', result command = 'SELECT:INPUT 2' If you do not provide timeout, the method uses current opc_timeout.

write_float(cmd: str, param: float) → None

Writes the command to the instrument followed by the boolean parameter: e.g.: cmd = 'CENTER:FREQ' param = '10E6', result command = 'CENTER:FREQ 10E6'

write_float_with_opc(cmd: str, param: float, timeout: int = None) → None

Writes the command with OPC to the instrument followed by the boolean parameter: e.g.: cmd = 'CENTER:FREQ' param = '10E6', result command = 'CENTER:FREQ 10E6' If you do not provide timeout, the method uses current opc_timeout.

write_bool(cmd: str, param: bool) → None

Writes the command to the instrument followed by the boolean parameter: e.g.: cmd = 'OUTPUT' param = 'True', result command = 'OUTPUT ON'

write_bool_with_opc(cmd: str, param: bool, timeout: int = None) → None

Writes the command with OPC to the instrument followed by the boolean parameter: e.g.: cmd = 'OUTPUT' param = 'True', result command = 'OUTPUT ON' If you do not provide timeout, the method uses current opc_timeout.

query_str(query: str) → str

Sends the query to the instrument and returns the response as string. The response is trimmed of any trailing LF characters and has no length limit.

query(query: str) → str

This method is an alias to the query_str(). Sends the query to the instrument and returns the response as string. The response is trimmed of any trailing LF characters and has no length limit.

query_bool(query: str) → bool

Sends the query to the instrument and returns the response as boolean.

query_int(*query: str*) → int

Sends the query to the instrument and returns the response as integer.

query_float(*query: str*) → float

Sends the query to the instrument and returns the response as float.

write_str_with_opc(*cmd: str, timeout: int = None*) → None

Writes the opc-synced command to the instrument. If you do not provide timeout, the method uses current `opc_timeout`.

write_with_opc(*cmd: str, timeout: int = None*) → None

This method is an alias to the `write_str_with_opc()`. Writes the opc-synced command to the instrument. If you do not provide timeout, the method uses current `opc_timeout`.

query_str_with_opc(*query: str, timeout: int = None*) → str

Sends the opc-synced query to the instrument and returns the response as string. The response is trimmed of any trailing LF characters and has no length limit. If you do not provide timeout, the method uses current `opc_timeout`.

query_with_opc(*query: str, timeout: int = None*) → str

This method is an alias to the `query_str_with_opc()`. Sends the opc-synced query to the instrument and returns the response as string. The response is trimmed of any trailing LF characters and has no length limit. If you do not provide timeout, the method uses current `opc_timeout`.

query_bool_with_opc(*query: str, timeout: int = None*) → bool

Sends the opc-synced query to the instrument and returns the response as boolean. If you do not provide timeout, the method uses current `opc_timeout`.

query_int_with_opc(*query: str, timeout: int = None*) → int

Sends the opc-synced query to the instrument and returns the response as integer. If you do not provide timeout, the method uses current `opc_timeout`.

query_float_with_opc(*query: str, timeout: int = None*) → float

Sends the opc-synced query to the instrument and returns the response as float. If you do not provide timeout, the method uses current `opc_timeout`.

write_bin_block(*cmd: str, payload: bytes*) → None

Writes all the payload as binary data block to the instrument. The binary data header is added at the beginning of the transmission automatically, do not include it in the payload!!!

query_bin_block(*query: str*) → bytes

Queries binary data block to bytes. Throws an exception if the returned data was not a binary data. Returns `data:bytes`

query_bin_block_with_opc(*query: str, timeout: int = None*) → bytes

Sends a OPC-synced query and returns binary data block to bytes. If you do not provide timeout, the method uses current `opc_timeout`.

query_bin_or_ascii_float_list(*query: str*) → List[float]

Queries a list of floating-point numbers that can be returned in ASCII format or in binary format. - For ASCII format, the list numbers are decoded as comma-separated values. - For Binary Format, the numbers are decoded based on the property `BinFloatFormat`, usually float 32-bit (FORM REAL,32).

query_bin_or_ascii_float_list_with_opc(*query: str, timeout: int = None*) → List[float]

Sends a OPC-synced query and reads a list of floating-point numbers that can be returned in ASCII format or in binary format. - For ASCII format, the list numbers are decoded as comma-separated values. - For Binary Format, the numbers are decoded based on the property `BinFloatFormat`, usually float 32-bit (FORM REAL,32). If you do not provide timeout, the method uses current `opc_timeout`.

query_bin_or_ascii_int_list(*query: str*) → List[int]

Queries a list of floating-point numbers that can be returned in ASCII format or in binary format. - For ASCII format, the list numbers are decoded as comma-separated values. - For Binary Format, the numbers are decoded based on the property BinFloatFormat, usually float 32-bit (FORM REAL,32).

query_bin_or_ascii_int_list_with_opc(*query: str, timeout: int = None*) → List[int]

Sends a OPC-synced query and reads a list of floating-point numbers that can be returned in ASCII format or in binary format. - For ASCII format, the list numbers are decoded as comma-separated values. - For Binary Format, the numbers are decoded based on the property BinFloatFormat, usually float 32-bit (FORM REAL,32). If you do not provide timeout, the method uses current `opc_timeout`.

query_bin_block_to_file(*query: str, file_path: str, append: bool = False*) → None

Queries binary data block to the provided file. If `append` is `False`, any existing file content is discarded. If `append` is `True`, the new content is added to the end of the existing file, or if the file does not exist, it is created. Throws an exception if the returned data was not a binary data. Example for transferring a file from Instrument -> PC: `query = f"MMEM:DATA? '{INSTR_FILE_PATH}'"`. Alternatively, use the dedicated methods for this purpose:

- `send_file_from_pc_to_instrument()`
- `read_file_from_instrument_to_pc()`

query_bin_block_to_file_with_opc(*query: str, file_path: str, append: bool = False, timeout: int = None*) → None

Sends a OPC-synced query and writes the returned data to the provided file. If `append` is `False`, any existing file content is discarded. If `append` is `True`, the new content is added to the end of the existing file, or if the file does not exist, it is created. Throws an exception if the returned data was not a binary data.

write_bin_block_from_file(*cmd: str, file_path: str*) → None

Writes data from the file as binary data block to the instrument using the provided command. Example for transferring a file from PC -> Instrument: `cmd = f"MMEM:DATA '{INSTR_FILE_PATH}'"`. Alternatively, use the dedicated methods for this purpose:

- `send_file_from_pc_to_instrument()`
- `read_file_from_instrument_to_pc()`

send_file_from_pc_to_instrument(*source_pc_file: str, target_instr_file: str*) → None

SCPI Command: `MMEM:DATA`

Sends file from PC to the instrument

read_file_from_instrument_to_pc(*source_instr_file: str, target_pc_file: str, append_to_pc_file: bool = False*) → None

SCPI Command: `MMEM:DATA?`

Reads file from instrument to the PC.

Set the `append_to_pc_file` to `True` if you want to append the read content to the end of the existing PC file

get_last_sent_cmd() → str

Returns the last commands sent to the instrument. Only works in simulation mode

go_to_local() → None

Puts the instrument into local state.

go_to_remote() → None

Puts the instrument into remote state.

get_lock() → RLock

Returns the thread lock for the current session.

By default:

- If you create standard new RsAreg800 instance with new VISA session, the session gets a new thread lock. You can assign it to other RsAreg800 sessions in order to share one physical instrument with a multi-thread access.
- If you create new RsAreg800 from an existing session, the thread lock is shared automatically making both instances multi-thread safe.

You can always assign new thread lock by calling `driver.utilities.assign_lock()`

assign_lock(lock: RLock) → None

Assigns the provided thread lock.

clear_lock()

Clears the existing thread lock, making the current session thread-independent from others that might share the current thread lock.

sync_from(source: Utilities) → None

Synchronises these Utils with the source.

RSAREG800 LOGGER

Check the usage in the Getting Started chapter [here](#).

class ScpiLogger

Base class for SCPI logging

mode

Sets the logging ON or OFF. Additionally, you can set the logging ON only for errors. Possible values:

- `LoggingMode.Off` - logging is switched OFF
- `LoggingMode.On` - logging is switched ON
- `LoggingMode.Errors` - logging is switched ON, but only for error entries
- `LoggingMode.Default` - sets the logging to default - the value you have set with `logger.default_mode`

default_mode

Sets / returns the default logging mode. You can recall the default mode by calling the `logger.mode = LoggingMode.Default`.

Data Type

`LoggingMode`

device_name: str

Use this property to change the resource name in the log from the default Resource Name (e.g. `TCPIP::192.168.2.101::INSTR`) to another name e.g. `'MySigGen1'`.

set_logging_target(target, console_log: bool = None, udp_log: bool = None) → None

Sets logging target - the target must implement `write()` and `flush()`. You can optionally set the console and UDP logging ON or OFF. This method switches the logging target global OFF.

get_logging_target()

Based on the `global_mode`, it returns the logging target: either the local or the global one.

set_logging_target_global(console_log: bool = None, udp_log: bool = None) → None

Sets logging target to global. The global target must be defined. You can optionally set the console and UDP logging ON or OFF.

log_to_console

Returns logging to console status.

log_to_udp

Returns logging to UDP status.

log_to_console_and_udp

Returns true, if both logging to UDP and console in are True.

info_raw(log_entry: str, add_new_line: bool = True) → None

Method for logging the raw string without any formatting.

info(start_time: datetime, end_time: datetime, log_string_info: str, log_string: str) → None

Method for logging one info entry. For binary log_string, use the info_bin()

error(start_time: datetime, end_time: datetime, log_string_info: str, log_string: str) → None

Method for logging one error entry.

set_relative_timestamp(timestamp: datetime) → None

If set, the further timestamps will be relative to the entered time.

set_relative_timestamp_now() → None

Sets the relative timestamp to the current time.

get_relative_timestamp() → datetime

Based on the global_mode, it returns the relative timestamp: either the local or the global one.

clear_relative_timestamp() → None

Clears the reference time, and the further logging continues with absolute times.

flush() → None

Flush all the entries.

log_status_check_ok

Sets / returns the current status of status checking OK. If True (default), the log contains logging of the status checking 'Status check: OK'. If False, the 'Status check: OK' is skipped - the log is more compact. Errors will still be logged.

clear_cached_entries() → None

Clears potential cached log entries. Cached log entries are generated when the Logging is ON, but no target has been defined yet.

set_format_string(value: str, line_divider: str = '\n') → None

Sets new format string and line divider. If you just want to set the line divider, set the format string value=None. The original format string is: PAD_LEFT12(%START_TIME%) PAD_LEFT25(%DEVICE_NAME%) PAD_LEFT12(%DURATION%) %LOG_STRING_INFO% %LOG_STRING%

restore_format_string() → None

Restores the original format string and the line divider to LF

abbreviated_max_len_ascii: int

Defines the maximum length of one ASCII log entry. Default value is 200 characters.

abbreviated_max_len_bin: int

Defines the maximum length of one Binary log entry. Default value is 2048 bytes.

abbreviated_max_len_list: int

Defines the maximum length of one list entry. Default value is 100 elements.

bin_line_block_size: int

Defines number of bytes to display in one line. Default value is 16 bytes.

udp_port

Returns udp logging port.

target_auto_flushing

Returns status of the auto-flushing for the logging target.

RSAREG800 EVENTS

Check the usage in the Getting Started chapter [here](#).

class Events

Common Events class. Event-related methods and properties. Here you can set all the event handlers.

property before_query_handler: Callable

Returns the handler of before_query events.

Returns

current before_query_handler

property before_write_handler: Callable

Returns the handler of before_write events.

Returns

current before_write_handler

property io_events_include_data: bool

Returns the current state of the io_events_include_data See the setter for more details.

property on_read_handler: Callable

Returns the handler of on_read events.

Returns

current on_read_handler

property on_write_handler: Callable

Returns the handler of on_write events.

Returns

current on_write_handler

sync_from(source: Events) → None

Synchronises these Events with the source.

**CHAPTER
TEN**

INDEX

INDEX

Symbols

| | | |
|--|-----|--|
| [SOURCE<HW>]:AREGenerator:CHANnel:BW, 137 | 150 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom: |
| [SOURCE<HW>]:AREGenerator:CHANnel:CATalog, 137 | 150 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom: |
| [SOURCE<HW>]:AREGenerator:CHANnel:CONDition, 139 | 151 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom: |
| [SOURCE<HW>]:AREGenerator:CHANnel:CONDition:INFO, 139 | 152 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom: |
| [SOURCE<HW>]:AREGenerator:CHANnel:ID, 137 | 153 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom: |
| [SOURCE<HW>]:AREGenerator:CHANnel:INPut:NOMGain, 140 | 154 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom: |
| [SOURCE<HW>]:AREGenerator:CHANnel:INPut:RELLevel, 140 | 155 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom: |
| [SOURCE<HW>]:AREGenerator:CHANnel:LEVel:MEASured, 141 | 156 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom: |
| [SOURCE<HW>]:AREGenerator:CHANnel:NAME, 137 | 158 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom: |
| [SOURCE<HW>]:AREGenerator:CHANnel:OPTimization:MODE, 141 | 159 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom: |
| [SOURCE<HW>]:AREGenerator:CHANnel:OUTPut:NOMGain, 142 | 160 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ATS, |
| [SOURCE<HW>]:AREGenerator:CHANnel:SYSTem:ALIGNment, 143 | 162 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNe |
| [SOURCE<HW>]:AREGenerator:CHANnel:[STATE], 137 | 164 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNe |
| [SOURCE<HW>]:AREGenerator:DLOGging:CLEar, 144 | 165 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNe |
| [SOURCE<HW>]:AREGenerator:DLOGging:DATA, 144 | 166 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNe |
| [SOURCE<HW>]:AREGenerator:DLOGging:LEVel, 144 | 168 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNe |
| [SOURCE<HW>]:AREGenerator:DLOGging:NERRor, 144 | 169 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNe |
| [SOURCE<HW>]:AREGenerator:DLOGging:NINFo, 144 | 170 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNe |
| [SOURCE<HW>]:AREGenerator:DLOGging:NWARning, 144 | 171 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CABLEcorr:CONNe |
| [SOURCE<HW>]:AREGenerator:DLOGging:SAVE, 144 | 173 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:CENTER, |
| [SOURCE<HW>]:AREGenerator:DLOGging:[STATE], 144 | 174 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ID, |
| [SOURCE<HW>]:AREGenerator:FRONTend:ANTenna:CUSTom:Import:PREdefined:CATalog, 147 | 174 | [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:RMV, |
| [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ADD, 148 | | |
| [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ALIAS, 149 | | |
| [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:ANTenna:CUSTom:Export, | | |

| | |
|---|---|
| 174 | 203 |
| [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:RTS | [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLEcorr:CONNE |
| 175 | 204 |
| [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:RX<SOURCE<HW>:AREGenerator:FRONTend:FE<CH>:CENTER, | |
| 176 | 205 |
| [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:RX<SOURCE<HW>:AREGenerator:FRONTend:FE<CH>:CONNECT, | |
| 177 | 206 |
| [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:TX<SOURCE<HW>:AREGenerator:FRONTend:FE<CH>:DISConnect, | |
| 178 | 206 |
| [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:TX<SOURCE<HW>:AREGenerator:FRONTend:FE<CH>:ID, | |
| 179 | 207 |
| [SOURCE<HW>]:AREGenerator:FRONTend:CFE<CH>:TYPE | [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:RMV, |
| 180 | 207 |
| [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ADD, [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:RTS, | |
| 181 | 208 |
| [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ALIAS | [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:RX<ST>:EFRontend |
| 181 | 209 |
| [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna | [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:RX<ST>:OTA:OFFSe |
| 182 | 210 |
| [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna | [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:STATUS, |
| 183 | 211 |
| [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna | [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:TX<ST0>:EFRonter |
| 184 | 212 |
| [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna | [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:TX<ST0>:OTA:OFFS |
| 185 | 213 |
| [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna | [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:TYPE, |
| 186 | 214 |
| [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna | [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:PREdefined |
| 186 | 214 |
| [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna | [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:LAST:FE<CH0>, |
| 187 | 215 |
| [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna | [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:LAST:QAT<CH>, |
| 188 | 216 |
| [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna | [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:LAST:QAT<CH>:ADD, |
| 190 | 217 |
| [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ANTenna | [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:LAST:QAT<CH>:ALIAS, |
| 191 | 217 |
| [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:ATS, [SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:ATS, | |
| 192 | 217 |
| [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:BW, [SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:BW, | |
| 193 | 217 |
| [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLE | [SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:CABLEcorr:CONNE |
| 195 | 218 |
| [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLE | [SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:CABLEcorr:CONNE |
| 197 | 219 |
| [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLE | [SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:CABLEcorr:CONNE |
| 198 | 219 |
| [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLE | [SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:CABLEcorr:CONNE |
| 199 | 219 |
| [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLE | [SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:CABLEcorr:CONNE |
| 201 | 220 |
| [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLE | [SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:CABLEcorr:CONNE |
| 202 | 220 |
| [SOURCE<HW>]:AREGenerator:FRONTend:FE<CH>:CABLE | [SOURCE<HW>]:AREGenerator:FRONTend:QAT<CH>:CABLEcorr:CONNE |

479

| | | | |
|-----|--|-----|--|
| 261 | [SOURCE<HW>]:AREGenerator:FRONTend:TRX<CH>:TYPE | 283 | [SOURCE<HW>]:AREGenerator:OMONitoring:[STATE], |
| 261 | [SOURCE<HW>]:AREGenerator:HIL:RATE, 262 | 283 | [SOURCE<HW>]:AREGenerator:OSETup:APPLY, 289 |
| | [SOURCE<HW>]:AREGenerator:HIL:RECeived, 262 | | [SOURCE<HW>]:AREGenerator:OSETup:BW, 289 |
| | [SOURCE<HW>]:AREGenerator:LAST:SENsOr, 263 | | [SOURCE<HW>]:AREGenerator:OSETup:BW:APPLY, |
| | [SOURCE<HW>]:AREGenerator:MAPPING<CH>:ADJust:ALL, | 290 | [SOURCE<HW>]:AREGenerator:OSETup:HIL:UPD, 291 |
| 264 | [SOURCE<HW>]:AREGenerator:MAPPING<CH>:ADJust:LEVEL, 264 | | [SOURCE<HW>]:AREGenerator:OSETup:HOSTName, |
| 265 | [SOURCE<HW>]:AREGenerator:MAPPING<CH>:ADJust:LEVEL, 265 | 285 | [SOURCE<HW>]:AREGenerator:OSETup:IPAddress, |
| | [SOURCE<HW>]:AREGenerator:MAPPING<CH>:ADJust:LEVEL, 266 | 285 | [SOURCE<HW>]:AREGenerator:OSETup:MODE, 285 |
| | [SOURCE<HW>]:AREGenerator:MAPPING<CH>:PSENsOr, 266 | | [SOURCE<HW>]:AREGenerator:OSETup:MULTIinstrument:CONNECT, |
| | [SOURCE<HW>]:AREGenerator:MAPPING<CH>:SENsOr, | 293 | [SOURCE<HW>]:AREGenerator:OSETup:MULTIinstrument:MODE, |
| 267 | [SOURCE<HW>]:AREGenerator:MAPPING<CH>:[SUBChannel<ST>]ADJust:LEVEL, | | [SOURCE<HW>]:AREGenerator:OSETup:MULTIinstrument:PRIMARY, |
| 269 | [SOURCE<HW>]:AREGenerator:MAPPING<CH>:[SUBChannel<ST>]ADJust:LEVEL, | | [SOURCE<HW>]:AREGenerator:OSETup:MULTIinstrument:REMOve:EX |
| 269 | [SOURCE<HW>]:AREGenerator:MARKer:OBJect:DELAy, | 294 | [SOURCE<HW>]:AREGenerator:OSETup:MULTIinstrument:SECOndary |
| 271 | [SOURCE<HW>]:AREGenerator:MARKer:OBJect:ONTime, | 294 | [SOURCE<HW>]:AREGenerator:OSETup:MULTIinstrument:SECOndary |
| 271 | [SOURCE<HW>]:AREGenerator:MARKer:OBJect:SOURCE, | 296 | [SOURCE<HW>]:AREGenerator:OSETup:MULTIinstrument:SECOndary |
| | [SOURCE<HW>]:AREGenerator:MEASurement:KEEPsettings, | 296 | [SOURCE<HW>]:AREGenerator:OSETup:MULTIinstrument:SECOndary |
| 273 | [SOURCE<HW>]:AREGenerator:OBJect:ALL:[STATE], | 297 | [SOURCE<HW>]:AREGenerator:OSETup:MULTIinstrument:SECOndary |
| 274 | [SOURCE<HW>]:AREGenerator:OBJect<CH>:[SUBChannel<ST>]ANGLE:HorizOntal, | | [SOURCE<HW>]:AREGenerator:OSETup:MULTIinstrument:SECOndary |
| 275 | [SOURCE<HW>]:AREGenerator:OBJect<CH>:[SUBChannel<ST>]ANGLE:HorizOntal, | | [SOURCE<HW>]:AREGenerator:OSETup:MULTIinstrument:SECOndary |
| | [SOURCE<HW>]:AREGenerator:OBJect<CH>:[SUBChannel<ST>]ATTenuation, | | [SOURCE<HW>]:AREGenerator:OSETup:PORT, 285 |
| 276 | [SOURCE<HW>]:AREGenerator:OBJect<CH>:[SUBChannel<ST>]ATTenuation, | | [SOURCE<HW>]:AREGenerator:OSETup:PROTOcol, |
| | [SOURCE<HW>]:AREGenerator:OBJect<CH>:[SUBChannel<ST>]ATTenuation, | 285 | [SOURCE<HW>]:AREGenerator:OSETup:REFERENCE, |
| 277 | [SOURCE<HW>]:AREGenerator:OBJect<CH>:[SUBChannel<ST>]ATTenuation, | 285 | [SOURCE<HW>]:AREGenerator:OSETup:SOURCE, 285 |
| 278 | [SOURCE<HW>]:AREGenerator:OBJect<CH>:[SUBChannel<ST>]ATTenuation, | | [SOURCE<HW>]:AREGenerator:OSETup:SWUNit:[STATE], |
| 279 | [SOURCE<HW>]:AREGenerator:OBJect<CH>:[SUBChannel<ST>]ATTenuation, | 285 | [SOURCE<HW>]:AREGenerator:OSETup:TBASe, 285 |
| | [SOURCE<HW>]:AREGenerator:OBJect<CH>:[SUBChannel<ST>]ATTenuation, | | [SOURCE<HW>]:AREGenerator:RADar:BASE:ATTenuation, |
| 280 | [SOURCE<HW>]:AREGenerator:OBJect<CH>:[SUBChannel<ST>]ATTenuation, | 299 | [SOURCE<HW>]:AREGenerator:RADar:LSENSitivity, |
| | [SOURCE<HW>]:AREGenerator:OBJect<CH>:[SUBChannel<ST>]ATTenuation, | 299 | [SOURCE<HW>]:AREGenerator:RADar:POWER:INDicator, |
| 281 | [SOURCE<HW>]:AREGenerator:OBJects:INValid, | 300 | [SOURCE<HW>]:AREGenerator:SCENario:FILE, 303 |
| 282 | [SOURCE<HW>]:AREGenerator:OBJects:INValid:CATalog, | | [SOURCE<HW>]:AREGenerator:SCENario:FILE:CATalog, |
| 282 | [SOURCE<HW>]:AREGenerator:OBJects:VALId, 283 | 303 | [SOURCE<HW>]:AREGenerator:SCENario:PAUSE, 303 |
| | [SOURCE<HW>]:AREGenerator:OBJects:VALId:CATalog, | | [SOURCE<HW>]:AREGenerator:SCENario:POSition:ACTual, |
| 283 | [SOURCE<HW>]:AREGenerator:OMONitoring:HOSTName | | [SOURCE<HW>]:AREGenerator:SCENario:POSition:ACTual, |
| 283 | [SOURCE<HW>]:AREGenerator:OMONitoring:PORT, | 304 | |

[SOURCE<HW>]:AREGenerator:SCENario:POSITION:STOP, 304
 [SOURCE<HW>]:AREGenerator:SCENario:POSITION:STOP, 304
 [SOURCE<HW>]:AREGenerator:SCENario:PROGress, 300
 [SOURCE<HW>]:AREGenerator:SCENario:REPLay:[MODE], 305
 [SOURCE<HW>]:AREGenerator:SCENario:RESet, 300
 [SOURCE<HW>]:AREGenerator:SCENario:START, 300
 [SOURCE<HW>]:AREGenerator:SCENario:STATUS, 300
 [SOURCE<HW>]:AREGenerator:SCENario:STOP, 300
 [SOURCE<HW>]:AREGenerator:SENSor<CH>:ADD, 306
 [SOURCE<HW>]:AREGenerator:SENSor<CH>:ALias, 307
 [SOURCE<HW>]:AREGenerator:SENSor<CH>:ANGLE, 307
 [SOURCE<HW>]:AREGenerator:SENSor<CH>:BW, 308
 [SOURCE<HW>]:AREGenerator:SENSor<CH>:CENTer, 309
 [SOURCE<HW>]:AREGenerator:SENSor<CH>:CFACtor, 310
 [SOURCE<HW>]:AREGenerator:SENSor<CH>:COUNT, 310
 [SOURCE<HW>]:AREGenerator:SENSor<CH>:DISTance, 311
 [SOURCE<HW>]:AREGenerator:SENSor<CH>:DYNamic:ID, 312
 [SOURCE<HW>]:AREGenerator:SENSor<CH>:ID, 313
 [SOURCE<HW>]:AREGenerator:SENSor<CH>:RMV, 313
 [SOURCE<HW>]:AREGenerator:SWUNit:CABLEcorr:CONNECTor<DI>:RX<ST>:MODE, 317
 [SOURCE<HW>]:AREGenerator:SWUNit:CABLEcorr:CONNECTor<DI>:RX<ST>:MODE, 318
 [SOURCE<HW>]:AREGenerator:SWUNit:CABLEcorr:CONNECTor<DI>:RX<ST>:MODE, 319
 [SOURCE<HW>]:AREGenerator:SWUNit:CABLEcorr:CONNECTor<DI>:RX<ST>:MODE, 320
 [SOURCE<HW>]:AREGenerator:SWUNit:CABLEcorr:CONNECTor<DI>:RX<ST>:MODE, 321
 [SOURCE<HW>]:AREGenerator:SWUNit:CABLEcorr:CONNECTor<DI>:TX<STO>:USER:ATTenuation, 323
 [SOURCE<HW>]:AREGenerator:SWUNit:CABLEcorr:CONNECTor<DI>:TX<STO>:USER:DEFault, 324
 [SOURCE<HW>]:AREGenerator:SWUNit:CABLEcorr:CONNECTor<DI>:TX<STO>:USER:FILE, 325
 [SOURCE<HW>]:AREGenerator:SWUNit:CONNECT, 326
 [SOURCE<HW>]:AREGenerator:SWUNit:DISConnect, 326
 [SOURCE<HW>]:AREGenerator:SWUNit:HOSTName, 314
 [SOURCE<HW>]:AREGenerator:SWUNit:MAPPING<CH>:[SUBChannel<ST>]:CONFIG, 328

[SOURCE<HW>]:AREGenerator:SWUNit:RX, 314
 [SOURCE<HW>]:AREGenerator:SWUNit:STATUS, 314
 [SOURCE<HW>]:AREGenerator:SWUNit:TX, 314
 [SOURCE<HW>]:AREGenerator:UNITs:ANGLE, 329
 [SOURCE<HW>]:AREGenerator:UNITs:C, 329
 [SOURCE<HW>]:AREGenerator:UNITs:DOPPler, 329
 [SOURCE<HW>]:AREGenerator:UNITs:KCONstant, 329
 [SOURCE<HW>]:AREGenerator:UNITs:RANGe, 329
 [SOURCE<HW>]:AREGenerator:UNITs:RCS, 329
 [SOURCE<HW>]:AREGenerator:UNITs:SHIFt, 329
 [SOURCE<HW>]:AREGenerator:UNITs:SPEEd, 329
 [SOURCE<HW>]:MODulation:[ALL]:[STATE], 337
 [SOURCE<HW>]:POWER:SPC:MEASure, 340
 [SOURCE<HW>]:POWER:SPC:SINGLe, 340
 [SOURCE<HW>]:POWER:[LEVel]:[IMMediate]:RCL, 339
 [SOURCE]:BB:PATH:COUNT, 332
 [SOURCE]:INPut:TRIGger:SLOPe, 333
 [SOURCE]:INPut:USER:CLOCK:IMPedance, 334
 [SOURCE]:INPut:USER:CLOCK:LEVel, 334
 [SOURCE]:INPut:USER:CLOCK:SLOPe, 334
 [SOURCE]:INPut:USER:TRIGger:IMPedance, 336
 [SOURCE]:INPut:USER:TRIGger:LEVel, 336
 [SOURCE]:INPut:USER:TRIGger:SLOPe, 336
 [SOURCE]:INPut:USER<CH>:DIRection, 335
 [SOURCE]:PATH:COUNT, 338
 [SOURCE]:ROSCillator:EXTernal:FREQuency, 342
 [SOURCE]:ROSCillator:EXTernal:RFOFF:[STATE], 343
 [SOURCE]:ROSCillator:EXTernal:SBANDwidth, 342
 [SOURCE]:ROSCillator:EXTernal:SENFREQuency:MODE, 345
 [SOURCE]:ROSCillator:EXTernal:SENFREQuency, 341
 [SOURCE]:ROSCillator:SOURCE, 341
 [SOURCE]:ROSCillator:USER:DEFault, 344
 [SOURCE]:ROSCillator:USER:FILE, 344
 [SOURCE]:ROSCillator:USER:INTERNAL]:ADJust:VALUE, 344
 [SOURCE]:ROSCillator:USER:INTERNAL]:ADJust:[STATE], 344
 [SOURCE]:ROSCillator:MODE, 344

Abbreviated_max_len_list (ScpiLogger attribute), 472
 abbreviated_max_len_list (ScpiLogger attribute), 472
 abbreviated_max_len_list (ScpiLogger attribute), 472
 abbreviated_max_len_list (ScpiLogger attribute), 472
 bin_line_block_size (ScpiLogger attribute), 472

C

CALibration:ALL:[MEASure], 56
 CALibration:DATA:EXPort, 56
 CALibration:DATA:FACTory:DATE, 57
 CALibration:DElay:MINutes, 59
 CALibration:DElay:SHUTdown:[STATe], 60
 CALibration:DElay:[MEASure], 59
 CALibration:FREquency:SWPoints, 60
 CALibration:ROSCillator:DATA:MODE, 62
 CALibration:ROSCillator:STORE, 63
 CALibration:ROSCillator:[DATA], 62
 CALibration:SElected:[MEASure], 64
 CALibration:TSElected:CATalog, 64
 CALibration:TSElected:STEP, 64
 CALibration:TSElected:[MEASure], 64
 CALibration<HW>:ALL:DATE, 55
 CALibration<HW>:ALL:INformation, 55
 CALibration<HW>:ALL:TEMP, 55
 CALibration<HW>:ALL:TIME, 55
 CALibration<HW>:CONTInueonerror, 54
 CALibration<HW>:DATA:UPDate, 57
 CALibration<HW>:DATA:UPDate:LEVel:FORCe, 58
 CALibration<HW>:DEBug, 54
 CALibration<HW>:LEVel:ATTenuator:STAGe, 61
 CALibration<HW>:LEVel:STATe, 61
 clear_cached_entries() (*ScpiLogger method*), 472
 clear_relative_timestamp() (*ScpiLogger method*), 472

D

default_mode (*ScpiLogger attribute*), 471
 DEvice:PRESet, 65
 DEvice:SETTings:BACKup, 66
 DEvice:SETTings:REStore, 67
 device_name (*ScpiLogger attribute*), 471
 DIAgnostic:INFO:OTIME, 73
 DIAgnostic:INFO:OTIME:SET, 73
 DIAgnostic:INFO:POCount, 74
 DIAgnostic:INFO:POCount:SET, 74
 DIAgnostic:SErvice, 77
 DIAgnostic<HW>:BGInfo, 68
 DIAgnostic<HW>:BGInfo:CATalog, 68
 DIAgnostic<HW>:DEBug:PAGE, 69
 DIAgnostic<HW>:DEBug:PAGE:CATalog, 69
 DIAgnostic<HW>:EEPRom<CH>:BIDentifier:CATalog, 71
 DIAgnostic<HW>:EEPRom<CH>:CUSTomize, 71
 DIAgnostic<HW>:EEPRom<CH>:DATA:POINts, 72
 DIAgnostic<HW>:EEPRom<CH>:DELeTe, 70
 DIAgnostic<HW>:POINt:CATalog, 75
 DIAgnostic<HW>:POINt:CONFIguration, 76
 DIAgnostic<HW>:SErvice:SFUNction, 77
 DIAgnostic<HW>:[MEASure]:POINt, 75
 DISPlay:ANNotation:[ALL], 79

DISPlay:BRIGhtness, 78
 DISPlay:BUTTon:BRIGhtness, 79
 DISPlay:DIALog:CLOSe, 80
 DISPlay:DIALog:CLOSe:ALL, 80
 DISPlay:DIALog:ID, 80
 DISPlay:DIALog:OPEN, 80
 DISPlay:FOCusobject, 78
 DISPlay:MESSage, 78
 DISPlay:PSAVe:HOLDoff, 81
 DISPlay:PSAVe:[STATe], 81
 DISPlay:TOUCH:TIME:CHARGe, 83
 DISPlay:UKEY:ADD, 84
 DISPlay:UKEY:NAME, 83
 DISPlay:UKEY:SCPI, 83
 DISPlay:UPDate:HOLD, 84
 DISPlay:UPDate:[STATe], 84

E

error() (*ScpiLogger method*), 472

F

flush() (*ScpiLogger method*), 472
 FORMat:BORDer, 85
 FORMat:SREGister, 85
 FORMat:[DATA], 85
 FPANel:KEYBoard:LAYout, 87

G

get_logging_target() (*ScpiLogger method*), 471
 get_relative_timestamp() (*ScpiLogger method*), 472

H

HCOPy:DATA, 88
 HCOPy:DEvice:LANGUage, 89
 HCOPy:FILE:[NAME], 90
 HCOPy:FILE:[NAME]:AUTO, 91
 HCOPy:FILE:[NAME]:AUTO:DIRectory, 92
 HCOPy:FILE:[NAME]:AUTO:DIRectory:CLEar, 92
 HCOPy:FILE:[NAME]:AUTO:FILE, 93
 HCOPy:FILE:[NAME]:AUTO:STATe, 91
 HCOPy:FILE:[NAME]:AUTO:[FILE]:DAY:STATe, 94
 HCOPy:FILE:[NAME]:AUTO:[FILE]:MONTH:STATe, 94
 HCOPy:FILE:[NAME]:AUTO:[FILE]:NUMBer, 93
 HCOPy:FILE:[NAME]:AUTO:[FILE]:PREfix, 95
 HCOPy:FILE:[NAME]:AUTO:[FILE]:PREfix:STATe, 95
 HCOPy:FILE:[NAME]:AUTO:[FILE]:YEAR:STATe, 96
 HCOPy:IMAGe:FORMat, 96
 HCOPy:REGion, 88
 HCOPy:[EXECute], 89

I

info() (*ScpiLogger method*), 472

info_raw() (*ScpiLogger method*), 471
 INITiate<HW>:[POWER]:CONTInuous, 98

K

KBOard:LAYout, 99

L

log_status_check_ok (*ScpiLogger attribute*), 472
 log_to_console (*ScpiLogger attribute*), 471
 log_to_console_and_udp (*ScpiLogger attribute*), 471
 log_to_udp (*ScpiLogger attribute*), 471

M

MEMory:HFRee, 106
 MMEMory:CATalog, 102
 MMEMory:CATalog:LENGth, 103
 MMEMory:CDIRectory, 99
 MMEMory:COPIY, 99
 MMEMory:DCATalog, 103
 MMEMory:DCATalog:LENGth, 104
 MMEMory:DELeTe, 99
 MMEMory:DRIVes, 99
 MMEMory:LOAD:STATe, 105
 MMEMory:MDIRectory, 99
 MMEMory:MOVE, 99
 MMEMory:MSIS, 99
 MMEMory:RDIRectory, 99
 MMEMory:RDIRectory:RECURSive, 99
 MMEMory:STORE:STATe, 105
 mode (*ScpiLogger attribute*), 471

O

OUTPut<HW>:USER<CH>:DIRectIon, 107
 OUTPut<HW>:USER<CH>:SIGNal, 108

R

READ<CH>:[POWER], 109
 restore_format_string() (*ScpiLogger method*), 472

S

ScpiLogger (*class in RsAreg800.Internal.ScpiLogger*), 471
 SENSE<CH>:UNIT:[POWER], 130
 SENSE<CH>:[POWER]:APERture:DEFault:STATe, 111
 SENSE<CH>:[POWER]:APERture:TIME, 112
 SENSE<CH>:[POWER]:CORRection:SPDevice:LIST, 113
 SENSE<CH>:[POWER]:CORRection:SPDevice:SELeCT, 113
 SENSE<CH>:[POWER]:CORRection:SPDevice:STATe, 114
 SENSE<CH>:[POWER]:DIRect, 115
 SENSE<CH>:[POWER]:DISPlay:PERManent:PRIority, 116
 SENSE<CH>:[POWER]:DISPlay:PERManent:STATe, 117
 SENSE<CH>:[POWER]:FILTer:LENGth:AUTO, 118
 SENSE<CH>:[POWER]:FILTer:LENGth:[USER], 119
 SENSE<CH>:[POWER]:FILTer:NSRatio, 120
 SENSE<CH>:[POWER]:FILTer:NSRatio:MTIME, 121
 SENSE<CH>:[POWER]:FILTer:SONCe, 121
 SENSE<CH>:[POWER]:FILTer:TYPE, 122
 SENSE<CH>:[POWER]:FREQuency, 123
 SENSE<CH>:[POWER]:LOGGing:STATe, 124
 SENSE<CH>:[POWER]:OFFSet, 125
 SENSE<CH>:[POWER]:OFFSet:STATe, 126
 SENSE<CH>:[POWER]:SNUMber, 126
 SENSE<CH>:[POWER]:SOURce, 127
 SENSE<CH>:[POWER]:STATus:[DEVice], 128
 SENSE<CH>:[POWER]:SVERsion, 128
 SENSE<CH>:[POWER]:TYPE, 129
 SENSE<CH>:[POWER]:ZERO, 129
 set_format_string() (*ScpiLogger method*), 472
 set_logging_target() (*ScpiLogger method*), 471
 set_logging_target_global() (*ScpiLogger method*), 471
 set_relative_timestamp() (*ScpiLogger method*), 472
 set_relative_timestamp_now() (*ScpiLogger method*), 472
 SLISt:CLEar:LAN, 132
 SLISt:CLEar:USB, 133
 SLISt:CLEar:[ALL], 131
 SLISt:ELEMent<CH>:MAPPING, 134
 SLISt:SCAN:LENSor, 134
 SLISt:SCAN:USENSor, 135
 SLISt:SCAN:[STATe], 134
 SLISt:SENSor:MAP, 136
 SLISt:[LIST], 131
 SOURce<HW>:AREGenerator:OSETup:CONFIg, 285
 SOURce<HW>:PRESet, 136
 STATus:OPERation:BIT<BITNR>:CONDition, 350
 STATus:OPERation:BIT<BITNR>:ENABle, 350
 STATus:OPERation:BIT<BITNR>:NTRAnsition, 351
 STATus:OPERation:BIT<BITNR>:PTRAnsition, 352
 STATus:OPERation:BIT<BITNR>:[EVENT], 351
 STATus:OPERation:CONDition, 347
 STATus:OPERation:ENABle, 347
 STATus:OPERation:NTRAnsition, 347
 STATus:OPERation:PTRAnsition, 347
 STATus:OPERation:[EVENT], 347
 STATus:PRESet, 346
 STATus:QUEStionable:BIT<BITNR>:CONDition, 355
 STATus:QUEStionable:BIT<BITNR>:ENABle, 356
 STATus:QUEStionable:BIT<BITNR>:NTRAnsition, 357

STATUS:QUESTIONable:BIT<BITNR>:PTRansition, 358
 STATUS:QUESTIONable:BIT<BITNR>:[EVENT], 357
 STATUS:QUESTIONable:CONDition, 353
 STATUS:QUESTIONable:ENABle, 353
 STATUS:QUESTIONable:NTRansition, 353
 STATUS:QUESTIONable:PTRansition, 353
 STATUS:QUESTIONable:[EVENT], 353
 STATUS:QUEue:[NEXT], 358
 SYSTem:BEEPer:STATe, 365
 SYSTem:BIOS:VERSion, 366
 SYSTem:COMMunicate:GPIB:LTERminator, 367
 SYSTem:COMMunicate:GPIB:RESourCe, 367
 SYSTem:COMMunicate:GPIB:[SELF]:ADDReSS, 368
 SYSTem:COMMunicate:HISLip:RESourCe, 368
 SYSTem:COMMunicate:NETWork:IPADdress, 371
 SYSTem:COMMunicate:NETWork:IPADdress:MODE, 371
 SYSTem:COMMunicate:NETWork:MACAddress, 369
 SYSTem:COMMunicate:NETWork:RESourCe, 369
 SYSTem:COMMunicate:NETWork:REStArT, 373
 SYSTem:COMMunicate:NETWork:STATus, 369
 SYSTem:COMMunicate:NETWork:[COMMON]:DOMain, 370
 SYSTem:COMMunicate:NETWork:[COMMON]:HOSTname, 370
 SYSTem:COMMunicate:NETWork:[COMMON]:WORKgrouP, 370
 SYSTem:COMMunicate:NETWork:[IPADdress]:DNS, 371
 SYSTem:COMMunicate:NETWork:[IPADdress]:GATeway, 371
 SYSTem:COMMunicate:NETWork:[IPADdress]:SUBNet:MASK, 373
 SYSTem:COMMunicate:RT:NETWork:IPADdress, 376
 SYSTem:COMMunicate:RT:NETWork:IPADdress:MODE, 376
 SYSTem:COMMunicate:RT:NETWork:MACAddress, 374
 SYSTem:COMMunicate:RT:NETWork:REStArT, 378
 SYSTem:COMMunicate:RT:NETWork:STATus, 374
 SYSTem:COMMunicate:RT:NETWork:[COMMON]:HOSTname, 375
 SYSTem:COMMunicate:RT:NETWork:[COMMON]:WORKgrouP, 375
 SYSTem:COMMunicate:RT:NETWork:[IPADdress]:SUBNet:MASK, 377
 SYSTem:COMMunicate:SCPI:ETHerNet:[ACTive], 379
 SYSTem:COMMunicate:SERial:BAUD, 379
 SYSTem:COMMunicate:SERial:PARity, 379
 SYSTem:COMMunicate:SERial:RESourCe, 379
 SYSTem:COMMunicate:SERial:SBITs, 379
 SYSTem:COMMunicate:SOCKeT:RESourCe, 381
 SYSTem:COMMunicate:SYST:NETWork:IPADdress, 383
 SYSTem:COMMunicate:SYST:NETWork:IPADdress:MODE, 383
 SYSTem:COMMunicate:SYST:NETWork:MACAddress, 381
 SYSTem:COMMunicate:SYST:NETWork:REStArT, 385
 SYSTem:COMMunicate:SYST:NETWork:STATus, 381
 SYSTem:COMMunicate:SYST:NETWork:[COMMON]:HOSTname, 382
 SYSTem:COMMunicate:SYST:NETWork:[COMMON]:WORKgrouP, 382
 SYSTem:COMMunicate:SYST:NETWork:[IPADdress]:SUBNet:MASK, 384
 SYSTem:COMMunicate:USB:RESourCe, 385
 SYSTem:CRASH, 359
 SYSTem:DATE, 386
 SYSTem:DATE:LOCAl, 386
 SYSTem:DATE:UTC, 386
 SYSTem:DEVice:ID, 387
 SYSTem:DEXChange:CATalog, 389
 SYSTem:DEXChange:DEBUg, 389
 SYSTem:DEXChange:DELeTe, 389
 SYSTem:DEXChange:EXECute, 391
 SYSTem:DEXChange:FORMAt, 389
 SYSTem:DEXChange:SELeCt, 389
 SYSTem:DEXChange:TEMPLate:PREDeFined:CATalog, 392
 SYSTem:DEXChange:TEMPLate:PREDeFined:SELeCt, 392
 SYSTem:DEXChange:TEMPLate:USER:CATalog, 392
 SYSTem:DEXChange:TEMPLate:USER:DELeTe, 392
 SYSTem:DEXChange:TEMPLate:USER:SELeCt, 392
 SYSTem:DEXChange:TRANsaction:STATe, 393
 SYSTem:DFPPrint, 388
 SYSTem:DFPPrint:HISTory:COUNT, 388
 SYSTem:DFPPrint:HISTory:ENTRy, 388
 SYSTem:DID, 359
 SYSTem:ERRor:ALL, 394
 SYSTem:ERRor:CODE:ALL, 395
 SYSTem:ERRor:CODE:[NEXT], 395
 SYSTem:ERRor:COUNT, 394
 SYSTem:ERRor:HISTory, 396
 SYSTem:ERRor:HISTory:CLEAr, 396
 SYSTem:ERRor:STATIC, 394
 SYSTem:EXTDevices:UPDate, 397
 SYSTem:EXTDevices:UPDate:CHECk, 397
 SYSTem:EXTDevices:UPDate:NEEDed:[STATe], 398
 SYSTem:EXTDevices:UPDate:TSELeCted:CATalog, 398
 SYSTem:EXTDevices:UPDate:TSELeCted:STEP, 398
 SYSTem:FPReset, 399
 SYSTem:GENeric:MSG, 400
 SYSTem:HELp:EXPort, 400

SYSTem:HELP:HEADers, 400
 SYSTem:HELP:SYNTax, 401
 SYSTem:HELP:SYNTax:ALL, 401
 SYSTem:IDENtification, 402
 SYSTem:IDENtification:PRESet, 402
 SYSTem:IMPort, 359
 SYSTem:INFormation:SR, 403
 SYSTem:IRESponse, 359
 SYSTem:LANGuage, 359
 SYSTem:LINux:KERNel:VERsion, 403
 SYSTem:LOCK:NAME, 405
 SYSTem:LOCK:NAME:DETAiled, 405
 SYSTem:LOCK:OWNer, 405
 SYSTem:LOCK:OWNer:DETAiled, 405
 SYSTem:LOCK:RELease, 406
 SYSTem:LOCK:RELease:ALL, 406
 SYSTem:LOCK:REQuest:SHARed, 407
 SYSTem:LOCK:REQuest:[EXCLusive], 406
 SYSTem:LOCK:SHARed:STRing, 407
 SYSTem:LOCK:TIMEout, 404
 SYSTem:MMEMory:PATH, 408
 SYSTem:MMEMory:PATH:USER, 408
 SYSTem:NINformation, 359
 SYSTem:NTP:HOSTname, 409
 SYSTem:OREsponse, 359
 SYSTem:OSYStem, 359
 SYSTem:PACKage:CHARTdisplay:VERsion, 409
 SYSTem:PACKage:GUIFramework:VERsion, 410
 SYSTem:PACKage:QT:VERsion, 410
 SYSTem:PCIFpga:UPDate:CHECK, 411
 SYSTem:PCIFpga:UPDate:NEEDed:[STATe], 412
 SYSTem:PCIFpga:UPDate:TSElected:CATalog, 412
 SYSTem:PCIFpga:UPDate:TSElected:STEP, 412
 SYSTem:PRESet, 359
 SYSTem:PRESet:ALL, 359
 SYSTem:PRESet:BASE, 359
 SYSTem:PROFiling:HWACcess:DEScRiption, 414
 SYSTem:PROFiling:HWACcess:PDURation, 414
 SYSTem:PROFiling:HWACcess:STATe, 414
 SYSTem:PROFiling:LOGging:STATe, 415
 SYSTem:PROFiling:MODule:CATalog, 415
 SYSTem:PROFiling:MODule:STATe, 415
 SYSTem:PROFiling:RECORD, 416
 SYSTem:PROFiling:RECORD:CLEar, 416
 SYSTem:PROFiling:RECORD:COUNt, 417
 SYSTem:PROFiling:RECORD:COUNt:MAX, 417
 SYSTem:PROFiling:RECORD:IGNore, 416
 SYSTem:PROFiling:RECORD:SAVE, 416
 SYSTem:PROFiling:RECORD:WRAP:STATe, 418
 SYSTem:PROFiling:STATe, 413
 SYSTem:PROFiling:TICK, 419
 SYSTem:PROFiling:TICK:ENABle, 419
 SYSTem:PROFiling:TPOint:CATalog, 420
 SYSTem:PROFiling:TPOint:REStArt, 420
 SYSTem:PROTect<CH>:[STATe], 421
 SYSTem:RCL, 359
 SYSTem:REBoot, 422
 SYSTem:RESet, 359
 SYSTem:RESet:ALL, 359
 SYSTem:RESet:BASE, 359
 SYSTem:REStArt, 423
 SYSTem:SAV, 359
 SYSTem:SCRPt:ARG, 423
 SYSTem:SCRPt:CMD, 423
 SYSTem:SCRPt:DATA, 423
 SYSTem:SCRPt:DISCard, 425
 SYSTem:SCRPt:RUN, 423
 SYSTem:SECurity:MMEM:PROTect:[STATe], 427
 SYSTem:SECurity:NETWork:AVAHi:[STATe], 428
 SYSTem:SECurity:NETWork:FTP:[STATe], 429
 SYSTem:SECurity:NETWork:HTTP:[STATe], 430
 SYSTem:SECurity:NETWork:RAW:[STATe], 431
 SYSTem:SECurity:NETWork:REMSupport:[STATe], 432
 SYSTem:SECurity:NETWork:RPC:[STATe], 432
 SYSTem:SECurity:NETWork:SMB:[STATe], 433
 SYSTem:SECurity:NETWork:SOE:[STATe], 434
 SYSTem:SECurity:NETWork:SSH:[STATe], 435
 SYSTem:SECurity:NETWork:SWUPdate:[STATe], 437
 SYSTem:SECurity:NETWork:VNC:[STATe], 438
 SYSTem:SECurity:NETWork:[STATe], 436
 SYSTem:SECurity:SANitize:[STATe], 439
 SYSTem:SECurity:SUPolicy, 439
 SYSTem:SECurity:USBStorage:[STATe], 440
 SYSTem:SECurity:VOLMode:[STATe], 441
 SYSTem:SECurity:[STATe], 425
 SYSTem:SHUTdown, 442
 SYSTem:SIMulation, 359
 SYSTem:SRCat, 359
 SYSTem:SRData, 442
 SYSTem:SRData:DELeTe, 442
 SYSTem:SREStore, 359
 SYSTem:SREXec, 443
 SYSTem:SRMode, 359
 SYSTem:SRSel, 359
 SYSTem:SRTIME:STATe, 443
 SYSTem:SRTIME:SYNChronize, 444
 SYSTem:ssAVe, 359
 SYSTem:STARtup:COMPlEte, 445
 SYSTem:TIME, 445
 SYSTem:TIME:DSTIME:MODE, 447
 SYSTem:TIME:DSTIME:RULE, 448
 SYSTem:TIME:DSTIME:RULE:CATalog, 448
 SYSTem:TIME:HRTimer:ABSolute, 449
 SYSTem:TIME:HRTimer:ABSolute:SET, 449
 SYSTem:TIME:HRTimer:RELative, 449
 SYSTem:TIME:LOCAl, 445
 SYSTem:TIME:PROTocol, 445

SYSTem:TIME:UTC, 445
SYSTem:TIME:ZONE, 450
SYSTem:TIME:ZONE:CATalog, 450
SYSTem:TZONE, 359
SYSTem:ULOCK, 451
SYSTem:UNDO:HCLear, 452
SYSTem:UNDO:HID:SElect, 453
SYSTem:UNDO:HLABLE:CATalog, 453
SYSTem:UNDO:HLABLE:SElect, 453
SYSTem:UNDO:STATe, 452
SYSTem:UPTime, 359
SYSTem:VERSion, 359
SYSTem:WAIT, 359

T

target_auto_flushing (*ScpiLogger attribute*), 472
TEST:DEvice:INTernal, 456
TEST:HS, 454
TEST:LEVel, 454
TEST:NRPTriGger, 454
TEST:PIXeL:COLor, 457
TEST:PIXeL:GRADient, 457
TEST:PIXeL:POINtsize, 457
TEST:PIXeL:RGBA, 457
TEST:PIXeL:TEXT, 457
TEST:PIXeL:WINDow, 457
TEST:PRESet, 454
TEST:RES:COLor, 459
TEST:RES:TEXT, 459
TEST:RES:WIND, 459
TEST:SERRor:SET, 461
TEST:SERRor:UNSet, 461
TEST:WRITe:RESult, 463
TEST<HW>:ALL:RESult, 455
TEST<HW>:ALL:STARt, 455
TEST<HW>:REMOte:LOCKout:[STATe], 459
TEST<HW>:SW:SCMD, 462

U

udp_port (*ScpiLogger attribute*), 472
UNIT:ANGLE, 463
UNIT:POWer, 463
UNIT:VELOCITY, 463